javax.accessibility.*

Values

Methods declared in supertypes are hidden in subtypes

AccessibleAction

Accessors

String getAccessibleActionDescription(int i) int getAccessibleActionCount() boolean doAccessibleAction(inti) Other Public Methods

Object getAccessibleActionAnchor(inti) Object getAccessibleActionObject(int i)

AccessibleHyperlink

int getStartIndex () int getEndIndex() boolean is Valid ()

Accessible con

String get / setAccessibleIconDescription() int getAccessibleIconHeight() int getAccessibleIconWidth()

AccessibleKeyBinding

int getAccessibleKeyBindingCount() java.lang.Object getAccessibleKeyBinding(int i)

Accessible Value

boolean setCurrentAccessibleValue(Number n) Number get / setCurrentAccessibleValue() Number getMaximumAccessibleValue() Number getMinimumAccessibleValue()

Accessible Selection

Accessors + Collectors

int getAccessibleSelectionCount() Accessible getAccessibleSelection(int i)

void add / removeAccessibleSelection (int i) boolean isAccessibleChildSelected(inti)

void selectAllAccessibleSelection() void clearAccessibleSelection() Other Public Methods

Accessible Editable Text

String getTextRange (int startIndex, int endIndex) void setAttributes (int startIndex, int endIndex, AttributeSet as) void setTextContents (String s)

Collectors

void insertTextAtIndex(int index, Strings) void delete (int startIndex, int endIndex)

void cut (int startIndex, int endIndex) Other Public Methods

String getBeforeIndex (int part, int index)

int getCaretPosition()

int getCharCount()

AttributeSet getCharacterAttribute (int i) Rectangle getCharacterBounds(inti) int getIndexAtPoint(Point p)

String getAtIndex (int part, int index)

String getAfterIndex (int part, int index)

AccessibleText

void paste (int startIndex)

void replaceText(int startIndex, int endIndex, String s) void selectText (int startIndex, int endIndex)

AccessibleHvpertext

Accessible Hyperlink getLink (int linkIndex)

int CHARACTER, WORD, SENTENCE

int getSelectionStart()

String getSelectedText() int getSelectionEnd() int getLinkIndex (int charIndex)

int getLinkCount()

Accessible get / setAccessibleCaption() Accessible getAccessibleAt (intr, int c)

Accessible Table

Accessible get / setAccessibleColumnDescription(int c) int getAccessibleColumnCount()

int getAccessibleColumnExtentAt(int r, int c) Accessible Table get / setAccessibleColumnHeader() int getAccessibleRowCount()

Accessible get / setAccessibleRowDescription(int r) int getAccessibleRowExtentAt(int r, int c) Accessible Table get / setAccessibleRowHeader()

int[] getSelectedAccessibleColumns() Accessible get / setAccessibleSummary ()

boolean isAccessibleColumnSelected(int c) int[] getSelectedAccessibleRows()

boolean isAccessibleSelected(int r, int c) boolean isAccessibleRowSelected(int r)

int INSERT, UPDATE, DELETE

AccessibleExtendedTable

int getAccessibleColumn(intindex) int getAccessibleIndex(int r, int c) int getAccessibleRow(intindex)

int getFirstColumn() int getFirstRow ()

Accessible Table Model Change

int getLastColumn()

int getLastRow()

int getType ()