java.awt.geom.*
Miscellaneous

Methods declared in supertypes are hidden in subtypes

PathIterator

Accessors
- int getWindingRule ()
- boolean isDone ()

Other Public Methods
- int currentSegment (float[] coords)
- int currentSegment (double[] coords)
- void next ()

int WIND_EVEN_ODD, WIND_NON_ZERO, SEG_MOVETO, SEG_LINETO, SEG_QUADTO, SEG_CUBICTO, SEG_CLOSE

FlatteningPathIterator

FlatteningPathIterator (PathIterator src, double flatness)
FlatteningPathIterator (PathIterator src, double flatness, int limit)

Accessors
- double getFlatness ()
- int getRecursionLimit ()
- int getWindingRule ()
- boolean isDone ()

Other Public Methods
- int currentSegment (float[] coords)
- int currentSegment (double[] coords)
- void next ()

Cloneable

Serializable

AffineTransform

AffineTransform ()
AffineTransform (AffineTransform Tx)
AffineTransform (float[] flatmatrix)
AffineTransform (double[] flatmatrix)
AffineTransform (float m00, float m10, float m01, float m11, float m02, float m12)
AffineTransform (double m00, double m10, double m01, double m11, double m02, double m12)

Static Methods
- AffineTransform **getRotateInstance** (double theta)
- AffineTransform **getRotateInstance** (double theta, double x, double y)
- AffineTransform **getScaleInstance** (double sx, double sy)
- AffineTransform **getShearInstance** (double shx, double shy)
- AffineTransform **getTranslateInstance** (double tx, double ty)

Accessors
- double getDeterminant ()
- void getMatrix (double[] flatmatrix)
- double getScaleX ()
- double getScaleY ()
- double getShearX ()
- double getShearY ()
- double getTranslateX ()
- double getTranslateY ()
- int getType ()
- boolean isIdentity ()
- void setToIdentity ()
- void setToRotation (double theta)
- void setToRotation (double theta, double x, double y)
- void setToScale (double sx, double sy)
- void setToShear (double shx, double shy)
- void setToTranslation (double tx, double ty)
- void setTransform (AffineTransform Tx)
- void setTransform (double m00, double m10, double m01, double m11, double m02, double m12)

Object
- Object clone ()
- boolean equals (Object obj)
- int hashCode ()
- String toString ()

Other Public Methods
- void concatenate (AffineTransform Tx)
- AffineTransform createInverse ()
- Shape createTransformedShape (Shape pSrc)
- Point2D deltaTransform (Point2D ptSrc, Point2D ptDst)
- void deltaTransform (double[] srcPts, int srcOff, double[] dstPts, int dstOff, int numPts)
- Point2D inverseTransform (Point2D ptSrc, Point2D ptDst)
- void inverseTransform (double[] srcPts, int srcOff, double[] dstPts, int dstOff, int numPts)
- void preConcatenate (AffineTransform Tx)
- void rotate (double theta)
- void rotate (double theta, double x, double y)
- void scale (double sx, double sy)
- void shear (double shx, double shy)
- Point2D transform (Point2D ptSrc, Point2D ptDst)
- void transform (Point2D[] ptSrc, int srcOff, Point2D[] ptDst, int dstOff, int numPts)
- void transform (float[] srcPts, int srcOff, float[] dstPts, int dstOff, int numPts)
- void transform (double[] srcPts, int srcOff, double[] dstPts, int dstOff, int numPts)
- void transform (float[] srcPts, int srcOff, double[] dstPts, int dstOff, int numPts)
- void transform (double[] srcPts, int srcOff, float[] dstPts, int dstOff, int numPts)
- void translate (double tx, double ty)

int TYPE_IDENTITY, TYPE_TRANSLATION, TYPE_UNIFORM_SCALE, TYPE_GENERAL_SCALE, TYPE_MASK_SCALE, TYPE_FLIP, TYPE_QUADRANT_ROTATION, TYPE_GENERAL_ROTATION, TYPE_MASK_ROTATION, TYPE_GENERAL_TRANSFORM

www.falkhausen.de Version 0.8 Copyright 2002 by Markus Falkhausen. All rights reserved.