javax.swing.plaf.*
ComponentUI




SeparatorUI
SliderUI
SpinnerUI
TableHeaderUI
TableUI
TabbedPaneUI
Accessors
Rectangle getTabBounds (JTabbedPane pane, int index)
int getTabRunCount (JTabbedPane pane)
Other Public Methods
int tabForCoordinate (JTabbedPane pane, int x, int y)
ViewportUI
ToolBarUI
ToolTipUI
SplitPaneUI
Accessors
int get / setDividerLocation (JSplitPane jc)
int getMaximumDividerLocation (JSplitPane jc)
int getMinimumDividerLocation (JSplitPane jc)
Other Public Methods
void finishedPaintingChildren (JSplitPane jc, Graphics g)
void resetToPreferredSizes (JSplitPane jc)
TextUI
Accessors
EditorKit getEditorKit (JTextComponent t)
int getNextVisualPositionFrom (JTextComponent t, int pos, Position.Bias b, int direction, Position.Bias[] biasRet)
View getRootView (JTextComponent t)
String getToolTipText (JTextComponent t, Point pt)
Other Public Methods
void damageRange (JTextComponent t, int p0, int p1)
void damageRange (JTextComponent t, int p0, int p1, Position.Bias firstBias, Position.Bias secondBias)
Rectangle modelToView (JTextComponent t, int pos)
Rectangle modelToView (JTextComponent t, int pos, Position.Bias bias)
int viewToModel (JTextComponent t, Point pt)
int viewToModel (JTextComponent t, Point pt, Position.Bias[] biasReturn)
TreeUI
Accessors
TreePath getClosestPathForLocation (JTree tree, int x, int y)
TreePath getEditingPath (JTree tree)
Rectangle getPathBounds (JTree tree, TreePath path)
TreePath getPathForRow (JTree tree, int row)
int getRowCount (JTree tree)
int getRowForPath (JTree tree, TreePath path)
boolean isEditing (JTree tree)
Other Public Methods
void cancelEditing (JTree tree)
void startEditingAtPath (JTree tree, TreePath path)
boolean stopEditing (JTree tree)