

Using NTU JumpHost to NSCC ASPIRE-2A



Soh Hwee Jin, Melvin
Senior Assistant Director, InfoComm Infrastructure

Q1. Why do I need to use a Jump Host to Access NSCC Login Node?

NTU users working outside of NTU campus cannot access NSCC ASP2A Login Node directly through NTU VPN due to the current NTU VPN policy and infrastructure setup designed not to allow NTU users to access cloud/outside services of NTU through NTU VPN.

A Jump Host within NTU is required to access NSCC ASPIRE-2A Login Node after you NTU-VPN in.

Q2. Can I use my Workstation / PC as a Jump Host to NSCC instead of HPCC Jump Host?

Of course! You can use your School's PC / Workstation located in your School / Centre and use them as a Jump Host which should be able to reach NSCC as long as they are located within NTU premises. If you are using a Windows Machine, please make sure you have RDP enabled for Remote Access and the necessary Access Rights. If you are using Linux, you should have the necessary rights to access via SSH to the on-premise machine.

Q3. What is Required for me to Access the Jump Host?

1. Your NTU ID

Your NTU ID is required to be registered with the HPCC Jump Host in order for you to login in with your NTU ID

2. Your Supervisor NTU ID

We will be tagging your ID to your Supervisor's NTU ID. This is for easier tracing and cost-recovery charges.

Q4. What are the Steps required to access ASPIRE2A after I have NTU-VPN in?

After you have NTU-VPN in

Step 1: SSH into the HPCC Jump Host with Your NTU-ID and NTU-Password

- You can use MobaXterm (<https://mobaxterm.mobatek.net/>) to access the Jump Host. Once you launch XTerm inside MobaXterm, you can use the following command

```
$ ssh -X Your_NTU_UserID@172.21.26.100  
Password: xxxxx
```

- Alternatively, you can use Putty (<https://www.putty.org/>) to access the Jump Host.

Step 2: From the Jump Host, SSH into the ASPIRE2A

- From the Jump Host, SSH into the ASPIRE-2A login Node with your NSCC ID and your NSCC Password.

\$ ssh -v Your_NSCC_ID@103.72.192.6 OR

\$ ssh -v Your_NSCC_ID@aspire2antu.nsc.sg

- Please take a look at the diagram below (Figure 1) for a better understanding




Figure 1

Q5. Is there a Quota on the HPCC Jump Host?

1. Yes. There is a **50GB** Disk Space for each user.
2. Please initiate at most 2 connection from the Server to NSCC

Q6. Are there cost-recovery charges for the Service?

Like many services in NTU, there may be cost-recovery charge if you need more than the default quota. See the table below for more information

S/No	Description	Annual Charges
3	Disk Space	\$250/TB/yr

Q7. Can I store my data in the Jumphost.

No. This JumpHost as the name implies is meant for you to serve as an intermediary to NSCC ASPIRE-2A.

- If you have large amount of data to transfer, you can use on-premise Computers in NTU to transfer and store your data permanently. See Q2.
- Please do not store your data at the JumpHost. System Administrators have the rights to DELETE data without warnings on 172.21.26.100.

Q8. I need NTU VPN Access. Can I get more Information how this can be done?

VPN is required for user who want to access the NTU Jump Host from outside NTU, e.g home.
By default, CITS disabled students from VPN access. For students who need the VPN access to the JumpHost, the PI must fill in the form from the link below

[NTU VPN Applicaiton \(Network Team\)](#).

We had received users asking about what's next after applying for the access for students.

The PI who applies the VPN access for the students should receive the acknowledgment in the email when the rights are given to the students. It should not take more than a week. If the PI does not receive the email after a week, You can email Eu Ming Yao <mingyao.eu@ntu.edu.sg> who is the network manager to check on the status. Please state the request ID in your email so that it is easy for him to check.

For Staff, use the URL

<http://vpngate-staff.ntu.edu.sg>

For Student, use the URL

<http://vpngate-student.ntu.edu.sg>