AZURE LOAD BALANCER

TO CREATE A 2 VIRTUAL MACHINE

WEB01 AND WEB02









WEB01 AND WEB02 VIRTUAL MACHINES

webserver-s01	···	Azure subscript...	sushmi	Japan East	Running	Linux	Standard_D2s_v3	20.48.3.193	1
webserver02-s	···	Azure subscript...	sushmi	Japan East	Running	Linux	Standard_D2s_v3	20.27.39.143	1

TO CREATE A LOAD BALANCER

Home › Load balancing and content delivery | Load balancers

Create load balancer ...

destination port, protocol type) hash to map traffic to available servers. Load balancers can either be internet-facing where it is accessible via public IP addresses, or internal where it is only accessible from a virtual network. Azure load balancers also support Network Address Translation (NAT) to route traffic between public and private IP addresses. Learn more.

Project details

Subscription * : Azure subscription 1

Resource group * : sushmi
Create new

Instance details

Name * : web1-s

Region * : Japan East

SKU * : (•) Standard (Distribute traffic to backend resources) ( ) Gateway (Direct traffic to network virtual appliances)

Type * : (•) Public ( ) Internal

Tier * : (•) Regional ( ) Global

ADD THE FRONTENED PUBLIC IP

Home › Load balancing and content delivery | Load balancers

Create load balancer ...

Basics | Frontend IP configuration | Backend pools | Inbound rules | Outbound rules | Tags | Review + create

A frontend IP configuration is an IP address used for inbound and/or outbound communication as defined within load balancing, inbound NAT, and outbound rul

+ Add a frontend IP configuration

Name ↑↓	IP address ↑↓
Add a frontend IP to get started	

Review + create | < Previous | Next : Backend pools > | Download a template for automation | Give feedback

Add frontend IP configuration

web1-s

Name * : piblic-ip

IP version : (•) IPv4 ( ) IPv6

IP type : (•) IP address ( ) IP prefix

Public IP address * : (new) azpublicip
Create new

Gateway Load balancer : None

Save | Cancel | Give feedback



ADD THE BACKEND POOL





ADD THE HEALTH PROBE



AND ADD THE LOAD BALANCING RULES



BY USING LOAD BALANCER IP BROWSE IT

```
<!DOCTYPE html>
<html>
<head>
<title>Welcome to nginx!</title>
<style>
html { color-scheme: light dark; }
body { width: 35em; margin: 0 auto;
font-family: Tahoma, Verdana, Arial, sans-serif; }
</style>
</head>
<body>
<h1>Welcome to web02!</h1>
<p>If you see this page, the nginx web server is successfully installed and
working. Further configuration is required.</p>

<p>For online documentation and support please refer to
<a href="http://nginx.org/">nginx.org</a>.<br/>
Commercial support is available at
<a href="http://nginx.com/">nginx.com</a>.</p>

<p><em>Thank you for using nginx.</em></p>
</body>
</html>
~
~
~
~
~
~
~
~
```

TO KNOW THE TRAFFIC WILL BE GOING TO WHICH SERVER

FOR THAT I WILL CHANGING THE NAMES WEB01 AND WEB02 IN THE FILE

THE TRAFFIC WILL BE GOING TO WEB02



AND I CAN STOP THE ONE MACHINE WEB02



THE TRAFFIC WILL GOING TO THE WEB01