區域 Zone	區域名 Zone Name	通道 Conduit	連接區域或管道 Connected zones or conduits	假設和外部相依性 Assumptions and external dependencies
Zone ID, unique identifier	Zone Name	Conduit ID	識別區域和管道之間的連接非常重要，以便識別系統內和進入系統內的所有邏輯存取點。通常，這在區域和管道圖中進行說明 Identify all logical access points in and into the system	區或管道的安全取決於區或管道之外的因素，例如清潔能源以及實體和網宇安全的附加層。應記錄這些假設和相互依賴性 The safety of a zone or conduit depends on factors outside the zone or conduit, such as clean energy and additional layers of physical and cyber security.
01 SIS Zone	Safety Zone	0103, 0104	03 SCADA Zone, 04 Operation Zone	
02 Control Zone	Control Zone	0203, 0204	03 SCADA Zone, 04 Operation Zone	
03 SCADA Zone	Supervisory Zone	0306, 0305, 0103, 0203	01 SIS Zone, 02 Control Zone, 05 Tempory Zone, 06 Interface Zone	
04 Operation Zone	OT Service Zone	0104, 0204	01 SIS Zone, 02 Control Zone	
05 Tempory Zone	OT Working Zone	0305	03 SCADA Zone	
06 Interface Zone	Substation Zone	0306	03 SCADA Zone	

構台名稱 No.	區域 Zone	通道 Conduit	資產ID Asset ID	資產名稱 Asset Name	資產詳細名稱 Asset Detail Name	資產類型 Asset Type		廠商 Asset Vendor	系統功能 Function	型號 Model No.	序號 Serial No.	版本號碼 Version No.	Network Segement	資產IP位址 Asset IP adress	MAC位址 MAC address	Services running	使用通訊埠 Ports Using	使用服務協定 Protocol Using	已安裝資安防護軟體 Security Software Installed	最近汰換憑證期限 Certificated Lists	實體放置/場域環境 Location	System Name/ Device Name	Operating System	Firmware name	Hypervisors	Dependencies	List open ports	Configuration	Logging
1	01 SCADA Zone	0100, 0101, 0103, 0203	HW-03-001	SCADA HMI Server	SCADA HMI for Supervisory	HIS	Windows Host Server	AXXXXX	Graphical monitoring interface	XXXXX	######	###	####	IP address: 192.168.1.2 Subnet Mask: 255.255.255.192 Gateway:192.168.1.1	##########	1.Control : Main software of IED HMI; used for graphic monitoring in substation. 2.Splunk agent 3.Pulsi Ahn 4.Acronis agent	123,102,443,22	SNTP, IEC61850 MMS, Https, SSH	XXXXXX	no	Cabinet_#####	Substation/ SCADA HMI Server	Microsoft Windows 10 pro 20H2(To mitigate the issue for come VPNs, you can disable Vendor ID within the server-side settings. Note: Not all VPN servers have the option to disable Vendor ID from being used)	NA	NA	TBD	COM*10 (Disable) ETH*8 USB*3 VGA (Disable) DVI-D LAN*2 HSB/RRP A HSB/RRP B	/Control: XXXXXX (v#.##.#) /Conf v#.####.#	1. Admin account integrated into Active Directory management 2. Emergency Response Administrator Account
2	02 Control Zone	0201, 0204	HW-02-001	IED (Control)	Intelligent electronic device (IED)	E01	IACS Devices	SXXXXX	An integrated microprocessor-based controller of power system equipment, such as circuit breakers, transformers and capacitor banks	XXXXX	######	###	####	IP address: 192.168.2.2 Subnet Mask: 255.255.255.192 Gateway:192.168.2.1	##########	N/A	22,102,123	SNTP, IEC61850 MMS , SSH	XXXXXX	no	Cabinet_#####	Substation/IED (Control)	TBD	TBD	TBD	TBD	TBD	TBD	TBD
3	01 SIS Zone	0101, 0104	HW-01-001	IED (Protection)	Intelligent electronic device (IED)	E01	IACS Devices	SXXXXX	An integrated microprocessor-based controller of power system equipment, such as circuit breakers, transformers and capacitor banks	XXXXX	######	###	####	IP address: 192.168.1.2 Subnet Mask: 255.255.255.192 Gateway:192.168.1.1	##########	N/A	22,102,123	SNTP, IEC61850 MMS , SSH	XXXXXX	no	Cabinet_#####	Substation/IED (Protection)	TBD	TBD	TBD	TBD	TBD	TBD	TBD
4	02 Control Zone	0201, 0204	HW-02-002	Ethernet Switch (Control)	Ethernet Switch	N01	Network Devices	MXXXX	Connects devices on a computer network by using packet switching to receive and forward data to the destination device	XXXXX	######	###	####	IP address: 192.168.2.3 Subnet Mask: 255.255.255.192 Gateway:192.168.2.1	##########	N/A	123,102,443,22	SNTP, IEC61850 MMS , Https , SSH ,GOOSE	XXXXXX	no	Cabinet_#####	Substation/Ethernet Switch (Control)	TBD	TBD	TBD	TBD	8x RJ45 ports.	TBD	TBD
5	01 SIS Zone	0101, 0104	HW-01-002	Ethernet Switch (Protection)	Ethernet Switch	N01	Network Devices	MXXXX	Connects devices on a computer network by using packet switching to receive and forward data to the destination device	XXXXX	######	###	####	IP address: 192.168.1.3 Subnet Mask: 255.255.255.192 Gateway:192.168.1.1	##########	N/A	123,102,443,22	SNTP, IEC61850 MMS , Https , SSH ,GOOSE	XXXXXX	no	Cabinet_#####	Substation/ Ethernet Switch (Protection)	TBD	TBD	TBD	TBD	8x RJ45 ports.	TBD	TBD
6	05 Tempory Zone	0105	HW-05-001	Wireless AP	Wireless Access Point	N02	Network Devices	MXXXX	A networking hardware device that allows other Wi-Fi devices to connect to a wired network or wireless network	XXXXX	######	###	####	IP address: 192.168.5.2 Subnet Mask: 255.255.255.192 Gateway:192.168.5.1	##########	N/A	N/A	N/A	XXXXXX	no	Cabinet_#####	Substation/Wireless AP	TBD	TBD	TBD	TBD	TBD	TBD	TBD
7	04 Operation Zone	0104, 0204, 0304	HW-04-001	GPS	Time Server	N03	Network Devices	SXXXXX	Provide synchronization and time calibration functions for all devices in the system	XXXXX																			