



You are viewing the **v4 (stable)** documentation. [Switch to v5 \(alpha\) →](#)

Keybinds

Take full control of Noctalia with keyboard shortcuts and IPC commands. This section covers all available commands you can bind to your favorite keys.

Installation-specific commands

- **NixOS Flake users:** Use `noctalia-shell` directly instead of `qs -c noctalia-shell`
- **PikaOS:** Use `qs` instead of `qs -c noctalia-shell`
- **Manual installation users:** If you have Noctalia in `~/.config/quickshell/`, you can use `qs ipc call...` directly

Available Commands

Every aspect of the shell can be controlled via IPC (Inter-Process Communication). Commands are grouped into the following categories:

Note

In the subpages below, commands are shown in their shortened form (e.g., launcher toggle). Hover over any command to see the full ipc call syntax, or use the copy icon to copy the full command to your clipboard.

Core & Navigation



Launcher, Control Center, Settings and basic utilities.

System Controls



Audio, Media, Connectivity, Display and Power management.

You are viewing the **v4 (stable)** documentation. [Switch to v5 \(alpha\) →](#)

Interface & Plugins



Notifications, Appearance, Security and Plugin controls.

Example Configurations

Apply these binds in your window manager configuration to integrate Noctalia.

Niri Configuration

Both spawn-sh and spawn are usable to run Noctalia keybinds.

Add these binds to your ~/.config/niri/config.kdl:

```
binds {  
  // Core Noctalia binds  
  Mod+Space { spawn-sh "qs -c noctalia-shell ipc call launcher toggle"; }  
  Mod+S { spawn-sh "qs -c noctalia-shell ipc call controlCenter toggle"; }  
  Mod+Comma { spawn-sh "qs -c noctalia-shell ipc call settings toggle"; }  
  
  // Audio & Brightness  
  XF86AudioRaiseVolume { spawn "qs" "-c" "noctalia-shell" "ipc" "call" "volume" "increase"; }  
  XF86AudioLowerVolume { spawn "qs" "-c" "noctalia-shell" "ipc" "call" "volume" "decrease"; }  
  XF86AudioMute { spawn "qs" "-c" "noctalia-shell" "ipc" "call" "volume" "muteOutput"; }  
  XF86MonBrightnessUp { spawn "qs" "-c" "noctalia-shell" "ipc" "call" "brightness" "increase"; }  
  XF86MonBrightnessDown { spawn "qs" "-c" "noctalia-shell" "ipc" "call" "brightness"  
    "decrease"; }  
}
```

Hyprland Configuration

Add these binds to your hyprland.conf:

```
$ipc = qs -c noctalia-shell ipc call
```

You are viewing the **v4 (stable)** documentation. [Switch to v5 \(alpha\) →](#)

```
bind = SUPER, SPACE, exec, $ipc launcher toggle
```

```
bind = SUPER, S, exec, $ipc controlCenter toggle
```

```
bind = SUPER, comma, exec, $ipc settings toggle
```

```
# Media keys
```

```
bindel = , XF86AudioRaiseVolume, exec, $ipc volume increase
```

```
bindel = , XF86AudioLowerVolume, exec, $ipc volume decrease
```

```
bindl = , XF86AudioMute, exec, $ipc volume muteOutput
```

```
bindel = , XF86MonBrightnessUp, exec, $ipc brightness increase
```

```
bindel = , XF86MonBrightnessDown, exec, $ipc brightness decrease
```

Sway / Scroll Configuration

Add these binds to your `~/.config/sway/config` (or equivalent for your compositor):

```
set $ipc qs -c noctalia-shell ipc call
```

```
# Core binds
```

```
bindsym $mod+space exec $ipc launcher toggle
```

```
bindsym $mod+s exec $ipc controlCenter toggle
```

```
bindsym $mod+comma exec $ipc settings toggle
```

```
# Media keys
```

```
bindsym --locked XF86AudioRaiseVolume exec $ipc volume increase
```

```
bindsym --locked XF86AudioLowerVolume exec $ipc volume decrease
```

```
bindsym --locked XF86AudioMute exec $ipc volume muteOutput
```

```
bindsym --locked XF86MonBrightnessUp exec $ipc brightness increase
```

```
bindsym --locked XF86MonBrightnessDown exec $ipc brightness decrease
```

Mango Configuration

Add these binds to your `~/.config/mango/config.conf`:

Core binds

You are viewing the **v4 (stable)** documentation. [Switch to v5 \(alpha\) →](#)

```
bind=SUPER,s,spawn,qs -c noctalia-shell ipc call controlCenter toggle
bind=SUPER,comma,spawn,qs -c noctalia-shell ipc call settings toggle

# Media keys
bind=NONE,XF86AudioRaiseVolume,spawn,qs -c noctalia-shell ipc call volume increase
bind=NONE,XF86AudioLowerVolume,spawn,qs -c noctalia-shell ipc call volume decrease
bind=NONE,XF86AudioMute,spawn,qs -c noctalia-shell ipc call volume muteOutput
bind=NONE,XF86MonBrightnessUp,spawn,qs -c noctalia-shell ipc call brightness increase
bind=NONE,XF86MonBrightnessDown,spawn,qs -c noctalia-shell ipc call brightness decrease
```

Discovering Commands

Not sure what else you can control? You can see all IPC commands via this terminal command:

List all targets:

```
qs -c noctalia-shell ipc show
```