

On This Page >

Vars

Manage vars

Usage: `clan vars`

Commands

- [check:](#)
- [fix:](#)
- [generate:](#)
- [get:](#)
- [keygen:](#)
- [list:](#)
- [set:](#)
- [upload:](#)

This subcommand provides an interface to `vars` of clan machines. Vars are variables that a service can generate. There are public and secret vars. Public vars can be referenced by other machines directly. Public vars can include: ip addresses, public keys. Secret vars can include: passwords, private keys.

A service is an included clan-module that implements vars generation functionality. For example the zerotier module will generate private and public vars. In this case the public var will be the resulting zerotier-ip of the machine. The secret var will be the zerotier-identity-secret, which is used by zerotier to prove the machine has control of the zerotier-ip.

Examples

```
$ clan vars generate
```

Will generate vars for all machines.

```
$ clan vars generate --service [SERVICE] --regenerate
```

Will regenerate vars, if they are already generated for a specific service. This is especially useful for resetting certain passwords while leaving the of the vars for a machine in place.

For more detailed information, visit: [secrets](#)

Vars check

Usage: `clan vars check`

Positional Arguments

1. **machine**: The machine to check secrets for

Options



Vars fix

Usage: `clan vars fix`

Positional Arguments

1. **machine**: The machine to fix vars for

Options



Vars generate

Usage: `clan vars generate`

Positional Arguments

1. **machines**: machine to generate vars for. if empty, generate vars for all machines

Options

Vars get

Usage: `clan vars get`

Positional Arguments

1. **machine**: The machine to print vars for
2. **var_id**: The var id to get the value for. Example: ssh-keys/pubkey

Options

Vars keygen

Usage: `clan vars keygen`

Options

Vars list

Usage: `clan vars list`

Positional Arguments

1. **machine**: The machine to print vars for

Options



Vars set

Usage: `clan vars set`

Positional Arguments

1. **machine**: The machine to set a var for
2. **var_id**: The var id for which to set the value. Example: ssh-keys/pubkey

Options



Vars upload

Usage: `clan vars upload`

Positional Arguments

1. **machine**: The machine to upload secrets to

Options



[← Previous](#)

Templates

Next →
Vms

Need help? Reach out to [our community](#).