

[On This Page](#) >

certificates

Sets up a PKI certificate chain using step-ca

Network

❖ Experimental

This service is experimental and will change in the future.

This service sets up a certificate authority (CA) that can issue certificates to other machines in your clan. For this the `ca` role is used. It additionally provides a `default` role, that can be applied to all machines in your clan and will make sure they trust your CA.

Example Usage

The following configuration would add a CA for the top level domain `.foo`. If the machine `server` now hosts a webservice at `https://something.foo`, it will get a certificate from `ca` which is valid inside your clan. The machine `client` will trust this certificate if it makes a request to `https://something.foo`.

This clan service can be combined with the `coredns` service for easy to deploy, SSL secured clan-internal service hosting.

```
1 inventory = {
2   machines.ca = { };
3   machines.client = { };
4   machines.server = { };
5
6   instances."certificates" = {
```

```
7     module.name = "certificates";
8     module.input = "self";
9
10    roles.ca.machines.ca.settings.tlds = [ "foo" ];
11    roles.default.machines.client = { };
12    roles.default.machines.server = { };
13 };
14 };
```

Roles

The certificates service has the following roles:

- ca
- default

Options for the `ca` role

acmeEmail

Email address for account creation and correspondence from the CA. It is recommended to use the same email for all certs to avoid account creation limits.

Type: `string`

Default:

`"none@none.tld"`

Declared in: clanServices/certificates/default.nix

expire

When the certificate should expire.

Type: `null or string`

Default:

`"8760h"`

Example

`"8760h"`

Declared in: [clanServices/certificates/default.nix](#)

tlds

Top level domain for this CA. Certificates will be issued and trusted for `*.<tld>`. Defaults to `[ config.clan.core.settings.tld ]`

Type: `list of string`

Default:

`[ ]`

Declared in: [clanServices/certificates/default.nix](#)

Options for the `default` role

acmeEmail

Email address for account creation and correspondence from the CA. It is recommended to use the same email for all certs to avoid account creation limits.

Type: `string`

Default:

"none@none.tld"

Declared in: [clanServices/certificates/default.nix](#)

← Previous
borgbackup

Next →
coredns

Need help? Reach out to [our community](#).