THLHP Globus quick web app guide

This guide is for uploading files using the web interface of globus. This is useful for quickly uploading smaller files and generating a link that could be shared with collaborators. The data is uploaded to ASU on-site storage which is snapshotted every night with each snapshot kept for 30 days.

Contents

1	Globus endpoints	1
2	Requesting access	2
3	Upload files	2
4	Download files	9
5	Deleting files	10
6	Sharing uploads with specific users	10

1 Globus endpoints

There is currently a single endpoint which by default makes any uploaded file accessible to all members of the THLHP project. The list of members that have access the THLHP Data Shares directory can be viewed using this direct link


• THLHP Data Shares

- UUID: 3522768-02fa-4117-a2d4-f8ff15011b1d
- Domain: g-ef43db.251141.e229.dn.glob.us
- Description: Default collection which allows read and write access to all members of the project.

2 Requesting access


To request access to the group visit the group page within globus and click 'Join this Group'. This will trigger an email to the group administrators with a link to approve or decline the join request. Once the request is approved you will be able to view the members of the group as well as all collections.

- 1. Link to request permission to group: https://app.globus.org/groups/94d5f71b-21ae-11ee-b52a-955597948ffe/about
- 2. Link to view members of the group: https://app.globus.org/groups/94d5f71b-21ae-11ee-b52a-955597948ffe/members




3 Upload files


1. Open the globus share using the web app. Here is the direct link




2. When uploading single or multiple files first create a new folder by right clicking anywhere in the directory box and clicking 'New Folder'. Name the directory with a meaningful name as appropriate.




3. a. Click the Upload button. If this is the first time you are uploading using the web interface then the application will request consent.




On the next page click 'Allow'.



b. Click one of the uploading options.




4. After selecting the files for uploading the upload progress should be visible at the bottom left corner of the page.




- 5. Once the upload concludes the directories should refresh and the uploaded directory should be visible in the list.
 - a. Sharing link for downloading File link

Double click the newly uploading directory, single click the desired file and click Get Link.




b. Sharing link for downloading - Folder link

For sharing link to entire folder one can either copy the current URL from the browser's address bar or click the copy link on access this Collection and Path in File Manager.




4 Download files

When downloading a single file using a direct link, opening the link should directly initiate the download (after authentication). When downloading specific files from a shared directory select individual files and click Download or right click the file and select download. Note: Entire directories cannot be downloaded using the web app. The recommended method for downloading entire files is using the globus desktop client.



5 Deleting files

Files or directories can be deleted by either selecting the path and clicking Delete Selected or by right clicking the path and choosing Delete Selected.



6 Sharing uploads with specific users

If sharing data with a particular subset of users instead of the whole THLHP group please use the Private shares directory under THLHP Data Shares. Please contact Suhail Ghafoor for setting up a protected directory. This directory can be used for sharing data within a specific group or between multiple groups.