Kickbase 0.4 – what's new and test list

Format: Do this → expected result. Tick the box when it matches. Report anything that does not. Tested in Lemon.

What's in 0.4

Effects and mixer

- **FX send matrix.** Old SEND links move to the matrix automatically when a project loads; INS shows as its own row.
- **Remove FX channel.** The FX popup has "- remove FXn" on the last channel. If it has effects or sends it asks first; Ctrl+Z restores effects, EQ, compressor, level and sends.
- **PATTERN rows.** The FX knob is gone, VOL is larger and the FX button shows "N x FX".
- **MIX tab.** The combined wave has the full width on top with the knobs below; WIDE/NARROW is gone.

KICK tab

- **New SYNTH tab layout.** The MIX control now sits in the tab row (SYNTH / SAMPLE / ENVELOPE). KEY moved into TUNING, the envelope curves are above the knobs, and the knobs use the 48 px size.
- **SYNTH / SAMPLE buttons are gone.** MIX alone controls the blend: left = synth only, middle = both, right = sample only. Old presets are migrated.
- **SAMPLE tab.** Split into three boxes: PITCH, AMP and REVERSE.

Look and feel

- **Hover everywhere.** Chips, tabs, pill buttons and dropdowns brighten under the mouse; popup menus have a rounded background and a cyan highlight.
- Shared edge glow, clearer menu levels, glass buttons and glass PREVIEWS; more air (margin and padding) in menus.
- **Glow strength** Off / Weak / Strong in SETTINGS (off by default).
- Large OUT knob; knob and label form one block; SWING / HUMAN / DELAY have one knob per row.
- **FILTER tab.** The allpass knobs use the same knob size as the rest.

Diagrams and views

- **OSC OUTPUT.** A new OUTPUT view of the oscillator (phase, warp, unison with detune/blend).
- **TIMING diagram.** All lanes on one time axis. Drag the left edge (POS DELAY) and right edge (LENGTH). FOCUS / OVERVIEW.
- **Small timing diagram on INSTR.** Read-only; a click opens TIMING.
- **FM diagram.**
- **Harmonic editor.** Tooltips and a HELP tab.

Preview and JOG

- **One preview at a time.** PREVIEW switches off when you audition locally (speaker, LISTEN, key, slice, JOG).
- **JOG TEST BPM.** Own knob for the tempo of the JOG test.

Before you start

Click inside the plugin window first so it has keyboard focus (otherwise the DAW may take Ctrl+Z and similar shortcuts). Older presets and projects should sound as before.

Test list

KICK tab

- [ ] **Open KICK > SYNTH** → the MIX control is in the tab row, KEY is in TUNING, the envelope curves sit above the knobs, nothing overlaps or is clipped. Make the window narrower → the preset selector and the help button stay usable, the MIX label is readable.
- [ ] **Look for the old SYNTH / SAMPLE buttons** → they are gone.
- [ ] **MIX fully left** → only the synthesised kick. Middle → both. Fully right → only the sample.
- [ ] **Open an old preset that had SYNTH off, and one that had SAMPLE off** → they sound as before. *Depends on the migration of the old toggles into MIX; if a preset sounds different, note its name.*
- [ ] **KICK > SAMPLE** → three boxes PITCH, AMP and REVERSE; each control responds.
- [ ] **HELP button on the KICK tab** → opens help and does not cover the tab row.

Hover and menus

- [ ] **Move the mouse over chips, tabs, pill buttons and dropdowns** → each brightens while hovered.
- [ ] **Open a dropdown or context menu** → rounded dark background, the hovered item has a cyan highlight.
- [ ] **Open menus in several tabs** → the levels are easy to tell apart and there is air around the items.

Look and feel

- [ ] **SETTINGS > Glow strength: Off, Weak, Strong** → the edge glow follows; Off is the default.
- [ ] **PREVIEW buttons** → glass look. OUT knob → large. SWING / HUMAN / DELAY → one knob per row.
- [ ] **FILTER tab** → the allpass knobs are the same size as the others.
- [ ] **Knobs and labels on INSTR, FILTER, SAMPLE and TIMING** → knob and label read as one block (known issue in 0.3). Note anything that is hard to use.

FX and mixer

- [ ] **Open an old project with an FX link in SEND mode** → one normal FX row in the popup (no double row). An INS link shows as "INS FXn".
- [ ] **FX popup, last channel, "- remove FXn"** → asks first if the channel has effects or sends; Ctrl+Z restores effects, EQ, compressor, level and sends.
- [ ] **PATTERN rows** → one larger VOL knob, no FX knob. The FX button shows None / FX / "2 x FX"; hovering lists the channels.
- [ ] **MIX tab** → the wave has the full width on top, knobs below, WIDE/NARROW is gone.

INSTRUMENT, OSC and timing

- [ ] **INSTRUMENT sub-tabs** → INSTR | OSC 1, OSC 2, OSC 3, SAMPLE, FM | FILTER, MIX, TIMING with dividers. The FM on/off icon controls FM.
- [ ] **Breadcrumb** → INSTRUMENT > instrument name > OSC 2, follows tab and instrument changes; no KICKBASE in it. Also KICK, and ANALYZER > SPECTRUM.
- [ ] **The row above the instrument tabs** → taller, nothing clipped.
- [ ] **OSC 1, click the MODE label until it says OUTPUT** → Phase shifts the wave sideways, Warp changes the shape. Unison 1 shows two periods; Unison 3+ shows many periods with beating; Detune and Blend change the beating. Push Position, Warp and Phase to their extremes with Unison 1 and 8 → the picture never goes empty and nothing crashes.
- [ ] **TIMING opens in FOCUS** → drag the left edge of the tall lane: POS DELAY follows; drag the right edge: LENGTH follows. Click another lane → it becomes tall and the knobs switch motor. With SYNC on, dragging does nothing.
- [ ] **Play a note** → playhead and release line move in the lanes. NUDGE and POLARITY → lanes shift / contour flips. NUDGE ≠ 0 and drag the left edge → no jump on the first drag.
- [ ] **LENGTH 0 without SYNC** → dragging right of the left edge pulls LENGTH out from 0.
- [ ] **OVERVIEW shows all boxes, FOCUS goes back; close and reopen the tab** → the choice is kept.
- [ ] **INSTR tab** → a small time diagram; the playhead moves with a note; dragging changes nothing; a click opens TIMING.
- [ ] **FM tab** → the FM diagram shows and follows the FM settings.

- [ ] **Harmonic editor** → hover the fields (tooltips); HELP opens the HARMONICS tab.

Preview and JOG

- [ ] **Start PREVIEW, then press a speaker button / LISTEN / a key / a slice / JOG** → PREVIEW switches off and no sound hangs.
- [ ] **JOG panel** → the JOG TEST BPM knob sets the tempo of the JOG test.

Older projects

- [ ] **Open a project and a preset made in 0.3** → loads and sounds as before.