

Lab 1: Networking & Interface Configuration

DATE:13/12/2025

The first screenshot shows the 'Interfaces / LAN (em1)' configuration page. A yellow notification bar at the top states: 'The LAN configuration has been changed. The changes must be applied to take effect. Don't forget to adjust the DHCP Server range if needed after applying.' A green 'Apply Changes' button is visible. The 'General Configuration' section includes: 'Enable' (checked), 'Description' (LAN), 'IPv4 Configuration Type' (DHCP), 'IPv6 Configuration Type' (DHCP6), 'MAC Address' (xxxxxxxxxx), 'MTU' (1400), 'MSS' (empty), and 'Speed and Duplex' (Default). The second screenshot shows the 'Interfaces / Interface Assignments' page. A red warning bar at the top states: 'WARNING: The password for this account is insecure. Password is currently set to the default value (pfsense). Change the password as soon as possible.' The 'Interface Assignments' tab is active, showing a table with columns 'Interface' and 'Network port'. The table contains two rows: 'WAN' assigned to 'em0 (08:00:27:33:01:d7)' and 'LAN' assigned to 'em1 (08:00:27:6c:c4:5d)'. A 'Save' button is at the bottom left, and a 'Delete' button is next to the LAN row. A blue information box at the bottom states: 'Interfaces that are configured as members of a lagg(4) interface will not be shown. Wireless interfaces must be created on the Wireless tab before they can be assigned.'

Interfaces / LAN (em1)

The LAN configuration has been changed.
The changes must be applied to take effect.
Don't forget to adjust the DHCP Server range if needed after applying.

Apply Changes

General Configuration

Enable ☒ Enable interface

Description LAN
Enter a description (name) for the interface here.

IPv4 Configuration Type DHCP

IPv6 Configuration Type DHCP6

MAC Address xxxxxxxxxxxx
This field can be used to modify ("spoof") the MAC address of this interface.
Enter a MAC address in the following format: xxxxxxxxxxxx or leave blank.

MTU 1400
If this field is blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary in some circumstances.

MSS
If a value is entered in this field, then MSS clamping for TCP connections to the value entered above minus 40 for IPv4 (TCP/IPv4 header size) and minus 60 for IPv6 (TCP/IPv6 header size) will be in effect.

Speed and Duplex Default (no preference, typically autoselect)
Explicitly set speed and duplex mode for this interface.
WARNING: MUST be set to autoselect (automatically negotiate speed) unless the port this interface connects to has its speed and duplex forced.

pfSense
COMMUNITY EDITION

System - Interfaces - Firewall - Services - VPN - Status - Diagnostics - Help

WARNING:
The password for this account is insecure. Password is currently set to the default value (pfsense).
Change the password as soon as possible.

Interfaces / Interface Assignments

Interface Assignments Interface Groups Wireless VLANs QinQs PPPs GREs GIGs Bridges LAGGs

Interface	Network port
WAN	em0 (08:00:27:33:01:d7)
LAN	em1 (08:00:27:6c:c4:5d) Delete

Save

Interfaces that are configured as members of a lagg(4) interface will not be shown.
Wireless interfaces must be created on the Wireless tab before they can be assigned.

pfSense is developed and maintained by Netgate. © ESF 2004 - 2025 View license.

