

TB Spectral Transient Shaper

USER MANUAL



Purpose

Separates attack and sustain so you can change punch, clarity, and length by frequency area.

License: MIT License

This software is licensed under the MIT License. Copyright (c) 2026 TaebeumKim. See the repository LICENSE file for the full terms.

Controllable properties

Each control is listed by its panel name. Use the description to decide what to listen for, then make small changes in the context of the music.

Control and settings	What it changes
ATK_HIGH Frequency Range: 20 to 20000 Default: 8000	Chooses the tonal area used for attack shaping in this band.
ATK_HIGH Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's attack focus is.
ATK_HIGH Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily attack energy is selected in this band.
ATK_LOW Frequency Range: 20 to 20000 Default: 100	Chooses the tonal area used for attack shaping in this band.
ATK_LOW Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's attack focus is.
ATK_LOW Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily attack energy is selected in this band.
ATK_MID Frequency Range: 20 to 20000 Default: 1000	Chooses the tonal area used for attack shaping in this band.

Control and settings	What it changes
ATK_MID Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's attack focus is.
ATK_MID Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily attack energy is selected in this band.
Attack Gain Range: -24 to 24 Default: 4	Raises or lowers the front edge of sounds.
Attack Release Range: 1 to 2000 Default: 50	Sets how quickly attack shaping relaxes after each hit.
Attack Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily the plug-in identifies attack energy.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Clipper Range: Off, On Default: Off	Turns on firm peak trimming before the final output.
Clipper Threshold Range: -20 to 0 Default: -0.7	Sets the level where the clipper begins trimming peaks.
Input Gain Range: -24 to 24 Default: 0	Sets how loud the sound enters the plug-in. Raise it for a stronger response or lower it for more headroom.
Limiter Range: Off, On Default: Off	Turns on final peak protection.

Control and settings	What it changes
Limiter Threshold Range: -24 to 0 Default: -0.1	Sets the maximum level allowed by the limiter.
Lookahead Range: 0 to 20 Default: 0	Helps catch sudden peaks more smoothly. Higher values can feel slightly less immediate.
Mode Range: Simple, EQ Default: Simple	Chooses one broad control pair or separate low, mid, and high sensitivity controls.
Monitor Range: Normal, Normal Delta, Attack, Attack Delta, Sustain, Sustain Delta Default: Normal	Chooses the full result or isolates the attack, sustain, or removed difference for listening.
Output Gain Range: -24 to 24 Default: 0	Sets the final listening level after processing.
Oversampling Range: x1, x2, x4, x8 Default: x1	Makes heavy distortion or limiting sound cleaner at the cost of more CPU use.
Program Range: 25 factory programs Default: Init	Loads a factory starting point. Adjust the controls afterward to fit the current sound.
Saturation Range: Off, On Default: Off	Sets how strongly this part controls level after the threshold.
Saturation Drive Range: 0 to 36 Default: 0	Sets how strongly this part controls level after the threshold.
Saturation Mode Range: Soft, Punch, Warm, Digital, Fold, Hard Default: Soft	Chooses the harmonic character added to the shaped sound.

Control and settings	What it changes
Saturation Shaper Link Range: Off, On Default: Off	Makes the saturation follow the current attack and sustain shaping.
SUS_HIGH Frequency Range: 20 to 20000 Default: 8000	Chooses the tonal area used for sustain shaping in this band.
SUS_HIGH Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's sustain focus is.
SUS_HIGH Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily sustain energy is selected in this band.
SUS_LOW Frequency Range: 20 to 20000 Default: 100	Chooses the tonal area used for sustain shaping in this band.
SUS_LOW Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's sustain focus is.
SUS_LOW Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily sustain energy is selected in this band.
SUS_MID Frequency Range: 20 to 20000 Default: 1000	Chooses the tonal area used for sustain shaping in this band.
SUS_MID Q Range: 0.1 to 10 Default: 1	Sets how wide or narrow this band's sustain focus is.
SUS_MID Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily sustain energy is selected in this band.
Sustain Gain Range: -24 to 24 Default: -2	Raises or lowers the body and tail of sounds.

Control and settings	What it changes
Sustain Release Range: 1 to 2000 Default: 50	Sets how quickly sustain shaping returns after the sound changes.
Sustain Sensitivity Range: 0 to 1 Default: 0.5	Sets how easily the plug-in identifies sustain energy.