




Assignment 4

Connecting Practical on Printer &
Webcam

1. Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

1. Plug in the USB Webcam:

Connect the webcam's USB cable directly to an available USB port on your computer. Wait a few seconds for the computer to detect it.

2. Install the Required Drivers:

- Windows 10/11: Most webcams are plug-and-play, so Windows will automatically install the required driver.
- If needed: Download the webcam driver from the manufacturer's official website and install it.

3. Open the Camera App:

- On Windows: Open Start Menu → Camera.
- On Mac: Open Finder → Applications → Photo Booth.

4. Check and Capture a Photo:

1. Make sure the webcam preview shows your video.
2. If you have more than one camera, select the USB webcam from the camera settings.
3. Click the Photo/Shutter button to capture a photo.
4. Check the saved photo to confirm that the webcam is working properly.

➤ Result: The USB webcam was successfully connected, detected, and tested by capturing a photo.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

1. Connect the Printer:

Connect the printer to your computer using a **USB cable**. If it is a network printer, connect the printer and computer to the **same Wi-Fi network**.

2. Install the Printer Driver:

- **Windows 10/11:** Windows may automatically detect and install the required driver.
- **Manual Setup:** If needed, download the correct driver from the printer manufacturer's official website and install it.

3. Add the Printer:

- Go to **Settings → Bluetooth & devices → Printers & scanners**.
- Click **Add device**.

- Select your printer and complete the setup.

4. Print a Test Page:

1. Open **Printers & scanners** and select your printer.
2. Open **Printer properties**.
3. Click **Print Test Page**.
4. Check that the page prints correctly.

- 3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem Hint Check for error icons and use the 'Scan for hardware changes' option after reconnecting.**

Step 1: Cause the Problem

- Open Device Manager (right-click the Start button and click Device Manager).
- Unplug the printer's USB cable from your computer.
- You will see the printer disappear from the list, or show a yellow warning sign (!).

Step 2: Fix the Problem

- Plug the cable back in: Firmly reconnect the USB cable and make sure the printer is turned on.
- Refresh the list: At the top menu of Device Manager, click Action and then click Scan for hardware changes (or click the blue monitor icon on the toolbar).
- Check the result: Windows will scan your computer and your printer will pop back up in the list with no warning signs.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

1. Check the Camera in the Camera App:

Open the Windows Camera app and make sure the webcam video is working. If it works there, the webcam itself is working properly.

2. Close Other Apps Using the Webcam:

Close apps such as Camera, Microsoft Teams, Google Meet, Skype, or other video apps that may be using the webcam. Then reopen Zoom.

3. Check Zoom Camera Settings:

- Open Zoom and go to Settings → Video.
- Under Camera, select the correct webcam.
- Check if the video preview is displaying.

4. Allow Camera Permission:

- Go to Settings → Privacy & security → Camera.
- Turn on Camera access.
- Turn on Let desktop apps access your camera.

5. Restart Zoom:

Completely close Zoom and open it again. Test the webcam during a meeting.

6. Test the Webcam:

Start a Zoom test meeting or video call and check whether the webcam video is now visible.