
## DATABASE PROGRAMMING SCHEMA DIAGRAM

NEM\_RM16 table is the table that will be used to deliver the AEMO data to you. You have select privileges only to this table. There is a public synonym created to make access to the table transparent



V_NEM_RM16		
COMPANY_CODE	TEXT(25)	
SETTLEMENT_CASE_ID	LONG	
SETTLEMENT_RUN_ID	LONG	
STATEMENT_TYPE	TEXT(25)	
TNI	TEXT(25)	
METERTYPE	TEXT(25)	
FRMP	TEXT(25)	
LR	TEXT(25)	
MDP	TEXT(25)	
CHANGE_DATE	DATETIME	
DAY	DATETIME	
HH	LONG	
VALUE	SINGLE	
TRANSACTION_ID	TEXT(25)	

The Object V-NEM\_RM16 is a VIEW
The purpose of the View is to Unwrap the
Objects in the NEM\_PRM16 table
The data is the same in the two Objects and
you can use either as the source of data for
your forecasting

NEM_RM16		
	COMPANY_CODE SETTLEMENT_CASE_ID SETTLEMENT_RUN_ID STATEMENT_TYPE TNI METERTYPE FRMP LR MDP CHANGE_DATE DAY VALUE TRANSACTION ID	VARCHAR(25) INTEGER INTEGER VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) DATETIME DATETIME RM16_DAY VARCHAR(25)

LOCAL_RM16		
COMPANY_CODE SETTLEMENT_CASE_ID SETTLEMENT_RUN_ID STATEMENT_TYPE TNI METERTYPE FRMP LR MDP CHANGE_DATE DAY VALUE TRANSACTION_ID	VARCHAR(25) INTEGER INTEGER VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) VARCHAR(25) DATETIME DATETIME RM16_DAY VARCHAR(25)	

DBP_HOLIDAY					
PK DATE DATETIME					

DBP_MESSAGE_LOG			
PK	INTEGER		
	STUDENT_ID MSG_DATE MSG_ID MESSAGE	VARCHAR(50) DATETIME VARCHAR(35) VARCHAR(2000)	

DBP_PARAMETER		
CATEGORY CODE VALUE ACTIVE MODIFIED	VARCHAR2(35) VARCHAR2(35) VARCHAR2(35) VARCHAR2(1) 'Y' DATE (sysdate)	

RUN_TABLE	
RUN_ID	NUMBER
RUN_START	DATE
RUN_END	DATE
OUTCOME	VARCHAR2(15)
REMARKS	VARCHAR2(255)

LOCAL\_RM16 table is the table that you will create to store your data.