
Practical 1: LAN Design with Subnetting and Router ConfigurationAim:

Design a Local Area Network (LAN) using 3 PCs connected to a router.

#### Instructions:

- Assign each PC a unique subnet.
- Configure IP addresses and subnet masks.
- Configure the router interfaces to connect the subnets.
- Ensure all devices can communicate via the router.



#### 1. Add Devices

- **Drag and drop** the following from the bottom device list:
  - o 1 Router (Router0)
  - 2 PCs (PC0 and PC1)

#### 2. Connect Devices

- Use Copper Cross-Over Cable:
  - $\circ$  Connect PC0  $\rightarrow$  Router0
  - $\circ$  Connect PC1 → Router0

You can use FastEthernet0 on PCs and GigabitEthernet0/0 or 0/1 on the router depending on availability.

#### 3. Configure IP Addresses

- PC0 Configuration:
  - o Go to **Desktop > IP Configuration**

IP Address: 192.168.1.1
 Subnet Mask: 255.255.255.0
 Default Gateway: 192.168.1.254

• PC1 Configuration:

IP Address: 192.168.2.1
 Subnet Mask: 255.255.255.0
 Default Gateway: 192.168.2.254

#### 4. Configure Router Interfaces

• Click on **Router0 > CLI** or **Config tab**, then configure interfaces:

```
enable configure terminal interface gigabitEthernet0/0 ip address 192.168.1.254 255.255.255.0 no shutdown exit interface gigabitEthernet0/1 ip address 192.168.2.254 255.255.255.0 no shutdown exit
```

#### **5. Verify Connection**

- Use **Simulation Mode** to test ICMP (ping):
  - From **PC0 Desktop > Command Prompt**, type:
  - o ping 192.168.2.1

You should see the ping packets go from  $PC0 \rightarrow Router \rightarrow PC1$  and a successful reply if configured correctly.


#### Practical 2: Router-to-Switch Connection and Basic Configuration

#### Aim:

Connect a router to a switch and perform initial router configurations.

#### Instructions:

- Connect the router to the switch using proper cabling.
- Assign IP addresses to connected devices.
- Configure basic settings such as hostname, interface IP, and default gateway.
- Verify end-to-end connectivity using ping.



# 1. Add Devices

- 1 **Router** (e.g. Router0)
- 1 **Switch** (e.g. Switch0)
- 2 **PCs** (e.g. PC0, PC1)

#### 2. Connect Devices

#### • Use Copper Straight-Through Cable:

- o Router0  $\leftrightarrow$  Switch0 (e.g., Gig0/0 to FastEthernet0/1)
- o PC0  $\leftrightarrow$  Switch0 (e.g., FastEthernet0/2)
- o PC1  $\leftrightarrow$  Switch0 (e.g., FastEthernet0/3)

# 3. Configure VLANs on the Switch

#### 1. Go to the **Switch CLI**:

```
enable
configure terminal
vlan 10
name VLAN10
vlan 20
name VLAN20
exit
```

#### 2. Assign switch ports to VLANs:

```
interface fastEthernet0/2
switchport mode access
switchport access vlan 10
exit

interface fastEthernet0/3
switchport mode access
switchport access vlan 20
exit
```

#### 3. Configure the trunk port (connection to router):

```
interface fastEthernet0/1
switchport mode trunk
exit
```

# 4. Configure Router Subinterfaces for Inter-VLAN Routing

#### Go to the Router CLI:

```
enable
configure terminal

interface gigabitEthernet0/0.10
encapsulation dot1Q 10
ip address 192.168.10.1 255.255.255.0
```

#### exit

interface gigabitEthernet0/0.20
encapsulation dot1Q 20
ip address 192.168.20.1 255.255.255.0
exit
interface gigabitEthernet0/0
no shutdown
exit

# 5. Configure IP on PCs

#### PC0:

IP Address: 192.168.10.2
Subnet Mask: 255.255.255.0
Default Gateway: 192.168.10.1

#### **PC1:**

IP Address: 192.168.20.2
Subnet Mask: 255.255.255.0
Default Gateway: 192.168.20.1

# 6. Test Connectivity

• Go to PC0 > Command Prompt:

ping 192.168.20.2

You should receive successful replies — meaning inter-VLAN routing is working properly.

Would you like to add **DHCP**, **DNS**, or **more VLANs** to this setup?


Practical 3: Setup a Small Office/Home Office (SOHO) Network

#### Aim:

Design and configure a basic SOHO network with internet access.

#### Instructions:

- Use a router, switch, and multiple PCs.
- Assign appropriate IP addresses.
- Configure DHCP (if required).
- Simulate internet connectivity using a cloud device.



#### 1. Add Devices

From the device selection at the bottom of Cisco Packet Tracer:

- 1 **Switch** (e.g., Switch0)
- 5 **PCs** (e.g., PC0 to PC4)
- 1 **Server** (e.g., Server0)

# 2. Connect Devices to the Switch

Use **Copper Straight-Through Cable** to connect each device to the switch:

- PC0 to Switch0
- PC1 to Switch0
- PC2 to Switch0
- PC3 to Switch0
- PC4 to Switch0
- Server0 to Switch0

(Connect all to different **FastEthernet ports**, like Fa0/1 to Fa0/6)

## 3. Assign IP Addresses

Use manual IP configuration:

# Device IP Address Subnet Mask Default Gateway (optional) PC0 192.168.1.1 255.255.255.0 192.168.1.254 (if needed) PC1 192.168.1.2 255.255.255.0 192.168.1.254 PC2 192.168.1.3 255.255.255.0 192.168.1.254 PC3 192.168.1.4 255.255.255.0 192.168.1.254 PC4 192.168.1.5 255.255.255.0 192.168.1.254 Server0 192.168.1.10 255.255.255.0 192.168.1.254

To assign IPs:


- Click each PC or Server
- Go to **Desktop** > **IP Configuration**
- Manually enter the IP Address and Subnet Mask

# 4. Test Connectivity

To verify the LAN is working:

- Open Command Prompt on PCO
- Type:
- ping 192.168.1.3
- ping 192.168.1.10

If responses return without packet loss, your LAN setup is working correctly.



- 1. Click on the PC (e.g., PC1).
- 2. Go to the **Desktop** tab.
- 3. Click on **IP Configuration**.
- 4. Select **Static**.
- 5. Enter:
  - o **IP Address**: 10.0.0.x (e.g., 10.0.0.4)
  - o **Subnet Mask**: auto-fills as 255.0.0.0
  - o **Default Gateway**: 10.0.0.1
- 6. Close the window.


#### Practical 4: Secure a Cisco Router or Switch with Passwords


#### Aim:

Secure access to Cisco devices using different types of passwords.

#### Instructions:

- Set a console password for accessing the device locally.
- Set an enable password for privileged mode.
- Configure VTY (telnet/SSH) passwords for remote access.
- Save the configuration and test login access





#### 1. Start the CLI

When prompted, press Enter.

# 2. Enter Privileged EXEC Mode:

enable

## 3. Enter Global Configuration Mode:

configure terminal

#### 4. Set a Hostname (Optional):

hostname Switch0

#### 5. Set Console Password:

line console 0
password cisco
login
exit

#### 6. Set Enable Password:

enable password class

# 7. Set IP Address for VLAN 1 (Switch Management):


interface vlan 1
ip address 192.168.1.2 255.255.255.0
no shutdown
exit

#### 8. Set Default Gateway (for remote access):

ip default-gateway 192.168.1.1

#### 9. Save the Configuration:

exit
write memory



#### 1. Enter Privileged EXEC Mode:

enable

# 2. Enter Global Configuration Mode:

configure terminal

#### 3. Set Console Password:

line console 0
password cisco
login
exit

#### 4. Set Enable Password:

enable password class


# **5. Save the Configuration:**


write memory


# ♦ Now your router is secured with:

- Console access requiring the password cisco
- Privileged mode access requiring the password class

# Practical 5: Configure RIP v2 on Multiple Router







# Static Routing Between 3 Routers

# **★** Step 1: Assign IP Addresses to Router Interfaces

#### Do this for each router:

```
enable
configure terminal
interface <INTERFACE_NAME>
ip address <IP_ADDRESS> <SUBNET_MASK>
no shutdown
exit
```

#### $\rightarrow \square$ Example from your image:

#### Router1:

```
interface g0/0
ip address 12.0.0.1 255.255.255.0
no shutdown
exit
interface g0/1
ip address 13.0.0.1 255.255.255.0
no shutdown
```

#### **Router2:**

```
interface g0/0
ip address 12.0.0.2 255.255.255.0
no shutdown
exit
interface g0/1
ip address 23.0.0.2 255.255.255.0
no shutdown
```

#### **Router3:**

```
interface g0/0
ip address 13.0.0.3 255.255.255.0
no shutdown
exit
interface g0/1
ip address 23.0.0.3 255.255.255.0
no shutdown
```

# **➡** Step 2: Configure Static Routes

On each router, add static routes to the **networks not directly connected**.

#### Router1:

```
ip route 23.0.0.0 255.255.255.0 12.0.0.2
```

#### **Router2:**

```
ip route 13.0.0.0 255.255.255.0 12.0.0.1
```

#### **Router3:**

ip route 12.0.0.0 255.255.255.0 13.0.0.1


# **Step 3: Verify Connectivity**

Use the **ping** command from one router to another:

```
ping 13.0.0.3
ping 12.0.0.1
ping 23.0.0.2
```

Or use the **Simulation Mode** like you've shown — all pings should be **successful**.

#### Practical 6: VLAN and VTP Configuration on Switches



# ✓ Static Routing in Cisco Packet Tracer (3 Routers)

# **Step 1: Connect the Routers**

Use **copper cross-over cables** to connect the routers like this:

Router1 ↔ Router2 ↔ Router3 ↔ Router1

(Connect via GigabitEthernet or FastEthernet ports)

# **♥**□ Step 2: Assign IP Addresses

Go to each router CLI and enter:

#### Router1

enable
configure terminal

interface g0/0
ip address 12.0.0.1 255.255.255.0
no shutdown
exit
interface g0/1
ip address 13.0.0.1 255.255.255.0
no shutdown
exit

#### Router2

enable configure terminal interface g0/0 ip address 12.0.0.2 255.255.255.0 no shutdown exit interface g0/1 ip address 23.0.0.2 255.255.255.0 no shutdown exit

#### Router3

enable configure terminal interface g0/0 ip address 13.0.0.3 255.255.255.0 no shutdown exit interface g0/1 ip address 23.0.0.3 255.255.255.0 no shutdown exit

# Step 3: Add Static Routes

#### Router1

ip route 23.0.0.0 255.255.255.0 12.0.0.2

#### Router2

ip route 13.0.0.0 255.255.255.0 12.0.0.1

#### Router3

ip route 12.0.0.0 255.255.255.0 13.0.0.1

# **Step 4:** Test the Network

- 1. Click on **Simulation Mode**.
- 2. Use Add Simple PDU (the lightning icon).
- Click Router1, then Router3 (and vice versa).
   Check that the packets show "Successful" in the event list (as in your screenshot).