Using Terminal Servers at the Department of Global Public Health and Primary Care - a manual for a 2-step authentication.

UiB machines:



- 1) Press the Start button in Windows
- 2) Click the mouse cursor at "All programs"
- 3) In the list find and press Cisco > Cisco AnyConnect Secure Mobility Client > Cisco AnyConnect Secure Mobility Client.

You can also start the program by using the shortcut-icon in the lower right corner of your



When the program starts → Select "UiB Tilgang Terminalserver" and click Connect.



This picture will appear:




Please enter your username and password.

Once that is done you will receive a code by SMS to your mobile phone from the University of Bergen. Type it here and press "Continue":



4) You now have access to log on to the terminal server using the Remote Desktop Connection application located in Start > All Programs > Accessories



Enter the name of the server i.e. hrist.uib.no or bigs.uib.no and press Connect.

- 5) Enter your username as UIB\username and enter your password
- 6) The terminal window should now appear and you can start working. After 8 hours you will have to login again.
- 7) Remember to store all your work in the folder with your name under S:\. Do not store your work in the Documents-folder!
- 8) Your password at UoB lasts for 13 months and must then be replaced using this website: https://sebra.uib.no/sebra/Password/chg pwd?lang=english

Private machines:

If you need access from a private computer which is not administered by the IT-department you have to install Cisco AnyConnect Secure Mobility Client.

Link to installation of Cisco AnyConnect:


https://elv.uib.no/Terminalserver

Additional information for Mac users

After installation¹ of Cisco AnyConnect you have to manually copy the file tilgang_terminalserver.xml
(http://vedlegg.uib.no/?id=88621b43c53f81144d441c16912360db) into the folder /opt/cisco/anyconnect/profile/ on the Mac.

¹ You must be logged in as an user with administrator rights to install the software. For UoB MAC-machines see https://it.uib.no/en/Mac_OS_X:_Install-account

2. Install Remote Desktop Connection for Mac (App Store):



- 3. Connect to Cisco AnyConnect and start Remote Desktop Connection
- 4. In the "Edit Remote Desktop"- window, give the connection a name under Connection name, e.g. hrist or bigs
- 5. Type the server name under PC name (hrist.uib.no or bigs.uib.no)
- 6. Type your username (UIB\username) and password
- 7. Close the window ("Edit Remote Desktop")
- 8. Connect to the server by double-clicking on the connection under "My Desktop".

Problems/Questions

For problems or questions regarding the hrist-server contact Kari Juul, or register a problem on https://bs.uib.no/ (Select "Open an issue for: BRITA).

For problems or questions regarding other servers contact Jannicke Igland, or register a problem on https://bs.uib.no/(Select "Open an issue for: BRITA).