


Assignment 07

Use packet Tracer tool for configuration of 3 router network using one of the following protocol RIP/OSPF/BGP.

3 Router Network



PC Configuration

PC0

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.10.2

Subnet Mask 255.255.255.0

Default Gateway 192.168.10.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::202:17FF:FE09:3011

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

☐ Top

ROUTER 0 Configuration

FastEthernet

Router0

PhysicalConfigCLIAttributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

FastEthernet0/0

Port Status

Bandwidth

Duplex

MAC Address

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

On

100 Mbps10 Mbps

Auto

Half DuplexFull Duplex

Auto

0090.2B5A.652D

192.168.10.1

255.255.255.0

10

Serial

Router0

PhysicalConfigCLIAttributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

Serial2/0

Port Status

Duplex

Clock Rate

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

On

Full Duplex

1200

10.0.0.1

255.0.0.0

10

Router 1 Configuration

FastEthernet

Router1

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

FastEthernet0/0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☐ Full Duplex ☒ Auto

MAC Address 0001.97C2.B348

IP Configuration

IPv4 Address 192.168.20.1

Subnet Mask 255.255.255.0

Tx Ring Limit 10

Serial

Router1

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

Serial2/0

Port Status ☒ On

Duplex ☐ Full Duplex

Clock Rate 1200

IP Configuration

IPv4 Address 10.0.0.2

Subnet Mask 255.0.0.0

Tx Ring Limit 10

Router1

Physical
Config
CLI
Attributes

GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0

Serial3/0

Port Status
Duplex
Clock Rate

Full Duplex
1200

☒ On

IP Configuration
IPv4 Address
Subnet Mask

11.0.0.1
255.0.0.0

Tx Ring Limit
10

Router 3

FastEthernet

Router2

Physical
Config
CLI
Attributes

GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0

FastEthernet0/0

Port Status
Bandwidth
Duplex
MAC Address

☒ On

100 Mbps
10 Mbps
☒ Auto

Half Duplex
Full Duplex
☒ Auto


00D0.9797.D8B3

IP Configuration
IPv4 Address
Subnet Mask


192.168.30.1
255.255.255.0

Tx Ring Limit
10


SERIAL



ROUTER 1



ROUTER 2



The screenshot shows a terminal window titled "Router1". The terminal displays a series of configuration commands and their outputs. The commands include exiting configuration mode, configuring FastEthernet0/0, exiting, configuring Serial3/0, enabling it, and assigning the IP address 11.0.0.1. Subsequent messages indicate that the link state for Serial2/0 and Serial3/0 has changed to up, and the line protocol for all three interfaces (Serial2/0, Serial3/0, and FastEthernet0/0) has also changed to up. The configuration then moves to router mode to enable RIP, with networks 192.168.20.0, 10.0.0.0, and 11.0.0.0 being advertised. At the bottom of the window, there are "Copy" and "Paste" buttons and a "Top" link.

```
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#no shutdown
Router(config-if)#ip address 11.0.0.1 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#router rip
Router(config-router)#network 192.168.20.0
Router(config-router)#network 10.0.0.0
Router(config-router)#network 11.0.0.0
Router(config-router)#
```

☐ Top

ROUTER 3



The screenshot shows a terminal window titled "Router2" with tabs for "Physical", "Config", "CLI", and "Attributes". The "CLI" tab is active, showing the "IOS Command Line Interface". The terminal displays a series of configuration commands and their outputs. The commands include enabling the router, configuring the terminal, configuring FastEthernet0/0, exiting, configuring Serial2/0, enabling it, and assigning the IP address 10.0.0.3. Subsequent messages indicate that the link state for FastEthernet0/0 and Serial2/0 has changed to up, and the line protocol for both interfaces has also changed to up. The configuration then moves to router mode to enable RIP, with networks 192.168.30.0 and 11.0.0.0 being advertised. At the bottom of the window, there are "Copy" and "Paste" buttons and a "Top" link.

```
Would you like to enter the initial configuration dialog? [yes/no]:

Press RETURN to get started!

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
ip address 192.168.30.1 255.255.255.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#no shutdown
Router(config-if)#ip address 10.0.0.3 255.0.0.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#ip address 11.0.0.2 255.0.0.0
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#router rip
Router(config-router)#network 192.168.30.0
Router(config-router)#network 11.0.0.0
Router(config-router)#
```

☐ Top

PING



The screenshot shows a window titled "PC0" with tabs for "Physical", "Config", "Desktop", "Programming", and "Attributes". The "Desktop" tab is active, displaying a "Command Prompt" window. The Command Prompt shows the results of two ping commands. The first command is for 192.168.20.3, which shows a 25% loss of packets. The second command is for 192.168.20.2, which shows a 100% loss of packets. The Command Prompt also shows the results of a Control-C interrupt and a subsequent ping command for 192.168.20.2, which shows a 0% loss of packets.

```
PC0
Physical Config Desktop Programming Attributes
Command Prompt
Ping statistics for 192.168.20.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 15ms, Average = 8ms

C:\>ping 192.168.20.3

Pinging 192.168.20.3 with 32 bytes of data:

Request timed out.
Reply from 192.168.20.3: bytes=32 time=10ms TTL=126
Reply from 192.168.20.3: bytes=32 time=10ms TTL=126
Reply from 192.168.20.3: bytes=32 time=10ms TTL=126

Ping statistics for 192.168.20.3:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 10ms, Maximum = 10ms, Average = 10ms

C:\>ping 192.168.20.2

Pinging 192.168.20.2 with 32 bytes of data:

Ping statistics for 192.168.20.2:
    Packets: Sent = 1, Received = 0, Lost = 1 (100% loss),

Control-C
^C
C:\>ping 192.168.20.2

Pinging 192.168.20.2 with 32 bytes of data:

Reply from 192.168.20.2: bytes=32 time=12ms TTL=126
Reply from 192.168.20.2: bytes=32 time=10ms TTL=126
Reply from 192.168.20.2: bytes=32 time=10ms TTL=126
Reply from 192.168.20.2: bytes=32 time=10ms TTL=126

Ping statistics for 192.168.20.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 10ms, Maximum = 12ms, Average = 10ms

C:\>|
```

☐ Top