## Screen VT100/ANSI Terminal Emulator Cheat Sheet Default Keyboard Shortcuts

Shortcut	Command	Description
ctrl + a '	select	Prompt for a window name or number to switch to.
ctrl + a "	windowlist -b	Present a list of all windows for selection.
ctrl + a 0 9	select 0select 9	Switch to window number 09.
ctrl + a -	select -	Switch to the blank window.
ctrl + a ->	focus	Switch the input focus to the next region.
ctrl + a ctrl + a	other	Toggle to the window displayed previously.
ctrl + a a	meta	Send the command character ctrl + a to window.
ctrl + a A	title	Allow the user to enter a name for the current window.
ctrl + a b ctrl + b	break	Send a break to window.
ctrl + a B	pow_break	Reopen the terminal line and send a break.
ctrl + a ctrl + c ctrl + a c	screen	Create a new window with a shell and switch to that window.
ctrl + a C	clear	Clear the screen.
ctrl + a d ctrl + d	detach	Detach screen from this terminal.
ctrl + a D D	pow_detach	Detach and logout.
ctrl + a f ctrl + f	flow	Toggle flow on, off or auto.
ctrl + a F	fit	Resize the window to the current region size.
ctrl + a ctrl + g	vbell	Toggles screen's visual bell mode.
ctrl + a h	hardcopy	Write a hardcopy of the current window to the file "hardcopy.n".
ctrl + a H	log	Begins/ends logging of the current window to the file "screenlog.n".
ctrl + a i ctrl + i	info	Show info about this window.
ctrl + a k ctrl + k	kill	Destroy current window.
ctrl + a I ctrl + I	redisplay	Fully refresh current window.
ctrl + a L	login	Toggle this windows login slot. Available only if screen is configured to update the utmp database.

Shortcut	Command	Description
ctrl + a m ctrl + m	lastmsg	Repeat the last message displayed in the message line.
ctrl + a M	monitor	Toggles monitoring of the current window.
ctrl + a n ctrl + a ctrl + n	next	Switch to the next window.
ctrl + a N	number	Show the number (and title) of the current window.
ctrl + a     ←       ctrl + a     h       ctrl + a     p       ctrl + a     ctrl + p	prev	Switch to the previous window (opposite of ctrl+a n).
ctrl + a q ctrl + q	xon	Send a ctrl+q to the current window.
ctrl + a Q	only	Delete all regions but the current one.
ctrl + a r ctrl + r	wrap	Toggle the current window's line-wrap setting (turn the current window's automatic margins on and off).
ctrl + a s ctrl + s	xoff	Send a ctrl+s to the current window.
ctrl + a S	split	Split the current region into two new ones.
ctrl + a t ctrl + t	time	Show system information.
ctrl + a v	version	Display the version and compilation date.
ctrl + a ctrl + v	digraph	Enter digraph.
ctrl + a w ctrl + w	windows	Show a list of window.
ctrl + a W	width	Toggle 80/132 columns.
ctrl + a x ctrl + x	lockscreen	Lock this terminal.
ctrl + a X	remove	Kill the current region.
ctrl + a z ctrl + z	suspend	Suspend screen. Your system must support BSD-style job-control.
ctrl + a Z	reset	Reset the virtual terminal to its "power-on" values.
ctrl + a .	dumptermcap	Write out a ".termcap" file.
ctrl + a ?	help	Show key bindings.
ctrl + a ctrl + \	quit	Kill all windows and terminate screen.
ctrl + a :	colon	Enter command line mode.
ctrl + a [       ctrl + a ctrl + [       ctrl + a [	copy	Enter copy/scrollback mode.
ctrl + a ]	paste	Write the contents of the paste buffer to the stdin queue of the current window.

Shortcut	Command	Description
ctrl + a {           ctrl + a }	history	Copy and paste a previous (command) line.
ctrl + a >	writebuf	Write paste buffer to a file.
ctrl + a <	readbuf	Reads the screen-exchange file into the paste buffer.
ctrl + a =	removebuf	Removes the file used by ctrl + a < and ctrl + a >.
ctrl + a ,	license	Shows where screen comes from, where it went to and why you can use it.
ctrl + a _	silence	Start/stop monitoring the current window for inactivity.
ctrl + a *	displays	Show a listing of all currently attached displays.