







10.0.0.10 able to access instagram server 180.0.0.10




10.0.0.20 able to access instagram server 180.0.0.10




10.0.0.10 can ping instagram server 180.0.0.10




10.0.0.20 cant ping instagram server 180.0.0.10




10.0.0.20 can access facebook server 180.0.0.20 through browser




10.0.0.20 can access ssh of facebook server 180.0.0.20




10.0.0.10 can access sn site 192.52.234.100 through browser



10.0.0.20 can access sn site 192.52.234.100 through browser



10.0.0.10 can ping sn labs 192.52.234.200



10.0.0.10 can access sn labs 192.52.234.200 through browser


R1

```
Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^]'.


R1#
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#int e0/0
R1(config-if)#ip access-group 100 in
R1(config-if)#$t tcp 10.0.0.0 0.255.255.255 180.0.0.10 0.0.0.0 eq 80
R1(config)#
*Sep 23 09:21:28.188: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#access-list 100 permit imcp 10.0.0.10 0.0.0.0 180.0.0.10 0.0.0.0
      ^
% Invalid input detected at '^' marker.

R1(config)#access-list 100 permit icmp 10.0.0.10 0.0.0.0 180.0.0.10 0.0.0.0
R1(config)#exit
R1#
*Sep 23 09:23:54.800: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#$ 100 permit ssh 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 22
access-list 100 permit ssh 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 22
      ^
% Invalid input detected at '^' marker.


R1(config)#$ 100 permit tcp 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 22
R1(config)#$ 100 permit tcp 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 80
R1(config)#$t tcp 10.0.0.0 0.255.255.255 192.52.234.100 0.0.0.0 eq 80
R1(config)#$ 100 permit tcp 10.0.0.10 0.0.0.0 192.52.234.200 0.0.0.0 eq 80
R1(config)#$ 100 permit icmp 10.0.0.10 0.0.0.0 192.52.234.200 0.0.0.0
R1(config)#
```




11.0.0.10 can access instagram 180.0.0.10 through browser




11.0.0.20 can access instagram server 180.0.0.10 through browser




11.0.0.20 can access facebook server 180.0.0.20 through browser



11.0.0.10 can access facebook server 180.0.0.20 through browser



11.0.0.10 can ping facebook server 180.0.0.20



```
labs.surennetwork.com:31214 labs.surennetwork.com:31215
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 11.0.0.10
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 11.0.0.1

C:\Documents and Settings\user>ping 180.0.0.20

Pinging 180.0.0.20 with 32 bytes of data:

Reply from 180.0.0.20: bytes=32 time=3ms TTL=60
Reply from 180.0.0.20: bytes=32 time=2ms TTL=60
Reply from 180.0.0.20: bytes=32 time=2ms TTL=60
Reply from 180.0.0.20: bytes=32 time=2ms TTL=60

Ping statistics for 180.0.0.20:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 3ms, Average = 2ms

C:\Documents and Settings\user>ping 192.52.234.200


Pinging 192.52.234.200 with 32 bytes of data:

Reply from 192.52.234.200: bytes=32 time=6ms TTL=60
Reply from 192.52.234.200: bytes=32 time=3ms TTL=60
Reply from 192.52.234.200: bytes=32 time=2ms TTL=60
Reply from 192.52.234.200: bytes=32 time=3ms TTL=60


Ping statistics for 192.52.234.200:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 6ms, Average = 3ms

C:\Documents and Settings\user>
```


11.0.0.10 can ping sn labs server 192.52.234.200




11.0.0.10 can access sn labs server 192.52.234.200 through browser




11.0.0.20 can access sn labs server 192.52.234.200 through browser




11.0.0.20 can ping sn labs server 192.52.234.200



11.0.0.10 can access ssh of sn lab server



11.0.0.20 can access ssh of sn lab server



The screenshot shows a Windows XP desktop environment. A PuTTY terminal window is open, displaying the command prompt output for a Windows XP system. The terminal shows the IP configuration for the Ethernet adapter Local Area Connection, which has an IP address of 11.0.0.10, a subnet mask of 255.0.0.0, and a default gateway of 11.0.0.1. The terminal also shows the results of three ping commands: ping 10.0.0.10, ping 10.0.0.20, and ping 10.0.0.1. All three ping commands result in 'Destination net unreachable'.

```
labs.surennetwork.com:31214
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 11.0.0.10
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 11.0.0.1

C:\Documents and Settings\user>ping 10.0.0.10

Pinging 10.0.0.10 with 32 bytes of data:

Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.

Ping statistics for 10.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Documents and Settings\user>ping 10.0.0.20

Pinging 10.0.0.20 with 32 bytes of data:

Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.

Ping statistics for 10.0.0.20:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Documents and Settings\user>ping 10.0.0.1


Pinging 10.0.0.1 with 32 bytes of data:

Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.
Reply from 11.0.0.1: Destination net unreachable.

Ping statistics for 10.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Documents and Settings\user>
```

11.0.0.10 cant ping 10.0.0.10, 10.0.0.20, 10.0.0.1



11.0.0.20 cant ping 10.0.0.10, 10.0.0.20, 10.0.0.1

R2



```
Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.
```

```
*Sep 23 09:55:01.819: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to down
*Sep 23 09:55:01.828: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to down
*Sep 23 09:55:02.819: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to down
R2#
R2#
R2#
*Sep 23 09:55:02.828: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to down
R2#
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip access-group 100 in
R2(config-if)#exit
R2(config)#$ 100 permit tcp 11.0.0.0 0.255.255.255 180.0.0.10 0.0.0.0 eq 80
R2(config)#$ 100 permit tcp 11.0.0.0 0.255.255.255 180.0.0.20 0.0.0.0 eq 80
R2(config)#
*Sep 23 09:59:51.423: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config)#access-list 100 permit icmp 11.0.0.10 0.0.0.0 180.0.0.20 0.0.0.0
R2(config)#$ 100 permit icmp 11.0.0.10 0.0.0.0 192.52.234.200 0.0.0.0
R2(config)#access-list 100 permit ip 11.0.0.0 0.0.0.0 192.52.243.200 0.0.0.0
R2(config)#$ist 100 permit icmp 11.0.0.10 0.0.0.0 192.52.234.200 0.0.0.0
R2(config)#$ 100 deny ip 11.0.0.0 0.255.255.255 10.0.0.0 0.255.255.255
R2(config)#
```