


```
R1
R1(config)#exit
R1#
*Sep  1 15:05:24.917: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 5 2 4
R1(dhcp-config)#exit
R1(config)#
R1(config)#ip dhcp excluded
*Sep  1 15:08:29.166: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.100
R1(config)#exit
R1#
R1#
R1#
R1#
*Sep  1 15:08:42.076: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip dhcp pool DESIGN
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.100
R1(config)#exit
R1#
R1#
R1#
R1#
R1#
```

```

R1
R1(config)#ip dhcp excluded
*Sep  1 15:08:29.166: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.100
R1(config)#exit
R1#
R1#
R1#
R1#
*Sep  1 15:08:42.076: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip dhcp pool DESIGN
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.100
R1(config)#exit
R1#
R1#
R1#
R1#
R1#
*Sep  1 15:10:07.846: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration    Type
                Hardware address/
                User name
50.0.0.101      0100.5079.6668.cf   Sep 06 2026 10:44 PM Automatic
50.0.0.102      0100.5079.6668.d9   Sep 06 2026 10:45 PM Automatic
192.168.2.101   0150.ae34.0911.00   Sep 02 2026 08:40 PM Automatic
192.168.2.102   0100.5079.6668.da   Sep 02 2026 08:41 PM Automatic
R1#

```

```
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip add 192.168.2.1 255.255.255.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#int e0/1
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
R2(config)#exit
R2#
R2#
R2#
R2#
*Sep  1 15:06:38.809: %SYS-5-CONFIG_I: Configured from console by console
R2#
*Sep  1 15:08:17.972: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2#
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
```



VPC-1



Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.101/8 GW 50.0.0.1

VPC-1> █

VPC-2



Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.102/8 GW 50.0.0.1

VPC-2>

VPC-4



Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4> ip dhcp
DDORA IP 192.168.2.102/24 GW 192.168.2.1

VPC-4> █