

Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^']'.

```
SW1#
SW1#
SW1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
SW1(config)#vlan 10
SW1(config-vlan)#name DESIGN
SW1(config-vlan)#exit
SW1(config)#vlan 20
SW1(config-vlan)#name DEV
SW1(config-vlan)#exit
SW1(config)#
SW1(config)#int e0/0
SW1(config-if)#switchport access vlan 10
SW1(config-if)#exit
SW1(config)#int e0/1
SW1(config-if)#switchport access vlan 20
SW1(config-if)#exit
SW1(config)#
SW1(config)#exit
SW1#sh
*Sep 16 04:37:06.253: %SYS-5-CONFIG_I: Configured from console by console
SW1#show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Et0/2, Et0/3
10	DESIGN	active	Et0/0
20	DEV	active	Et0/1
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	


```
SW1#
SW1#
SW1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
SW1(config)#int e0/2
SW1(config-if)#switchport trunk encapsulation dot1q
SW1(config-if)#switchport mode trunk
SW1(config-if)#exit
SW1(config)#
SW1(config)#
SW1(config)#exit
```

SW2


```
Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^]'.

SW2#
SW2#
SW2#
SW2#
SW2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
SW2(config)#vlan 10
SW2(config-vlan)#name DESIGN
SW2(config-vlan)#exit
SW2(config)#vlan 20
SW2(config-vlan)#name DEV
SW2(config-vlan)#exit
SW2(config)#
SW2(config)#
SW2(config)#int e0/0
SW2(config-if)#switchport access vlan 10
SW2(config-if)#exit
SW2(config)#int e0/1
SW2(config-if)#switchport access vlan 20
SW2(config-if)#exit
SW2(config)#
*Sep 16 04:41:54.564: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
SW2(config)#int e0/2
SW2(config-if)#switchport trunk encapsulation dot1q
SW2(config-if)#switchport mode trunk
SW2(config-if)#exit
SW2(config)#
SW2(config)#
SW2(config)#show int trunk
      ^
% Invalid input detected at '^' marker.

SW2(config)#exit
SW2#sh
*Sep 16 04:48:32.368: %SYS-5-CONFIG_I: Configured from console by console
SW2#show int trunk
```



PC 1 10.0.0.10 → 10.0.0.20 (Vlan 10)



PC 2 20.0.0.10 —> 20.0.0.20 (Vlan 20)