

R1

```
Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^]'.

R1#
R1#
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#int e0/0
R1(config-if)#ip add 12.0.1.129 255.255.255.240
R1(config-if)#no sh
R1(config-if)#ex
R1(config)#exit
R1#
*Sep 13 11:36:49.025: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#int
*Sep 13 11:37:31.992: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#int e0/1
R1(config-if)#ip add 12.0.1.145 255.255.255.252
R1(config-if)#no sh
R1(config-if)#ex
R1(config)#exit
R1#
R1#
R1#
R1#
R1#
*Sep 13 11:39:21.257: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip route 0.0.0.0 0.0.0.0 12.0.1.146
R1(config)#exit
R1#
R1#
R1#
R1#
*Sep 13 11:42:04.480: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#int e0/0
R1(config-if)#ip dhcp helper-address 12.0.1.146
^
```

R2



```
Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.
```

```
R2#
```

```
R2#
```

```
R2#
```

```
R2#conf t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R2(config)#int e0/0
```

```
R2(config-if)#ip add 12.0.1.1 255.255.255.128
```

```
R2(config-if)#no sh
```

```
R2(config-if)#ex
```

```
R2(config)#int e0/1
```

```
R2(config-if)#ip add 12.0.1.149 255.255.255.252
```

```
R2(config-if)#no sh
```

```
R2(config-if)#ex
```

```
R2(config)#exit
```

```
R2#
```

```
R2#
```

```
R2#
```

```
*Sep 13 11:43:32.675: %SYS-5-CONFIG_I: Configured from console by console
```

```
R2#conf t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R2(config)#ip route 0.0.0.0 0.0.0.0 12.0.1.150
```

```
R2(config)#exit
```

```
R2#
```

```
R2#
```

```
R2#
```

```
*Sep 13 11:43:55.920: %SYS-5-CONFIG_I: Configured from console by console
```

```
R2#
```

```
*Sep 13 11:44:57.426: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
```

```
R2#
```

```
R2#
```

```
R2#conf t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R2(config)#int e0/0
```

```
R2(config-if)#ip helper-address 12.0.1.150
```

```
R2(config-if)#exit
```

```
R2(config)#
```

```
R2(config)#exit
```

```
R2#
```

```
*Sep 13 12:17:32.350: %SYS-5-CONFIG_I: Configured from console by console
```

```
R2#
```

R3

Trying 49.204.127.18...
Connected to labs.surennetwork.com.
Escape character is '^['.

R3#

R3#

R3#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#

*Sep 13 11:44:57.295: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

R3(config)#int e0/0

R3(config-if)#ip add 12.0.0.1 255.255.255.0

R3(config-if)#no sh

R3(config-if)#ex

R3(config)#int e0/1

R3(config-if)#ip add

% Incomplete command.

R3(config-if)#ip add 12.0.1.153 255.255.255.252

R3(config-if)#no sh

R3(config-if)#ex

R3(config)#exit

R3#

R3#

R3#

*Sep 13 11:46:21.936: %SYS-5-CONFIG_I: Configured from console by console

R3#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#ip route 0.0.0.0 0.0.0.0 12.0.1.154

R3(config)#exit

R3#

R3#

*Sep 13 11:46:45.560: %SYS-5-CONFIG_I: Configured from console by console

R3#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#int e0/0

R3(config-if)#ip helper-address 12.0.1.154

R3(config-if)#exit

R3(config)#

R3(config)#

R3(config)#exit

R3#

*Sep 13 12:23:17.256: %SYS-5-CONFIG_I: Configured from console by console

R3#

R4

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int e0/0
Router(config-if)#ip add 12.0.1.146 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int
*Sep 13 11:57:47.521: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
*Sep 13 11:57:48.524: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
Router(config)#int e0/1
Router(config-if)#ip add 12.0.1.150 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int e
*Sep 13 11:58:14.271: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up
*Sep 13 11:58:15.271: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up
Router(config)#int e0/2
Router(config-if)#ip add 12.0.1.154 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int e
*Sep 13 11:58:40.277: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to up
*Sep 13 11:58:41.280: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to up
Router(config)#int e0/3
Router(config-if)#ip add 129.70.1.66 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#int
*Sep 13 11:59:09.833: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to up
*Sep 13 11:59:10.833: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to up
Router(config)#int e1/0
Router(config-if)#ip add 129.70.1.70 255.255.255.252
Router(config-if)#no sh
Router(config-if)#ex
Router(config)#exit
Router#
*Sep 13 11:59:45.023: %LINK-3-UPDOWN: Interface Ethernet1/0, changed state to up
Router#
Router#
*Sep 13 11:59:45.183: %SYS-5-CONFIG_I: Configured from console by console
*Sep 13 11:59:46.024: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/0, changed state to up
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 12.0.1.128 255.255.255.240 12.0.1.145
Router(config)#ip route 12.0.1.0 255.255.255.128 12.0.1.149
```

R4

```
Router(config)#ip route 129.70.0.0 255.255.255.0 129.70.1.69
Router(config)#exit
Router#
Router#
Router#
Router#
*Sep 13 12:02:08.059: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool SNF1
Router(dhcp-config)#network 12.0.1.128 255.255.255.240
Router(dhcp-config)#default-router 12.0.1.129
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 12.0.1.129 12.0.1.135
Router(config)#exit
Router#
*Sep 13 12:03:40.519: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool SNF2
Router(dhcp-config)#network 12.0.1.0 255.255.255.128
Router(dhcp-config)#default-router 12.0.1.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 12.0.1.1 12.0.1.50
Router(config)#exit
Router#
*Sep 13 12:07:22.485: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool SNF3
Router(dhcp-config)#network 12.0.0.0 255.255.255.0
Router(dhcp-config)#default-router 12.0.0.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 12.0.0.1 12.0.0.100
Router(config)#exit
Router#
Router#
Router#
*Sep 13 12:10:15.097: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool
% Incomplete command.
```

R4

```
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 12.0.1.1 12.0.1.50
Router(config)#exit
Router#
*Sep 13 12:07:22.485: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool SNF3
Router(dhcp-config)#network 12.0.0.0 255.255.255.0
Router(dhcp-config)#default-router 12.0.0.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 12.0.0.1 12.0.0.100
Router(config)#exit
Router#
Router#
Router#
*Sep 13 12:10:15.097: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool
% Incomplete command.

Router(config)#ip dhcp pool NTF1
Router(dhcp-config)#network 129.70.1.0 255.255.255.192
Router(dhcp-config)#default-router 129.70.1.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 129.70.1.1 129.70.1.10
Router(config)#exit
Router#
*Sep 13 12:13:29.207: %SYS-5-CONFIG_I: Configured from console by console
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool NTF2
Router(dhcp-config)#network 129.70.0.0 255.255.255.0
Router(dhcp-config)#default-router 129.70.0.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 129.70.0.1 129.70.0.50
Router(config)#exit
Router#
Router#
Router#
*Sep 13 12:15:01.786: %SYS-5-CONFIG_I: Configured from console by console
Router#
```

Trying 49.204.127.18...

Connected to labs.surennetwork.com.

Escape character is '^['.

R5#

R5#

R5#

R5#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R5(config)#int e0/0

R5(config-if)#ip add 129.70.1.65 255.255.255.252

R5(config-if)#no sh

R5(config-if)#ex

R5(config)#int e0/1

R5(config-if)#ip add 129.70.1.1 255.255.255.192

R5(config-if)#no sh

R5(config-if)#ex

R5(config)#exit

R5#

*Sep 13 11:48:25.340: %SYS-5-CONFIG_I: Configured from console by console

R5#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R5(config)#

*Sep 13 11:50:49.351: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

R5(config)#ip route 0.0.0.0 0.0.0.0 129.70.1.66

R5(config)#exit

R5#

R5#

*Sep 13 11:51:17.552: %SYS-5-CONFIG_I: Configured from console by console

R5#

R5#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R5(config)#int e0/1

R5(config-if)#ip helper-address 129.70.1.66

R5(config-if)#exit

R5(config)#exit

R5#

R5#

*Sep 13 12:24:04.249: %SYS-5-CONFIG_I: Configured from console by console

R5#

```
R6#
R6#
R6#
R6#
R6#
R6#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R6(config)#ip add e0/0
      ^
% Invalid input detected at '^' marker.

R6(config)#int e0/0
R6(config-if)#ip add 129.70.1.69 255.255.255.252
R6(config-if)#no sh
R6(config-if)#ex
R6(config)#int e0/1
R6(config-if)#ip add 129.70.0.1 255.255.255.0
R6(config-if)#no sh
R6(config-if)#ex
R6(config)#exit
R6#
R6#ip
*Sep 13 11:55:10.144: %SYS-5-CONFIG_I: Configured from console by console
R6#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R6(config)#ip route 0.0.0.0 0.0.0.0 129.70.1.70
R6(config)#exit
R6#
R6#
R6#
*Sep 13 11:55:42.200: %SYS-5-CONFIG_I: Configured from console by console
R6#
*Sep 13 11:57:32.431: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R6#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R6(config)#int e0/1
R6(config-if)#ip helper-address 129.70.1.70
R6(config-if)#exit
R6(config)#
R6(config)#
R6(config)#exit
R6#
R6#
*Sep 13 12:26:01.071: %SYS-5-CONFIG_I: Configured from console by console
R6#
```











