


Send Message to Slack Channel or DMs

Flow Diagram



General Information

Process Type	Auto Launched Flow
Label	Send Message to Slack Channel or DMs
Status	Active
Description	Send Message to Slack Channel or DMs
Environments	Default
Interview Label	Send Message to Slack Channel or DMs {!\$Flow.CurrentDateTime}
Run In Mode	Default Mode
Builder Type (PM)	LightningFlowBuilder
Canvas Mode (PM)	AUTO_LAYOUT_CANVAS
Origin Builder Type (PM)	LightningFlowBuilder
Connector	ChannelORDirectMessage
Next Node	ChannelORDirectMessage

Variables

Name	Data Type	Is Collection	Is Input	Is Output	Object Type	Description
agentName	String	☐	☒	☐		Name of the Agent that sends the message
channelID	String	☐	☒	☐		ID of the channel to invite user to
message	String	☐	☐	☒		Output message
MessageToSend	String	☐	☒	☐		

Flow Nodes Details

CheckChannelExist

Type	Action Call
Label	CheckChannelExist
Action Type	Apex
Action Name	checkChannelExist
Flow Transaction Model	CurrentTransaction
Name Segment	checkChannelExist
Offset	0
Store Output Automatically	☒
Agent Name (input)	agentName
Channel Id (input)	channelID
Channel Name (input)	
Connector	ifChannelExist

Copy_1_of_Send_Slack_Message_Action_Fault_Join

Type	Action Call
Label	Copy 1 of Send Slack Message Action Fault Join
Action Type	Slack Post Message
Action Name	slackPostMessage
Flow Transaction Model	CurrentTransaction

Name Segment	slackPostMessage
Offset	0
Store Output Automatically	
Slack App Id For Token (input)	A03269G3DNE
Slack Workspace Id For Token (input)	T08LMTRBD2B
Slack Conversation Id (input)	C08MEA2DEJK
Slack Message (input)	message

JoinChannel

Type	Action Call
Label	JoinChannel
Action Type	Slack Join Channel
Action Name	slackJoinChannel
Fault Connector	Add Output to Message Fault Join
Flow Transaction Model	CurrentTransaction
Name Segment	slackJoinChannel
Offset	0
Slack App Id For Token (input)	A03269G3DNE
Slack Workspace Id For Token (input)	T08LMTRBD2B
Slack Conversation Id (input)	channelID
Connector	SendMessageToSlackChannelorDMs

Send_Slack_Message_Action_1

Type	Action Call
Label	Send Slack Message Action 1
Action Type	Slack Post Message
Action Name	slackPostMessage
Flow Transaction Model	CurrentTransaction
Name Segment	slackPostMessage
Offset	0

Store Output Automatically	✓
Slack App Id For Token (input)	A03269G3DNE
Slack Workspace Id For Token (input)	T08LMTRBD2B
Slack Conversation Id (input)	C08MEA2DEJK
Slack Message (input)	message

Send_slack_message_fault_send_message

Type	Action Call
Label	Send slack message fault send message
Action Type	Slack Post Message
Action Name	slackPostMessage
Flow Transaction Model	CurrentTransaction
Name Segment	slackPostMessage
Offset	0
Store Output Automatically	✓
Slack App Id For Token (input)	A03269G3DNE
Slack Workspace Id For Token (input)	T08LMTRBD2B
Slack Conversation Id (input)	C08MEA2DEJK
Slack Message (input)	message

SendMessageToSlackChannelorDMs

Type	Action Call
Label	Send Message to Slack Channel or DMs
Action Type	Apex
Action Name	SendSlackToChannel
Fault Connector	Add Output to Message fault send
Flow Transaction Model	CurrentTransaction
Name Segment	SendSlackToChannel
Offset	0
Store Output Automatically	✓

Agent Name (input)	agentName
Channel Id (input)	channelID
Message Text (input)	MessageToSend
Connector	Add Output to Message

SendSlackMessageActionFaultJoin

Type	Action Call
Label	Send Slack Message Action Fault Join
Action Type	Slack Post Message
Action Name	slackPostMessage
Flow Transaction Model	CurrentTransaction
Name Segment	slackPostMessage
Offset	0
Store Output Automatically	☒
Slack App Id For Token (input)	A03269G3DNE
Slack Workspace Id For Token (input)	T08LMTRBD2B
Slack Conversation Id (input)	C08MEA2DEJK
Slack Message (input)	\$Flow.FaultMessage

Add_Output_to_Message

Type	Assignment
Label	Add Output to Message
Connector	Send Slack Message Action 1

Assignments

Assign To Reference	Operator	Value
message	Assign	Send message to user or channel {!channelID} success

Add_Output_to_Message_Fault_Join

Type	Assignment
Label	Add Output to Message Fault Join

Connector	SendSlackMessageActionFaultJoin
-----------	---

Assignments

Assign To Reference	Operator	Value
message	Assign	Invite User In Slack Channel : Can't join {!channelID}

Add_Output_to_Message_fault_send

Type	Assignment
Label	Add Output to Message fault send
Connector	Send_slack_message_fault_send_message

Assignments

Assign To Reference	Operator	Value
message	Assign	Send message to user or channel: failed {!channelID}

AddOutputChannelNotFound

Type	Assignment
Label	Add Output Channel not Found
Connector	Copy_1_of_Send_Slack_Message_Action_Fault_Join

Assignments

Assign To Reference	Operator	Value
message	Assign	Invite User In Slack Channel : Channel doesn't exist

ChannelORDirectMessage

Type	Decision
Label	Channel OR Direct Message
Default Connector	SendMessageToSlackChannelorDMs
Default Connector Label	Direct Message

Rule Channel (Channel)

Connector	CheckChannelExist
Condition Logic	and

Condition Id	Left Value Reference	Operator	Right Value
1	channelID	Starts With	C

ifChannelExist

Type	Decision
Label	ifChannelExist
Default Connector	AddOutputChannelNotFound
Default Connector Label	channelNotFound

Rule channelExist (channelExist)

Connector	JoinChannel
Condition Logic	and

Condition Id	Left Value Reference	Operator	Right Value
1	CheckChannelExist.channelExists	Equal To	

Documentation generated from branch documentation by [sfdx-hardis](#), featuring [salesforce-flow-visualiser](#)

Dependencies

- [ChallengeAfterUpdateChallengeLaunch](#)
- [ChallengeAfterUpdateSlackChanCreation](#)