$things_to_do$

November 21, 2018

Contents

1	Tasks											
	1.1	1.1 TODO Finish doing the gamma surfaces for all planes for pure titanium										
		1.1.1 Checking the convergence criteria	2									
		1.1.2 Notes on the model	3									
		1.1.3 DONE Implement Homogenous Shear boundary con-										
		ditions for gamma surface calculation	5									
	1.2	TODO Python script: remove include statements -> One file.	5									
	1.3	TODO Summarise UCL DFT lectures	5									
	1.4	4 TODO Write first paragraph of Literature review										
		1.4.1 TODO Summarise Stacking Faults and write review .	5									
		1.4.2 TODO Write up the tight binding fitting of oxygen										
		and an explanation for paramagnetism	5									
		1.4.3 TODO Summarise dislocations and Oxygen interac-										
		tions (review)	5									
	1.5	TODO Write summary of org-mode	5									
	1.6											
		Titanium graphically										
		1.6.1 Pair potentials in the code	5									
		1.6.2 Bond integrals from the	8									
	1.7	DONE Investigate why rmaxh changes energy	8									
	1.8	DONE Show supercell of BOP working	10									
2	Ger	General notes of codes.										
	2.1	Pair potentials in the code	10									
	2.2	Notes for the gamma surfaces	13									
		2.2.1 Relaxing in the	13									
	2.3	Ti Swarm fitting	13									

3	Useful Notes 14								
3.1 Org-mode									
3.2 Physics									
		3.2.1 Hartree-Fock	14						
4	\mathbf{DF}'	T Lectures UCL	15						
	4.1	David Bowler O(N) DFT	15						
		4.1.1 Types of Exchange-correlation Functionals	15						
	4.2	Jochen Blumberger: Molecular dynamics	17						
		4.2.1 Introduction	17						
		4.2.2 Born-Oppenheimer approximation	17						
		4.2.3 Molecular Dynamics	18						
	4.3	Matteo Salvalglio: Enhanced Sampling	19						
		4.3.1 Introduction	19						
		4.3.2 Ergodic principle	20						
		4.3.3 Collective variables	20						
	4.4	Useful definitions of Thermodynamic potentials	21						
5		-mode cheat sheet	22						
1	T	asks							
1.		FODO Finish doing the gamma surfaces for all planfor pure titanium.	es						
1.	1.1	Checking the convergence criteria							
	• N	ow checking the convergence criteria.							
	1. H	ow the lattice parameters change with the fineness of the k mesh							
		• Maybe with a less fine k mesh the lattice parameters becowerse.	me						
	• SOLUTION: The lattice parameters do not change that much under								
	differences with the k mesh. File with change of the lattice parameters with k mesh. a vs nk $c_{\rm vsnk}$ $e_{\rm vsnk}$								

(a) What if rmaxh is smaller or larger?

Variation of total energy of hcp at minimum lattice parameters with nk




Figure 1: Variation of energy with k mesh.

• If rmaxh is is smaller (say rmaxh = 6.7 bohr) then we get the same results.

Ш

- Data: a_{hcp} small rmaxh, c_{hcp} small rmaxh, e_{hcp} small rmaxh.
- If rmaxh is larger (rmaxh = 20 bohr), all possible interactions must be included then. And so we get the same results.
- Data: a_{hcp} large rmaxh, c_{hcp} large rmaxh, e_{hcp} large rmaxh
- 2. How does rmaxh change the lattice parameters?
 - (a) How does rmaxh change the energy of a supercell
 - How does the number of neighbours change and what is the relation between rmaxh and larger cell sizes.

1.1.2 Notes on the model.

It seems that there is a lot of charge moving around when doing the relaxations. I think that this may be due to the fact that there is no Hubbard U interactions, a parameter for the coulomb interaction, which stops the charges from moving freely.

• TBE control file is currently set to this:




Figure 2: Variation of a hcp with k mesh.

TBE: nbas = 128 nspec = 1 verb 31

TB: rmaxh = 20, m-stat: F-P rlx-vol, rho

bz: metal




Figure 3: Variation of c hcp with k mesh.

- 1.1.3 DONE Implement Homogenous Shear boundary conditions for gamma surface calculation.
- 1.2 TODO Python script: remove include statements -> One file.
- 1.3 TODO Summarise UCL DFT lectures.
- 1.4 TODO Write first paragraph of Literature review
- 1.4.1 TODO Summarise Stacking Faults and write review
- 1.4.2 TODO Write up the tight binding fitting of oxygen and an explanation for paramagnetism.
- 1.4.3 TODO Summarise dislocations and Oxygen interactions (review)
- 1.5 TODO Write summary of org-mode
- 1.6 DONE Look at the range of the bond integrals we have in Titanium graphically.
- 1.6.1 Pair potentials in the code
 - Pair potential is constructed by makupp.f.

of total energy of hcp at minimum lattice parame




Figure 4: Variation of energy with k mesh.

- This calls vppder.f which actually evaluates the pair potential at that point
- In makupp.f, if in the range of $r_1 < r < r_c$, then augmentative/multiplicative polynomial is used.
 - To make this polynomial pcut45.f is used.
 - Depending on the degree of polynomial we have this structure:

```
rr = r1 - r2
    xr1 = x - r1
    xr2 = x - r2

    c = val*rr*rr
    if (n == 5) then
pnorm = rr**(-5)
a = (0.5d0*curv*rr - 3d0*slo)*rr + 6d0*val
b = (slo*rr - 3d0*val)*rr
    elseif (n == 4) then
pnorm = rr**(-4)
```




Figure 5: Variation of a hcp with k mesh.

- So the form of the polynomial used is

*
$$P_5(x) = (x - r_2)^3 P_2(x)$$
*
$$P_2(x) = a(x - r_1)^2 + b(x - r_1) + c$$
*
$$a = \frac{1}{(r_1 - r_2)^5} \left\{ \frac{1}{2} (r_1 - r_2)^2 f''(r_1) - 3(r_1 - r_2) f'(r_1) + 6f(r_1) \right\}$$




Figure 6: Variation of c hcp with k mesh.

*
$$b = \frac{1}{(r_1 - r_2)^4} \left\{ f'(r_1) * (r_1 - r_2) - 3f(r_1) \right\}$$
*
$$\frac{1}{(r_1 - r_2)^5} x$$
*
$$c = \frac{f(r_1)}{(r_1 - r_2)^3}$$

* Where f(x) is the function that needs to be cut

• Current model has this

Ti,Ti: type 2 (Exp. decay), $V(d) = a \exp(-b d)$ SSS sps sds pds pdp dds ddp ddd pps ppp ${\tt coeff:}$ 0.00 0.00 0.00 0.00 0.00 0.00 0.00 -2.75 1.84 -0.46 0.00 0.00 0.00 0.00 0.00 0.00 0.00 0.71 0.71 0.71 decay: cutoff type 2 (multiplicative), 5th order polynomial, range [r1, rc]

SSS	sps	pps	ppp	sds	pds	pdp	dds	ddp	ddd	
r1:	0.00	0.00	0.00	0.00	0.00	0.00	0.00	6.20	6.20	6.20
rc:	0.00	0.00	0.00	0.00	0.00	0.00	0.00	8.50	8.50	8.

1.6.2 Bond integrals from the

 \bullet So bond integrals from titanium look like this, from this file plot_{bondintegrals}.py




Figure 7: Bond integrals with multiplicative polynomial cutoffs.

1.7 DONE Investigate why rmaxh changes energy

- Variation of rmaxh does not change the energy
- Obviously the number of neighbours changes with rmaxh.
- Conclusion: rmaxh only determines what atoms are its neighbours.
- This is the file which investigates this: check_{rmaxhenergynumberneighbours}
- \bullet Here is the data: Energy data for energy vs rmaxh rmaxh data for energy/ $n_{\rm neighbours}$ vs rmaxh $n_{\rm neighbours}$ for $n_{\rm neighbours}$ vs rmaxh
- The output pictures are this:




Figure 8: Bond integrals with multiplicative polynomial cutoffs: zoomed in.

1.8 DONE Show supercell of BOP working

2 General notes of codes.

2.1 Pair potentials in the code

- Pair potential is constructed by makupp.f.
- This calls vppder.f which actually evaluates the pair potential at that point
- In makvpp.f, if in the range of $r_1 < r < r_c$, then augmentative/multiplicative polynomial is used.
 - To make this polynomial pcut45.f is used.
 - Depending on the degree of polynomial we have this structure:




Figure 9: Variation of energy with change in rmaxh

 $P_5(x) = (x - r_2)^3 P_2(x)$

*




Figure 10: Variation of number of neighbours with change in rmaxh

*
$$P_{2}(x) = a(x - r_{1})^{2} + b(x - r_{1}) + c$$
*
$$a = \frac{1}{(r_{1} - r_{2})^{5}} \left\{ \frac{1}{2} (r_{1} - r_{2})^{2} f''(r_{1}) - 3(r_{1} - r_{2}) f'(r_{1}) + 6f(r_{1}) \right\}$$
*
$$b = \frac{1}{(r_{1} - r_{2})^{4}} \left\{ f'(r_{1}) * (r_{1} - r_{2}) - 3f(r_{1}) \right\}$$
*
$$\frac{1}{(r_{1} - r_{2})^{5}} x$$
*
$$c = \frac{f(r_{1})}{(r_{1} - r_{2})^{3}}$$

• Current model has this

* Where f(x) is the function that needs to be cut

Ti, Ti:

```
type 2 (Exp. decay), V(d) = a \exp(-b d)
  SSS
          sps
                                 sds
                                         pds
                                                 pdp
                                                        dds
                                                                ddp
                                                                        ddd
                 pps
                         ppp
                                                                               -0.46
coeff:
                 0.00
                         0.00
                                 0.00
                                         0.00
                                                 0.00
                                                        0.00
                                                               -2.75
          0.00
                                                                        1.84
         0.00
                 0.00
                         0.00
                                 0.00
                                         0.00
                                                 0.00
                                                        0.00
                                                                0.71
                                                                        0.71
                                                                                0.71
decay:
cutoff type 2 (multiplicative), 5th order polynomial, range [r1,
                                                                        rc]
          sps
                 pps
                                 sds
                                         pds
                                                 pdp
                                                        dds
                                                                ddp
                                                                        ddd
                         ppp
r1:
          0.00
                 0.00
                         0.00
                                 0.00
                                         0.00
                                                 0.00
                                                        0.00
                                                                6.20
                                                                        6.20
                                                                                6.20
rc:
          0.00
                 0.00
                         0.00
                                 0.00
                                         0.00
                                                 0.00
                                                        0.00
                                                                8.50
                                                                        8.50
                                                                                8.
```

- So bond integrals from titanium look like this
- Bond integrals with multiplicative polynomial cutoffs.
- Bond integrals with multiplicative polynomial cutoffs: zoomed in.

2.2 Notes for the gamma surfaces

- Seems like some atoms are missing in the site file when it is being read in to the.
- This means that there are some erroneous forces that make the program exit.
 - SOLUTION: Coordinates were not in units of alat.

2.2.1 Relaxing in the

- To relax in the need to modify:
 - Ewald tolerance: ewtol
 - * This can generally be set quite low: 1d-14
 - Convergence criteria:
 - * gtol: The tolerance in the force for convergence e.g. 1d-8
 - * xtol: The tolerance in the atomic position e.g. 1d-8.

2.3 Ti Swarm fitting.

 Here used fitting with uniform weights across all target quantities without a regularisation of the parameters.

- It can be seen that the lattice parameters aren't as good as they could be. This calls for the use of weighted parameters.
- Have now started weighted parameter search for the best parameters with regards to titanium.

Build Objective Function

...with L1 norm

Objective function: 563

Objective Function = 563.2340263379571

Stopping search: Swarm best position change less than 1e-08

[0.34606728 -0.22330935 65.79555644 0.52284417 0. -0.62229341 1.98315066]

563.2340263379571

Quantity	predicted	target	squared diff.	p_{norm}	weight	objective
a_{hcp} :	4.744693	5.576790	0.692385	0.832097	1.000000	1.524483
c_{hcp} :	7.495518	8.852101	1.840316	1.356583	1.000000	3.196899
c_{11} :	174.924630	176.100000	1.381495	1.175370	1.000000	2.556865
c ₃₃ :	190.161490	190.500000	0.114589	0.338510	1.000000	0.453099
c_{44} :	54.517320	50.800000	13.818465	3.717320	1.000000	17.535784
c_{12} :	65.010403	86.900000	479.154446	21.889597	1.000000	501.044043
c_{13} :	73.335501	68.300000	25.356271	5.035501	1.000000	30.391772
a_{omega} :	7.331279	8.732543	1.963543	1.401265	1.000000	3.364808
c_{omega} :	4.768459	5.323431	0.307994	0.554972	1.000000	0.862966
u_{omega} :	1.000025	1.000000	0.000000	0.000025	1.000000	0.000025
$DeltaE_{Ohcp}$:	-1.170318	-0.734754	0.189716	0.435564	1.000000	0.625281
a_{bcc} :	5.331467	6.179489	0.719140	0.848021	1.000000	1.567162
bandwidth:	0.325300	0.426000	0.010140	0.100700	1.000000	0.110840

3 Useful Notes

3.1 Org-mode

(setq org-latex-create-formula-image-program 'dvipng)

3.2 Physics

3.2.1 Hartree-Fock

• Hartree-Fock is a method of calculating the energy of a configuration with exact exchange.

- This is done by essentially putting everything we don't know into the kinetic energy functional.
- Hamiltonian is split into contributions:

$$\hat{H} = \hat{T} + \hat{V}_{\text{ext}} + \hat{G}$$

 $-\hat{G} = \hat{J} - \hat{K}$

 $-\hat{J}$ is the coulombic interaction:

$$\left\langle \mathbf{r}\right|\hat{J}\left|\mathbf{n}\right\rangle =\int\frac{\left\langle \mathbf{r}\right|n
ight
angle }{\left|\mathbf{r}-\mathbf{r}'\right|}d\mathbf{r}$$

- So

$$E_{\rm H} = \int \frac{\rho \mathbf{r} \rho \mathbf{r}'}{|\mathbf{r} - \mathbf{r}'|}$$

- This includes fictitious self-interaction of electron density.
- The Exchange functional removes this part, thus lowering the energy
- This method is used in Hybrid DFT. This corrects band gaps mainly. But there are also problems.

4 DFT Lectures UCL

4.1 David Bowler O(N) DFT

4.1.1 Types of Exchange-correlation Functionals

1. LDA

- The electron density is the same as a uniform electron gas.
- Exchange is Slater.
- Still parameterised (Ceperly). Parameters from Quantum Monte-Carlo calculations.

2. GGA

• The gradient of the electron density is included in functional.

• Have the reduced density

$$\frac{\nabla n(\mathbf{r})}{n(\mathbf{r})}$$

.

(a) Perdew-Burke-Ernzerhof

•

$$E_{\rm x} = \int n(\mathbf{r}) \epsilon_{\rm xc}[n(\mathbf{r})] F_{\rm x}(S) d\mathbf{r}$$

•

$$E_{\rm c} = \int n[\epsilon_{\rm c} + H(n, S)] d{\bf r}$$

• These integrals are then fitted to various limits.

3. Hybrid Functionals

- These are functionals to correct the self-interaction energy that is apparent in the previously mentioned functionals.
- The Hartree term

$$V_{
m H} = \int rac{
ho({f r})}{|{f r}-{f r}'|} d{f r}$$

- The exchange term cancels the celf interaction.
- Generally only a part of this Hartree-Fock calculation is included in the function otherwise it is not stable.

DFT speed is limited by how it can find the energies of the system we are interested in. Diagonalisation is inherently an $\mathcal{O}(N^3)$ process.

To actually build the hamiltonian it is of $\mathcal{O}(N^2)$. Solving is $\mathcal{O}(N^3)$.

How do we solve for DFT? Generally it depends on the choice of functional we have. Hybrid functionals almost scale as $\mathcal{O}(N^4)$ due to the inclusion of exact exchange interaction by Hartree-Fock. Because of this exact exchange, there are better band gaps .

The $\mathcal{O}(N)$ DFT generally comes because of the manipulation of sparse matrices. Insead of matrix multiplication being of $\mathcal{O}(N^3)$ we can have matrix multiplication being of $\mathcal{O}(N)$.

The reason we can essentially do $\mathcal{O}(N)$ is that in the Kohn-Sham equations, the density is actually a local function $(n(\mathbf{r}), \text{ not } n(\mathbf{r} - \mathbf{r}'))$ This means that in theory we can actually have a theory which sufficiently

describes the dynamics of a given system with an electron density that is local in space. In many DFT codes however, the electron density is non-local $(n(\mathbf{r} - \mathbf{r}'))$, and this slows down the calculation. To actually make it $\mathcal{O}(N)$, we have to have range cutoffs for the interactions of the atoms. This means that the hamilitonian is sparse as quite a lot of the elements are zero such that we can use methods that involve $\mathcal{O}(N)$ multiplication.

When it comes to Structural relaxation there are a few things that come to mind when structures are not converging: there is usually only one atom that has some huge force on it. Consider the boundary conditions.

For faster diagonalisation of the hamiltonian matrix it may be useful to look at methods such as Krylov-Subsapace, Lanczos and foldedspectrum methods.

4.2 Jochen Blumberger: Molecular dynamics

4.2.1 Introduction

- Molecular dynamics is important. (Even at 0K there is a zero point energy of vibration).
- Need theory to see how atoms move

4.2.2 Born-Oppenheimer approximation

- Have hamiltonian that consists of interaction between:
 - nucleus-nucleus
 - nucleus-electron
 - electron-electron
- First assumption is that we can write the eigenfunction of this large hamiltonian as a product state consisting of an electronic ground state and nuclear eigenstate.
- Second approximation is that we are able to say, as the mass of the ion $M_I \sim 1000 m_e$ then we can say that the kinetic energy term of with regard to the nucleus positions will be small.
- From this we can say that the action of this nuclear kinetic energy operator on the electronic eigenstate is small.

• This means we can neglect the **electronic** wavefunction, and work with the equation

$$\hat{H}\Phi(\mathbf{R}) = E_{\mathbf{R}}^0\Phi(\mathbf{R})$$

- Where $E_{\mathbf{R}}^0$ is the ground state energy hypersurface from the electronic wavefunction. We get this from DFT calculations.
- Even now we can only really calculate 8 degrees of freedom for the Nuclear wavefunction.

4.2.3 Molecular Dynamics

- 1. Verlet Algorithm
 - This algorithm simply uses the forward and backward derivative of the nuclear positions and adds them together to get a formula for the position.

$$\mathbf{R}_{I}(t+\delta t) = 2\mathbf{R}_{I} - \mathbf{R}_{I}(t-\delta t) + \frac{f_{I}(t)}{M_{I}}\delta t^{3}\mathcal{O}(\delta t^{4})$$

$$\mathbf{\dot{R}}_I(t) = \frac{1}{2\delta t} [\mathbf{R}_I(t+\delta t) - \mathbf{R}_I(t-\delta t)] + \mathcal{O}(\delta t^3)$$

- This causes a problem however: the velocity is calculated a step after that of the positons. So this leads to the Velocity Verlet algorithm.
- The timestep for these algorithms is on the order of 1fs, such that one can have adequate resolution of atomic vibrations $(sim10^{-14}s^{-1})$, so period is around 10fs
- 2. Velocity Verlet Algorithm
 - For this algorithm the forward derivative with respect to nuclear positions is used with a calculation of the force at a later time.
 - Then the taylor expansion of the position at time t is used with the terms of later time.

$$\mathbf{R}_I(t+\delta t) = \mathbf{R}_I(t) + \dot{\mathbf{R}}_I\delta t + rac{f_I(t)}{M_I}\delta t^3 + \mathcal{O}(\delta t^3)$$

$$\dot{\mathbf{R}}_I(t+\delta t) = \dot{\mathbf{R}}_I(t) + \frac{1}{2M_I}[\mathbf{f}_I(t+\delta t) + \mathbf{R}_I(t)] + \mathcal{O}(\delta t^3)$$

- 3. How to calculate the forces
 - Use the Hellmann-Feynman theorem.

$$\mathbf{f}_{I} = \left\langle \psi_{\mathbf{R}}^{0} \right| \frac{\partial}{\partial \mathbf{R}_{I}} \hat{H} \left| \psi_{\mathbf{R}}^{0} \right\rangle$$

• This is derived using the parameter λ , assuming that the Hamiltonian depends on this lambda.

4. Carr-Parinello MD

- This is a form of molecular dynamics where both the positions and the orbitals are used as dynamical variables.
- An *orbital velocity* and (orbital mass) is defined.
- Using this one can create trajectories that propagate both the ionic positions and orbitals in time.
- This circumvents the need for self-consistent cycles to obtain the correct orbitals, but:
 - The dynamics are not always in the ground state energy.
 - The necessary time step is decreased by about 3-4 times (speed increase is 5-10 times from removal of self-consistency)

4.3 Matteo Salvalglio: Enhanced Sampling

4.3.1 Introduction

- Have a phase space that is 6N dimensional (3 spatial positions and 3 components of momenta).
- Each point in this phase space is a microstate.
- The microstates sampled are from the Canonical Ensemble (N,V,T).
- Can define partition function

$$Q(N, V, T) = \frac{1}{N! h^{3N}} \int \mathrm{d}x e^{-\beta \mathbf{H}(\mathbf{x})}$$

• Can have thermodynamic potential defined from this:

$$A(N, V, T) = -k_B ln(Q(N, V, T))$$

• What we really want to do is obtain an observable quantity from this high dimensional space.

4.3.2 Ergodic principle

- This is the principle which states that the amount of time that microstates of the same energy spend in a configuration is proportional to the volume of phase space they occupy.
- In other words, every microstate is equiprobable.
- So the observable quantity:

$$O = \langle O \rangle = \lim_{t \to \inf} \frac{1}{t} \int_0^t \mathrm{d}t O(x(t)),$$

where O(x(t)) is the instantaneous realisation of O(x)

4.3.3 Collective variables

- Collective variables are just functions that depend on the coordinates (CVs) $S(\mathbf{R})$
- Given a collective variable we can define a probability density p(S)
- So

$$p(S) = \int d\mathbf{R} [\delta(S(\mathbf{R}) - S)] p(\mathbf{R})$$

•

$$p(\mathbf{R}) = \frac{e^{-\beta U(\mathbf{R})}}{\int e^{-\beta U(\mathbf{R})} d\mathbf{R}},$$

where the denominator is the configuration integral \mathcal{Z}

- 1. Calculating free energies from collective variables
 - Free energy profile is then just

$$F(S) = -k_B T ln(p(S))$$

• The free energy change between configurations A and B are then just

$$\Delta F_{AB} = -k_B T ln \left\{ \frac{\int_B p(S) dS}{\int_A p(S) dS} \right\}$$

• Can think of these configurations as spikes in p(S) and troughs in F(S), with some form of energy barrier between them. This region can then be split in to regions belonging to A and B, from which the separate integrations can be evaluated.

- This energy barrier is on the order of kT
- If not, then simulation times will be very large to be able to obtain a result that obeys ergodicity.
- Can use a biased potential for the sampling and work backwards to obtain the actual probability density.

4.4 Useful definitions of Thermodynamic potentials

- Internal Energy:
 - The capacity to do work and release heat.
 - The energy contained withing the system excluding kinetic energy.
 - Equation:

$$U = \int (t dS - p dV + \sum_{i} \mu_{i} dN_{i})$$

- $-\Delta U$ is the total energy added to the system.
- Natural variables: $\{S, V, \{N_i\}\}$
- Helmholtz Free Energy:
 - The energy at constant temperature and pressure.
 - The capacity to do mechanical plus non-mechanical work
 - Equation:

$$F = U - TS$$

- $-\Delta F$ is the total work done on the system.
- Natural variables: $\{T, V, \{N_i\}\}$
- Gibbs Free Energy:
 - The capacity to do non-mechanical work.
 - The maximum amount of non-expansion work.
 - The energy at constant temperature and pressure.
 - Gibbs energy is the thermodynamic potential that is minimized when a system reaches chemical equilibrium at constant pressure and temperature.
 - Equation:

$$G = U + pV - TS$$

- ΔG is the total non-mechanical work done on the system.
- Natural variables: $\{T, p, \{N_i\}\}$

• Enthalpy:

- The capacity to do non-mechanical work plus capacity to release heat.
- Equation:

$$H = U + pV$$

- ΔH is the total non-mechanical work and heat added to the system.
- Natural variables: $\{S, p, \{N_i\}\}$

5 org-mode cheat sheet

- New TODO: M-<shift>-<ret>
- Done TODO: C-c C-t
- Links: [[][] [link] then [description]
- Open link: Move over cursor and do C-c C-o
- Link to local files:
 - Open file (C-x C-f) then do C-c l,
 - then go back to org file and do C-c C-l (e.g. Upgrade_{report plus notes})
- \bullet To remove window in buffer C-x 0
- Overview of document <shift>-<TAB> to condense to titles.
- Can have global todo list
- < s TAB expands to a 'src' code block.
- < l TAB expands to:
- If I want more help I can go to the org-mode manual