STRSoftware Test Report



Reported by: Tomer Darmon

Verified by: Gal Matalon – Automation College

Table of Contents

Purpose	3
Application Overview	3
TestRail STD	4
TestRail Print Screen	14
Metrics	15
Recommendations	18
Conclusion	18
Bugs List	19
Bug Reports	20

Purpose

The document represents the findings after testing the mobile application "Instagram" which used as a popular social media platform of sharing photos and videos among people who follow each other through this application and contents that matches each profile user interests.

The tests cases examine every feature test by different section on the application: the profile tab takes the user own page where it contains the personal content , the story and reels tabs provides experience of shared content by other followers, the explore tab used for searching other users or any content and the home tab used for watching posts and videos of the followed accounts .

The application suits to content creators, photographers, companies or brands and anyone who want to share content from their life in a social media platform.

Application Overview

The Instagram mobile app is used as a Native application which can be downloaded from the app store where the individual can share and view his own content or other depending on the interests he is interested about and follow.

The contents can be as posts or videos that share ideas, thoughts, promotional content or any captured moment from everyday life when the followers can like it or add a comment to the published content.

STD by TestRail

<u>ID</u>	<u>Title</u>	Created By	<u>Priority</u>	Section
<u>C204</u>	Download and test the app from the application Store.	Tom D.	Medium	Install the Instagram App
<u>C205</u>	Verify that the installation was downloaded successfully without errors.	Tom D.	Medium	Install the Instagram App
<u>C420</u>	Uninstall and remove the app to make sure that all the data is deleted	Tom D.	Medium	Install the Instagram App
<u>C421</u>	Checking the time to install the app from the App store	Tom D.	Medium	Install the Instagram App
<u>C206</u>	Launch the app and check if the app launches without any errors	Tom D.	Medium	Launch the Instagram app
<u>C422</u>	Testing the CPU and the battery life	Tom D.	Medium	Launch the Instagram app
<u>C207</u>	Verify that the app correctly requests and handles camera access permissions	Tom D.	Medium	App Premissions
<u>C208</u>	Make sure that the app is asking and identify your current location	Tom D.	Medium	App Premissions
<u>C211</u>	Test the App if it shows the location when I'm offline	Tom D.	Medium	App Premissions
<u>C209</u>	Sign up the app by using Facebook	Tom D.	Medium	Sign Up
<u>C210</u>	Sign up the app by using your Email or your phone number	Tom D.	Medium	Sign Up
<u>C212</u>	Verify we get an error message when the email is not written completely	Tom D.	Medium	Sign Up
<u>C213</u>	Enters an invalid email format without @	Tom D.	Medium	Sign Up
<u>C214</u>	Test the app when the email address field is left empty	Tom D.	Medium	Sign Up
<u>C219</u>	Verify that the error messages are clear	Tom D.	Medium	Sign Up
<u>C220</u>	Sign up with an email that is already associated with another existing account	Tom D.	Medium	Sign Up
<u>C221</u>	Make sure that the system sends a verification code to the email or phone number	Tom D.	Medium	Sign Up
<u>C222</u>	Write wrong verification code and make sure you get an error message	Tom D.	Medium	Sign Up
<u>C412</u>	Write too short verification code and make sure you get an error message	Tom D.	Medium	Sign Up
<u>C413</u>	Write too long verification code and make sure you get an error message	Tom D.	Medium	Sign Up

<u>C228</u>	Enter a weak password such as short password with 2 characters	Tom D.	Medium	Sign Up
<u>C230</u>	Write invalid phone number	Tom D.	Medium	Sign Up
<u>C417</u>	Try to sign up the app with a different old phone which has old hardware	Tom D.	Medium	Sign Up
<u>C215</u>	Login with a valid email and a correct password	Tom D.	Medium	Login
<u>C216</u>	Log in with a valid email but incorrect password	Tom D.	Medium	Login
<u>C217</u>	Ensure that after we logged in with the right details, the correct name or nickname is written at the user page	Tom D.	Medium	Login
<u>C218</u>	Ensure there are tabs which are written next to each text box that tells what to write inside	Tom D.	Medium	Login
<u>C223</u>	Trying to log out and then log in the app again	Tom D.	Medium	Login
<u>C224</u>	Log in with a correct email and password but with incorrect case "WorkThisWay"	Tom D.	Medium	Login
<u>C225</u>	Trying to log in but with empty email field	Tom D.	Medium	Login
<u>C226</u>	Press on the tab "Forgot Password" and try to reset the password	Tom D.	Medium	Login
<u>C414</u>	Verify that choosing the English language will display "Instagram" menu in English	Tom D.	Medium	Login
<u>C227</u>	Trying to login several times with incorrect details and see what happens	Tom D.	Medium	Login
<u>C415</u>	Pressing the "Menu" in two different users accounts	Tom D.	Medium	Login
<u>C416</u>	Pressing on the setting of the "Story" to switch the camera tab side	Tom D.	Medium	Login
<u>C251</u>	Press on the "Search" tab	Tom D.	Medium	Search Tab
<u>C252</u>	Put a name inside the "Search" tab and see if you enter the profile	Tom D.	Medium	Search Tab
<u>C253</u>	Enters characters that does not match any existing content	Tom D.	Medium	Search Tab
<u>C254</u>	Try to clear all the search content by pressing the "X"	Tom D.	Medium	Search Tab
<u>C255</u>	Search any content in the "Search" tab and check that it shows under options for posts, places, accounts	Tom D.	Medium	Search Tab
<u>C256</u>	Type a name in the Search and press on "Accounts" in order to see that only "Accounts" are display	Tom D.	Medium	Search Tab

<u>C257</u>	Use the # with the content for a search and see if the results show relevant posts that matches	Tom D.	Medium	Search Tab
<u>C258</u>	Search for places and see if we get locations and photos of the location	Tom D.	Medium	Search Tab
<u>C259</u>	Enter to a profile after pressing the "Accounts" tab	Tom D.	Medium	Search Tab
<u>C260</u>	Press on the "Tags" tab and choose one of the hashtag pages	Tom D.	Medium	Search Tab
<u>C261</u>	Press on "Places" tab and choose a location and its relevant content	Tom D.	Medium	Search Tab
<u>C262</u>	Typing in the "Search" tab and see if Instagram complete the type automatically based on previous searches	Tom D.	Medium	Search Tab
<u>C263</u>	Press on the "Search" tab and see if we have recommended posts	Tom D.	Medium	Search Tab
<u>C264</u>	Press on one of the recommended posts and see if it's display	Tom D.	Medium	Search Tab
<u>C265</u>	Follow one of the users in the "Accounts" tab and then unfollow	Tom D.	Medium	Search Tab
<u>C266</u>	Start typing a name of a place and see if it's the name is automatically completed	Tom D.	Medium	Search Tab
<u>C267</u>	Type a search name and see if the latest searches are display below	Tom D.	Medium	Search Tab
<u>C268</u>	Type a name in the "Search" tab and then switch between the titles under (Top, Account, Tag, Places)	Tom D.	Medium	Search Tab
<u>C269</u>	Try to make a search when the internet connection is disconnected	Tom D.	Medium	Search Tab
<u>C270</u>	Search a location and see under the tab "Places" all the nearest results by my location	Tom D.	Medium	Search Tab
<u>C271</u>	Press on "Clear all" tab and verify that all the content was deleted	Tom D.	Medium	Search Tab
<u>C272</u>	Check that a verified name profile has a blue checkmark next to its name in the "Accounts" subsection	Tom D.	Medium	Search Tab
<u>C231</u>	Refresh the feed by pulling down the page	Tom D.	Medium	Home
<u>C232</u>	Try to scroll down and up the feed and see if the content changed	Tom D.	Medium	Home
<u>C233</u>	Click twice to like a post on the feed	Tom D.	Medium	Home
<u>C234</u>	Unlike a post that you liked	Tom D.	Medium	Home
<u>C235</u>	Press the comment field and leave a comment	Tom D.	Medium	Home
<u>C236</u>	It takes a few times to navigate in between the posts feeds by swiping left and right	Tom D.	Medium	Home

<u>C237</u>	Verify that videos posts are working once you click them	Tom D.	Medium	Home
<u>C238</u>	Click on Mute and Unmute tab of the video to see if the sound is going off/on	Tom D.	Medium	Home
<u>C239</u>	Press on a profile icon at the top of the Home tab to view a story	Tom D.	Medium	Home
<u>C240</u>	Swipes down while viewing a story to exit the story	Tom D.	Medium	Home
<u>C241</u>	Press on Save or Share on a post in the feed	Tom D.	Medium	Home
<u>C242</u>	Enter to one of the profiles by tapping their name	Tom D.	Medium	Home
<u>C243</u>	Disconnect and then connect again the internet connection while scrolling through the feed	Tom D.	Medium	Home
<u>C244</u>	Check if the Likes under a post are counted	Tom D.	Medium	Home
<u>C245</u>	Scroll down until you reach to the end of the feed	Tom D.	Medium	Home
<u>C246</u>	After a video is finished press on "Watch again"	Tom D.	Medium	Home
<u>C247</u>	After a video is finished press on the "Watch more reels"	Tom D.	Medium	Home
<u>C248</u>	Check if you get notifications of new posts by the followed accounts	Tom D.	Medium	Home
<u>C249</u>	Check if ads are being published on your feed by scrolling down	Tom D.	Medium	Home
<u>C250</u>	View a story and react to it by using one of the emojis or send a comment	Tom D.	Medium	Home
<u>C273</u>	Verify that when pressing on the "Reels" tab it will leads us to the right place	Tom D.	Medium	Reels
<u>C274</u>	Swiping up and down "Reels" videos	Tom D.	Medium	Reels
<u>C275</u>	Play and Paus the video and see the reaction	Tom D.	Medium	Reels
<u>C276</u>	Like a "Reel" video by tapping twice or press the heart icon	Tom D.	Medium	Reels
<u>C277</u>	Comment on a "Reel" video	Tom D.	Medium	Reels
<u>C278</u>	Share a "Real" video	Tom D.	Medium	Reels
<u>C279</u>	Save a "Real" video	Tom D.	Medium	Reels
<u>C280</u>	Taps on the audio name or icon used in a Reel and check if other Reels use the same audio	Tom D.	Medium	Reels
<u>C281</u>	Follow/Unfollow "Reel" user account	Tom D.	Medium	Reels
<u>C282</u>	Create a "Reel" video	Tom D.	Medium	Reels

<u>C283</u>	Add music from the Instagram library to the Reel video	Tom D.	Medium	Reels
<u>C284</u>	Test the filter effects for the Reel video	Tom D.	Medium	Reels
<u>C285</u>	Test the speed of the Reel video that you created	Tom D.	Medium	Reels
<u>C286</u>	Add a text to the Reel video	Tom D.	Medium	Reels
<u>C287</u>	Publish the Reel video you made	Tom D.	Medium	Reels
<u>C288</u>	Search for Reel videos from the "Reels" tab in the Explore field	Tom D.	Medium	Reels
<u>C290</u>	Check if you can see sponsored Reels video while browsing and use interactive elements	Tom D.	Medium	Reels
<u>C291</u>	Check the Reel video on different browsing network experience (Wi Fi, 2G)	Tom D.	Medium	Reels
<u>C292</u>	Report a Reel video by pressing the "Report" option	Tom D.	Medium	Reels
<u>C293</u>	Blocking a Reel creator by pressing the option "Block"	Tom D.	Medium	Reels
<u>C294</u>	Testing the Accessibility options while viewing a Reel video	Tom D.	Medium	Reels
<u>C295</u>	Trying to record a Reel video longer than the time duration	Tom D.	Medium	Reels
<u>C296</u>	Access the camera from Instagram	Tom D.	Medium	Camera
<u>C297</u>	Switch between Front to Rear camera	Tom D.	Medium	Camera
<u>C298</u>	Take a photo using the camera	Tom D.	Medium	Camera
<u>C299</u>	Record a video using the camera	Tom D.	Medium	Camera
<u>C300</u>	Using the filter or effect before taking a photo or recording a video	Tom D.	High	Camera
<u>C301</u>	Use the settings of the camera such as flash	Tom D.	Medium	Camera
<u>C302</u>	Press the gallery icon inside the camera and see if you can choose other existing videos/photos	Tom D.	Medium	Camera
<u>C303</u>	Pressing the "Cancel" button while taking a photo or a video	Tom D.	Medium	Camera
<u>C304</u>	Take a photo or a video and try to save it	Tom D.	Medium	Camera
<u>C305</u>	Use the timer to take a photo	Tom D.	Medium	Camera
<u>C306</u>	Create a video by using the "Boomerang" feature and if it's plays in loops	Tom D.	Medium	Camera
<u>C309</u>	Check if the app request permissions to use the camera	Tom D.	Medium	Camera

<u>C310</u>	Tap the "Gallery" icon to enter the gallery from the Instagram	Tom D.	Medium	Gallery
<u>C311</u>	Check that the photos are display in the gallery	Tom D.	Medium	Gallery
<u>C312</u>	Select a video from the gallery and see that it displays	Tom D.	Medium	Gallery
<u>C314</u>	Share the photo or video on your feed	Tom D.	Medium	Gallery
<u>C315</u>	Share a photo or a video from your gallery to your stories	Tom D.	Medium	Gallery
<u>C317</u>	Make sure you can navigate to your albums folder through the gallery	Tom D.	Medium	Gallery
<u>C318</u>	Try to upload several photos at the same time	Tom D.	Medium	Gallery
<u>C322</u>	Add a tag to an uploaded photo/video	Tom D.	Medium	Gallery
<u>C323</u>	Uploading successfully a large video/photo from the gallery	Tom D.	Medium	Gallery
<u>C324</u>	Press on the Story tab at the top of the Home page	Tom D.	Medium	Story
<u>C325</u>	Tap a Story to view it	Tom D.	Medium	Story
<u>C326</u>	Tap the right side of the Story to go to the next Story or left side to go to the previous one	Tom D.	Medium	Story
<u>C327</u>	Watch a story and swipe to the left to skip to the next account's Stories	Tom D.	Medium	Story
<u>C328</u>	Tap and hold the screen to pause the Story	Tom D.	Medium	Story
<u>C329</u>	Press the speaker icon to mute and unmute the Story	Tom D.	Medium	Story
<u>C330</u>	Swipe up and select icon to react the Story	Tom D.	Medium	Story
<u>C331</u>	Send a message as a response to the Story	Tom D.	Medium	Story
<u>C332</u>	Play a Story that has a link and see if the link opens in the browser or external browser	Tom D.	Medium	Story
<u>C333</u>	Taps the "Your Story" icon and adds a photo or video	Tom D.	Medium	Story
<u>C334</u>	Enter the Story camera and uses features like Boomerang and upload the content to the Story	Tom D.	Medium	Story
<u>C335</u>	Add a sticker to the uploaded Story such as location, questions, poll, hashtag	Tom D.	Medium	Story
<u>C336</u>	Add a text to the Story using font type and colours	Tom D.	Medium	Story


<u>C337</u>	Add music to the Story from the Instagram music library	Tom D.	Medium	Story
<u>C338</u>	Add a previously posted Story with a Story you Highlighted on your profile	Tom D.	Medium	Story
<u>C339</u>	Check who has viewed my Story that i published	Tom D.	Medium	Story
<u>C340</u>	Choose from the Story settings the option to hide the Story from specific followers or show it only to close ones	Tom D.	Medium	Story
<u>C341</u>	Delete a Story before it will disappear in 24 hours	Tom D.	Medium	Story
<u>C342</u>	Share a Story you made in your Instagram feed	Tom D.	Medium	Story
<u>C343</u>	Share a Story from another user	Tom D.	Medium	Story
<u>C344</u>	Try to watch expired Story	Tom D.	Medium	Story
<u>C345</u>	Watch a Story from the archive to view past Stories	Tom D.	Medium	Story
<u>C346</u>	Press on the "Report" button to report a content by tapping the three dots and selecting "Report"	Tom D.	Medium	Story
<u>C347</u>	Block or mute another user's Story from the feed	Tom D.	Medium	Story
<u>C348</u>	See notifications if someone replied to one of my Stories	Tom D.	Medium	Story
<u>C349</u>	Open the DM inbox by tapping the DM icon	Tom D.	Medium	Direct Message (DM)
<u>C350</u>	Send a text message	Tom D.	Medium	Direct Message (DM)
<u>C351</u>	Open the conversation to see the chat history	Tom D.	Medium	Direct Message (DM)
<u>C352</u>	Send an image from the gallery.	Tom D.	Medium	Direct Message (DM)
<u>C353</u>	Send a video from the gallery	Tom D.	Medium	Direct Message (DM)
<u>C354</u>	Send a voice message	Tom D.	Medium	Direct Message (DM)
<u>C355</u>	Send a GIF in a chat	Tom D.	Medium	Direct Message (DM)
<u>C356</u>	React back with a heart icon by double tap	Tom D.	Medium	Direct Message (DM)
<u>C357</u>	Send a message and then try to remove it after you sent it	Tom D.	Medium	Direct Message (DM)
<u>C358</u>	Create a group chat with several users	Tom D.	Medium	Direct Message (DM)

<u>C359</u>	Mute a conversation	Tom D.	Medium	Direct Message (DM)
<u>C360</u>	Try to block a user from the DM	Tom D.	Medium	Direct Message (DM)
<u>C361</u>	Delete a conversation	Tom D.	Medium	Direct Message (DM)
<u>C362</u>	Share a post in the DM conversation	Tom D.	Medium	Direct Message (DM)
<u>C363</u>	View a message request from someone who is not in your friends list	Tom D.	Medium	Direct Message (DM)
<u>C364</u>	Accept/decline a message request	Tom D.	Medium	Direct Message (DM)
<u>C365</u>	Try to move a message to the Archive/General	Tom D.	Medium	Direct Message (DM)
<u>C366</u>	Start a video call from the video icon in the DM	Tom D.	Medium	Direct Message (DM)
<u>C367</u>	Sending a photo/video that can only be viewed once and then disappears	Tom D.	Medium	Direct Message (DM)
<u>C368</u>	Try to report a conversation	Tom D.	Medium	Direct Message (DM)
<u>C369</u>	Forward message to another user	Tom D.	Medium	Direct Message (DM)
<u>C370</u>	Mark a conversation as unread	Tom D.	Medium	Direct Message (DM)
<u>C371</u>	Send a message when there is no internet connection	Tom D.	Medium	Direct Message (DM)
<u>C372</u>	Send a large file in a DM and receive an error message	Tom D.	Medium	Direct Message (DM)
<u>C373</u>	Checks if there is a sign when the recipient has read a message	Tom D.	Medium	Direct Message (DM)
<u>C374</u>	Taps the heart icon on the home screen to see latest notifications	Tom D.	Medium	Notifications Tab
<u>C375</u>	Receives a notification when someone likes our post	Tom D.	Medium	Notifications Tab
<u>C376</u>	Receives a notification when someone comments on our post.	Tom D.	Medium	Notifications Tab
<u>C377</u>	Receives a notification when someone follows us	Tom D.	Medium	Notifications Tab
<u>C378</u>	View a notification when someone mentioned us in a post or comment	Tom D.	Medium	Notifications Tab
<u>C379</u>	Receive a notification for a new message	Tom D.	Medium	Notifications Tab
<u>C380</u>	Receives a notification when someone reacts to our story that we posted	Tom D.	Medium	Notifications Tab

<u>C381</u>	Receives a notification when someone likes our comment	Tom D.	Medium	Notifications Tab
<u>C382</u>	We will get notification when someone shares our post	Tom D.	Medium	Notifications Tab
<u>C383</u>	Check the functional of the notifications filter	Tom D.	Medium	Notifications Tab
<u>C384</u>	Clear the notifications by swiping them or tap the clear button	Tom D.	Medium	Notifications Tab
<u>C385</u>	Receive notifications while the app is minimized	Tom D.	Medium	Notifications Tab
<u>C386</u>	Turn off the notifications and see if you receive any notification	Tom D.	Medium	Notifications Tab
<u>C387</u>	Receive notifications when someone new is following you	Tom D.	Medium	Notifications Tab
<u>C388</u>	Trying to access the notifications without an internet connection	Tom D.	Medium	Notifications Tab
<u>C389</u>	Receives a notification when we are tagged in a post	Tom D.	Medium	Notifications Tab
<u>C390</u>	Scroll in between the notifications	Tom D.	Medium	Notifications Tab
<u>C418</u>	Receiving messages through "Whatsapp" app while using "Instagram"	Tom D.	Medium	Notifications Tab
<u>C419</u>	Receiving phone call on "Whatsapp" while using "Instagram"	Tom D.	Medium	Notifications Tab
<u>C391</u>	Tap on the profile icon in the bottom right corner	Tom D.	Medium	Profile tab
<u>C392</u>	Check the profile information, profile picture, bio, and website link	Tom D.	Medium	Profile tab
<u>C393</u>	Edit the profile information such as bio/username	Tom D.	Medium	Profile tab
<u>C394</u>	Edit the profile photo by choosing a photo from the gallery	Tom D.	Medium	Profile tab
<u>C395</u>	Check for posts that you were tagged, and they are displayed on your grid	Tom D.	Medium	Profile tab
<u>C396</u>	Navigate to the "saved" post and see if you are able to view them	Tom D.	Medium	Profile tab
<u>C397</u>	Navigate to the "Reels" section in the personal profile	Tom D.	Medium	Profile tab
<u>C398</u>	Add a story highlight to the profile	Tom D.	Medium	Profile tab
<u>C399</u>	View the followers list by tapping on the "Followers" tab	Tom D.	Medium	Profile tab
<u>C400</u>	View the following list by tapping the "Followers" tab	Tom D.	Medium	Profile tab

<u>C401</u>	Enter the settings menu by pressing the three-line icon in the top right corner.	Tom D.	Medium	Profile tab
<u>C402</u>	Share your profile by tapping the menu three-line icon at the top and choose "Share" feature	Tom D.	Medium	Profile tab
<u>C403</u>	Press the "Your Activity" tab inside the menu three-line icon and check for your interactions	Tom D.	Medium	Profile tab
<u>C404</u>	Check if the account is changed in the settings between public to private	Tom D.	Medium	Profile tab
<u>C405</u>	Remove a post from the profile and check if it moved to the archive section by the settings	Tom D.	Medium	Profile tab
<u>C406</u>	View all the different tabs on the profile including Posts, Tagged, Reels	Tom D.	Medium	Profile tab
<u>C407</u>	Try to save a bio that passed the characters limit and see if we get an error message	Tom D.	Medium	Profile tab
<u>C408</u>	Website link can be shown in the bio after you write it	Tom D.	Medium	Profile tab
<u>C409</u>	Enter a non-existing website to the bio	Tom D.	Medium	Profile tab
<u>C410</u>	Check for mutual followers when you're visiting another profile through their follower's tab	Tom D.	Medium	Profile tab
<u>C411</u>	Try to enter the profile without connection to the internet	Tom D.	Medium	Profile tab
<u>C427</u>	Check if removed photos were saved after re-installing the app	Tom D.	Medium	Profile tab
<u>C423</u>	Testing the breaking point of the server depending on users amount	Tom D.	Medium	General App Test
<u>C424</u>	Testing whether the app's details were saved after it crashed and attempting to recover.	Tom D.	Medium	General App Test
<u>C425</u>	API testing weather the server replies correctly	Tom D.	Medium	General App Test
<u>C426</u>	Testing the App with the "Auto-rotate" mode	Tom D.	Medium	General App Test
<u>C428</u>	Testing the App by using one hand to navigate	Tom D.	Medium	General App Test

TestRail Print Screen




Metrics

Test Cases Status

The test cases in the app shows the result of how many cases passed or failed and how many were untested through the tests. As it shown, most of the tests passed and only a few failed.


Passed	Failed	Untested	Total
188	24	4	216



Severity Bugs Status


The column displays the different severities level of the bugs that were tested and found on the Instagram app. As it shown most of the severities are major and minor.

S1-Show	S2-	S3-	S4-	S5-	
Stopper	Critical	Major	Minor	Low	Total
0	0	18	5	1	24



<u>Defect Distribution – Modul Wise</u>

	Functionality	Interrupts	UI/UX	Localization	Campatibility	Total
S1-Show Stopper	0	0	0	0	0	0
S2- Critical	0	0	0	0	0	0
S3 - Major	9	2	6	0	1	18
S4 - Minor	0	1	3	0	0	4
S5 - Low	1	0	0	1	0	2
Total	10	3	9	1	1	24



Recommendations

- 1. The application keeps saving my data even though I marked not to save it before I logged out.
- **2.** I recommend checking the app when it comes to notifications while the internet is disconnected, and the videos are still displayed
- **3.** Tapping the "Like" button and tap back to "Dislike" won't take the number down on a Reel video
- **4.** Uncomfortable way to pause a Reel video by pressing and not letting go the finger, therefore it's better to change the settings for this mode in the app
- **5.** I recommend fixing the "Live" mode if a user would like to display a live video since it was not functioning
- **6.** The app doesn't rotate when I chose the option automatic rotation on my mobile device, I would recommend fixing it since it will add more enjoyable and user-friendly experience for the user in some of the contents
- **7.** When it comes to accessibility using, I recommend having much more options than only Captions and translation or the Dark mode option, such as voice control for example when the text can be heard or adjusting font size of the text for people with disabilities in order to make the use much easier for them.

Conclusion

After reviewing the tests that were done and the bugs that were found on "Instagram" mobile application, I can say that most of the bugs are in between Major to Minor severity level and most of the bugs are functional and UI/UX which affect the app when it comes to usability and performance.

While there were not any bugs that were found as on Critical level or Show Stopper, I can only see a place for improvements when it comes to the user experience.

As a result, I recommend releasing the app.

Bugs List

- [IMA-1] <u>Uninstall the app gives me a message that my data will be deleted but it's still saved</u> when you install the app again
- [IMA-2] <u>Turning off my Internet connection and the App is still able to show my current location when I'm creating a "Story"</u>
- [IMA-3] After logging out and choosing not to save my info, the App still remembers my username when i log back in
- [IMA-4] Choosing English language won't change all tabs to English in the app
- [IMA-5] Pressing the menu for two different Instagram users will show different results
- [IMA-6] Switching side of camera icon in the toolbar doesn't react as should
- [IMA-7] Invalid search term does not display "no results" message on Instagram
- [IMA-8] Receiving limit error message after 15 followers instead of 200 on Instagram
- [IMA-9] Not a disconnection message displayed after searching with the internet turned off
- [IMA-10] Photo navigation requires multiple swipes to move smoothly
- [IMA-11] Video posts continue playing without notification after disconnected internet
- [IMA-12] Pressing on the tab "Watch more reels" will play the same reel again
- [IMA-13] Tapping on the Reel video will only mute it instead of pausing it
- [IMA-14] Tapping twice on Reel video that i liked won't dislike my like
- [IMA-15] The speed control functionality in the Reels videos is behaving in reverse
- [IMA-16] Changing the network connection affects the ability to browse videos on Reels
- [IMA-17] Filming on "Live" mode is not working
- [IMA-18] The timer option isn't displayed in the "Post" and "Story" mode
- [IMA-19] Having "Boomerang" video in "Reels" takes many steps
- [IMA-20] Differences in the option "View once" while viewing a photo on a mobile and Web
- [IMA-21] The app doesn't count the numbers of "Followers" as it should
- [IMA-22] <u>Top menu missing after pressing "Profile" tab requires navigation through "Home"</u> tab to access it
- [IMA-23] Instagram limits the bio to 150 characters, but it limits me to write 124 characters
- [IMA-24] The app doesn't rotate when I press on "Auto rotate" mode

Bug Reports

[IMA-1] Uninstall the app gives me a message that my data will be deleted but it's still saved when you install the app again Created: 08/Sep/24 Updated: 09/Sep/24

Status: To Do

Project: Instagram Mobile App


Type: Bug Priority: Medium

Reporter: <u>Tomer Darmon</u> **Assignee:** Unassigned

Environment: OS : Android

Device : One Plus 11 5G OS Version : Android 14

Attachments:



Description

Severity1:

Steps to Reproduce:

- 1. After launching the "Instagram" app press on its icon on your home screen or in the app drawer
- 2. Press and hold the icon and tap on "Uninstall" and then "Ok"
- 3. Enter the Google app store and download the "Instagram" app again
- 4. Launched the app and write your username that you registered before with the same password
- 5. Enter to your profile and check the posts, Stories, Reels and tags

Actual Result:

After uninstalling the app and receiving a message that my data would be deleted, Instagram shows all my posts, stories, reels, and tags after reinstalling

Expected Result:


I will expect that after uninstalling the "Instagram" app from my device and re-installing it back again, the app won't remember my account and i won't be able to see my previous data

[IMA-2] <u>Turning off my Internet connection and the App is still able to show my current location</u> when I'm creating a "Story" Created: 08/Sep/24 Updated: 08/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Press the "+" icon in the bottom middle
- 3. Choose the "Story" mode and take a video or a photo
- 4. Press the "Sticker" icon at the top and turn off the internet connection
- 5. Press on "Location" tab
- 6. View the current places that the app is showing you

Actual Result:

The app shows me my current location even though that i turned off the internet connection before **Expected Result**:


I will expect after turning off the location the app won't show me my current location

[IMA-3] After logging out and choosing not to save my info, the App still remembers my username when i log in back again Created: 08/Sep/24 Updated: 11/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. Enter the Instagram app
- 2. Press on your profile photo
- 3. Enter your correct password
- 4. After login to the app, log out from your account
- 5. Tap on your profile picture in the bottom right
- 6. Tap your username again and then tap on the three lines in the top right corner
- 7. Go to "Settings and privacy"
- 8. Scroll down and tap "Log Out"
- 9. On the new message to save your login info, choose "Not now"
- 10. Press the Log out tab
- 11. Enter the app again

Actual Result:

The Instagram app saved my details even though i chose not to save it before i logout.

Expected Result:

I will expect that after logout and choosing not to save my info for the next time i'm entering, the app won't save my details.


[IMA-4] Choosing English language won't change all tabs to English in the app

Created: 08/Sep/24 Updated: 08/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. Enter to the "Instagram" app
- 2. Enter the menu and press "Settings and privacy"
- 3. Scroll down to the tab "Language" and choose English
- 4. Go back to menu and chose the tab "Your activity"

Actual Result :

After selecting English as a language, i will enter to "Your activity" tab and it will be displayed in Hebrew

Expected Result:

I will expect after selecting English language, everything will be displayed in English.


[IMA-5] Pressing the menu for two different Instagram users will show different results.

Created: 08/Sep/24 Updated: 08/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- Enter Instagram app with first user (donny_vee1)
- 2. Press on the "Home" tab at the bottom left and then the "Profile" tab on the bottom right
- 3. Press on the menu at the top right corner
- 4. Choose the tab "Settings and Privacy"
- 5. Enter the "Instagram" app with the second user (mr_no_one81)
- 6. Pressing on your profile photo at the bottom right
- 7. Press on the "Home" tab at the bottom left and then the "Profile" tab on the bottom right
- 8. Press the menu at the top right

Active Result:

When pressing the menu at one profile "donny_vee1" it will lead me to a window with different tabs options while in the second profile "mr_no_one1" when i press the menu it will lead me directly to the "Setting and activity"

Expected Result:

I will expect to get the same result with the two different profiles

[IMA-6] Switching side of camera icon in the toolbar doesn't react as should

Created: 09/Sep/24 Updated: 09/Sep/24

Status: To Do


Project: Instagram Mobile App

Type:BugPriority:MediumReporter:Tomer DarmonAssignee:Unassigned

Environment: OS : Android

Device : One Plus 11 5G OS Version : Android 14

Attachments:



Description

Severity1:

Steps to Reproduce:

- 1. Enter Instagram app
- 2. Press the "+" tab in the middle bottom of the page
- 3. Choose the "Story" option in the bottom of the page
- 4. Swipe up the page and see the camera icon on the last side
- 5. Press on the top right side on the settings icon
- 6. Under "Camera tools" switch the camera to the right side
- 7. Go back to the home page and enter again to the "Story"
- 8. Swipe up and check which side is the "Camera" icon

Actual Result:


The "Camera" icon is not being switched to the right side of the toolbar as i chose in the "Story" settings

Expected Result:

I will expect that the camera will display at the side that I chose

[IMA-7] Invalid search term does not display "no results" message on Instagram Created: 09/Sep/24 Updated: 09/Sep/24 Status: To Do Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. 1.Enter the Instagram app
- 2. Tap on the "Search" icon (magnifying glass) at the bottom page
- 3. In the new search page enter a term that randomly won't show any result like: "non exist content"

Actual Result:

I don't receive any error message from the app after typing a non-existed content in the search **Expected Result**:

I will expect to receive a message that says "No result" or will tell me that the result doesn't match to my search

[IMA-8] Receiving limit error message after 15 followers instead of 200 on Instagram

Created: 09/Sep/24 Updated: 09/Sep/24

Status: To Do


Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android		

Environment: OS : Android

Device : One Plus 11 5G OS Version : Android 14

Attachments:



Severity1: S3 - Major

Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Press on the "Search" icon at the bottom page(magnifying glasses)
- 3. Type a name of a user in the "Search" tab ("Carina Söderlund")
- 4. Press on one of the profile users
- 5. Press on the "Follow" tab

Actual Result :

When pressing the "Follow" tab, i get a message that tells me "Try Again Later" and Instagram limited my following people while i followed only 15 people and Instagram limit 200 following for a day. The limit was for a minute and then i could continue.

Expected Result:

I expect i will be able to press on the "Follow" tab of the profile i typed and then press twice on the "Follow" tab to unfollow the profile


[IMA-9] No disconnection message displayed after searching with the internet turned off

Created: 09/Sep/24 Updated: 12/Sep/24

Status: To Do

Project: Instagram Mobile App

Type:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. Enter the "Instagram" app
- 2. Press on the magnifying glass icon at the bottom of the page
- 3. Turn off the wifi connection on the mobile device
- 4. Type a name "Don Dokken" to search in the "Search" text box
- 5. Press on the "Search" tab on your device
- 6. Turn on the wifi back and continue the search

Actual Result:

After turning off the wifi connection, i didn't receive any error message about internet connection **Expected Result**:

I will expect to receive an error message for internet disconnection or a notification to try later

[IMA-10] Photo navigation requires multiple swipes to move smoothly

Created: 09/Sep/24 Updated: 09/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned

Environment: OS : Android

Device : One Plus 11 5G OS Version : Android 14

Attachments:



Severity1: S4 - Minor

Description

Steps to Reproduce:

- 1. 1.Enter the "Instagram" app
- 2. Scroll to one of the posts which is a photo and has several photos in the post (Under each photo there is a dot)
- 3. Swipe to the left to move the photos to the next one until you reach to the end
- 4. Swipe to the right to move back to the first photo

Actual Result:

It takes a few times to swipes especially when you swipe fast in between the post photos **Expected Result**:

I would expect that the navigating behaving will be smoothly in between the photos and i won't need to press a few times on same photo to pass it

[IMA-11] <u>Video posts continue playing without notification after disconnected internet</u> Created: 09/Sep/24 Updated: 09/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android		

Device : One Plus 11 5G OS Version : Android 14

Severity1: S4 - Minor

Description

Steps to Reproduce:

- 1. Enter "Instagram" app
- 2. Scroll down the feed
- 3. Disconnect your internet connection
- 4. Continue to scroll down the feed
- 5. Connect the internet connection back again
- 6. Scroll up and down the feed

Actual Result:


I don't get an error message regarding internet disconnection, only a message that the page can't be refreshed but i can still watch content, save a post, view a video and swipe in between photos of the posts on my feed

Expected Result:

I will expect to get an error message once i disconnect the internet and continue to scroll my feed

[IMA-12] Pressing on the tab "Watch more reels" will play the same reel again Created: 09/Sep/24 Updated: 09/Sep/24 Status: To Do Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. 1.Enter the "Instagram" app
- 2. Scroll down your feed and stay on a Reel video
- 3. Watch the Reel video once it automatically plays until it finished
- 4. Press on the button "Watch more Reels" once it finished

Actual Result:

After pressing "Watch more Reels" i get the same Reel video that i watched now only in a full screen which is same reactions as i pressed on "Watch again" button


Expected Result:

I will expect to watch more Reels videos from the same profile or same style of Reels videos as i watched now

[IMA-13] Tapping on the Reel video will only mute it instead of pause it Created: 10/Sep/24 Updated: 10/Sep/24 Status: To Do Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		

Attachments:



Severity1: S3 - Major

Description

Steprs to Reproduce :

- 1. Enter the "Instagram" app
- 2. Press on the "Reels" (film) icon at the bottom of the home page
- 3. Enter the "Reels" section and tap everywhere to pause a video on the screen
- 4. The Reel video supposed to stop once you tap one time

Actual Result:


Tapping on the screen once doesn't pause the video, only when you hold the Reel video and not releasing which is not the most convenient

Expected Result:

I will expect that once you tap and let go on the Reel video everywhere on the screen, it will be paused.

[IMA-14] Tapping twice on Reel video that i liked won't dislike my like Created: 10/Sep/24 Updated: 10/Sep/24 Status: To Do Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. 1.Enter the "Instagram" app
- 2. Press on the "Reels" (film) icon at the bottom of the home page
- 3. Press on the "Heart" icon on the right side in the middle
- 4. Press again on the "Heart" tab and see how it goes from red to transparent colour
- 5. Enter the "Reels" section and tap twice on the video and see the "Heart" icon will be display on the screen
- 6. Tap twice again on the video and the like should turn to dislike

Actual Result:

Tapping twice on the Reel video and i can see an icon of heart on the screen which means that the video was liked but when i tap twice again it continue to be liked and doesn't remove the like that i did

Expected Result:


I will expect that when i tap twice on the Reel video, the video will be liked and once i tap twice again on the video, it will dislike and cancel my like.

I will expect to press on the "Heart" icon, and it will like the video and when i press back it will dislike the video.

[IMA-15] The speed control functionality in the Reels videos is behaving in reverse Created: 10/Sep/24 Updated: 10/Sep/24 Status: To Do Project: Instagram Mobile App

Type:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		

Attachments:



Severity1: S3 - Major

Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Press on the "Reels" icon at the bottom home page
- 3. Tap the "Camera" icon at the top right side
- 4. Press on the "Speed" icon on the left side
- 5. Choose one of the speeds from 1 to 5 when 1 is normal speed and 5 is i times faster speed
- 6. Tap and don't let go on the circle icon in the middle and start to film a "Reel" video
- 7. Release the finger once you want to stop recording the "Reel" video

Actual Result

The speed limits are synchronized in reverse. When I choose 1x speed, the video plays in the fastest motion, and when I select 5x speed, it plays in the slowest motion.

Expected Result:

I expect that when I press the 1x speed option, the video will play at normal speed. As the speed increases to 2x, 3x, and 5x, the video should play progressively faster


[IMA-16] Changing the network connection affects the ability to browse videos on Reels

Created: 10/Sep/24 Updated: 10/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce:

- 1. Enter to your Settings on your mobile device
- 2. Chose Mobile network
- 3. Put your Prefered network type on 5G
- 4. Enter to "Instagram" app
- 5. Tap the "Reels" icon at the bottom
- 6. In the "Reels" feed play on of the "Reels" videos
- 7. Go back to your mobile Settings
- 8. Chose Mobile network
- 9. Put your Preferred network type on 2G
- 10. Enter the "Instagram" again
- 11. Play the last "Reels" video you watch (It will be shown on your screen)
- 12. Turn on your wi-fi connection and turn off your mobile internet connection
- 13. Play the same "Reels" videos you played before


Actual Result:

The "Reels" video stuck in the middle when i play it on 2G while on 5G it plays it smoothly in repeat **Expected Result**:

I will expect the app will play the "Reels" video in a smooth way between 5G to 2G connection.

[IMA-17] Filming on "Live" mode is not working Created: 10/Sep/24 Updated: 17/Sep/24 Status: To Do Project: Instagram Mobile App

Type:	Bug	Priority:	High
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce :

- 1. Entering the "Instagram" app
- 2. Swipe to the right side for camera mode
- 3. Choosing one of the options between "Post", "Story", "Reel" and "Live"
- 4. Choose "Post" and then press on the "Camera" icon on the right side
- 5. Take a photo and only after the "Effects" will be displayed when pressing on "Edit" button on the bottom left side
- 6. Press on it and you will be able to use it for one type of effect
- 7. For "Story", take a video first and then type on the "Effects" icon on the top right side
- 8. Switch in between the effects options
- 9. For "Reels", Press the top left side and chose from the options, then you can take a video
- 10. For "Live" option the "Effects" aren't being shown

Actual Result

Switching to 'Live' mode doesn't display the effects and I'm unable to film; instead, I receive an error message

Expected Result:

I will expect to choose effects for every option ("Post", "Story" "Reels", "Live") when I switch to camera

[IMA-18] The timer option isn't displayed in the "Post" and "Story" mode

Created: 10/Sep/24 Updated: 10/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		

Attachments:



Severity1: S3 - Major

Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Swipe to the right to access the camera
- 3. In "Reels" press on the "Timer" icon on the left side of the screen and tap on it.
- 4. Tap on the timer icon and choose duration time from 3 seconds to 15 seconds, once you finished press on "Set timer" button
- 5. Tap the circle button to start the timer countdown
- 6. After the countdown is finish, the photo will be taken automatically.

Actual Result:

Timer option isn't displayed on the "Post" mode and not on the "Story", only in the "Reel" mode **Expected Result**:

I will expect to have time option in the Post, Story and Reel mode and adjust it by the time I chose

[IMA-19] Having "Boomerang" video in "Reels" takes many steps

Created: 10/Sep/24 Updated: 10/Sep/24


Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android	-	

Device : One Plus 11 5G OS Version : Android 14

Attachments:



Severity1: S4 - Minor

Description

Steps to Reproduce:

- 1. Enter the "Instagram" app
- 2. Press on the "Story" mode and choose on the top left side the "Boomerang" icon
- 3. Tap and hold the circle button until you finish to record
- 4. Press the "Next" at the bottom right and then press "Share" at the bottom page
- 5. Press on the "+" option to be at Reel mode and choose from the gallery and "Share"

Actual Result:

"Boomerang" option is not available on "Reels", in order to have a "Boomerang" it requires many steps to use Boomerang in "Reels"

Expected Result:

I will expect the" Boomerang" option will be available also on the "Reel" beside the "Story" mode

[IMA-20] <u>Differences in the option "View once" while viewing a photo on a mobile and Web</u>


Created: 10/Sep/24 Updated: 10/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS: Android Device: One Plus 11 5G OS Version: Android 14 Browser: Chrome Version 12: OS: Windows 11 Pro, 22631.3		

Attachments:



Severity1: S3 - Major

Description

Steps to Reproduce:

- 1. Enter the "Instagram" app
- 2. Enter to the messages and choose a recipient you would like to send a photo
- 3. Press on the "Camera" icon at the bottom left
- 4. Select a photo from your gallery or take a new photo
- 5. Tap once on the photo and choose at the bottom left on the option "View once"
- 6. Press "Send"

Actual Result:

The recipient received the photo i sent and successfully open it in a Web but even though it's written under the photo "No longer available", he can still see it on his conversation but when the App is opened on a mobile device it's not available to view


Expected Result:

I will expect that receiver will be able to view the photo only once and then he won't be able again

[IMA-21] The app doesn't count the numbers of "Followers" as it should Created: 10/Sep/24 Updated: 10/Sep/24 Status: To Do

Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Project:

Steps to Reproduce:

- 1. Enter the "Instagram" app
- 2. Tap on your "Profile" tab at the bottom right
- 3. Press at the middle top on the "Followers"
- 4. View your "Followers" account

Actual Result:

The app doesn't count correctly the number of followers and shows the followers profile twice **Expected Result**:


I will expect the number will be displayed at the "Followers" and match to the actual accounts that follow my profile and the profile who follows me won't be displayed more than once

[IMA-22] <u>Top menu missing after pressing "Profile" tab requires navigation through "Home" tab to access it</u> Created: 10/Sep/24 Updated: 10/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Tap on the profile picture or the profile icon in the bottom right corner of the screen
- 3. Tap again on the "Home" tab on the left side of the screen and then your profile icon on the right once again
- 4. At the top right-side tap on the three lines and the menu will be opened

Actual Result :

After pressing the "Profile" tab in the bottom right corner, the menu at the top doesn't appear. Instead, the app takes me to my profile page, requiring me to press the "Home" tab and then the "Profile" tab again to see the top menu.

Expected Result:

I would expect that after entering the "Instagram" app, i will tap on the profile tab on the bottom right side and i will see the menu at the top right side immediately

[IMA-23] Instagram limits the bio to 150 characters, but it limits me to write 124 characters

Created: 10/Sep/24 Updated: 10/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G OS Version : Android 14		



Description

Steps to Reproduce :

- 1. Enter the "Instagram" app
- 2. Press on your "Profile" icon at the bottom right
- 3. Tap on the tab "Edit profile" at the top left
- 4. Chose the "Bio" section and write a bio
- 5. Press on the "Checkmark" at the top right once you finished

Actual Result:

"Instagram" limits my "bio's" writing after only 124 characters without a notification while the limit is until 150 characters

Expected Result:

I will expect that "Instagram" won't limit me under 150 characters according to its last update

[IMA-24] The app doesn't rotate when i press on "Auto rotate" mode

OS Version: Android 14


Created: 11/Sep/24 Updated: 11/Sep/24

Status: To Do

Project: Instagram Mobile App

Туре:	Bug	Priority:	Medium
Reporter:	Tomer Darmon	Assignee:	Unassigned
Environment:	OS : Android Device : One Plus 11 5G		

Attachments:



Severity1: S3 - Major

Description

Steps to Reproduce:

- 1. Swipe down from the top on the screen to access the quick settings
- 2. Press on the option "Auto Rotate" and swipe up the page
- 3. Ener the "Instagram" app
- 4. Rotate your phone on any page from portrait mode to landscape mode

Actual Result:

The app doesn't rotate after choosing the rotate mode and the screen still stay on portrait mode and not landscape mode when i rotate it.

Expected Result:

I expect the screen to change its view according to the mode I rotated my phone