

Joseph Costello

CNSA-117

11/21/2025

To check that my router's DHCP settings were active and working I first went into the web agent of the browser. Then under the local area network settings I checked that it was turned on. To check that my PC was actually getting an address assigned through it, I changed the lowest number on the range that the router could assign from 192.168.10.101 to 192.168.10.102. I then went into command line and out in Ipconfig and it worked assigning me the new lowest number made available to it verifying it was what gave my PC the IP address.

TRENDNET AC2600 MU-MIMO WiFi Router
Firmware 8.2/DRU
New firmware is available

Local Area Network (LAN) Settings

This section allows you to modify the router's IP address settings. Typically, the router IP address settings do not need to be changed. In addition, this page allows you to configure the router's DHCP server settings or DHCP reservations which automatically assigned IP addresses to your wired and wireless devices that connect to your router.

LAN Interface Setting

IP Address	192.168.10.1
Subnet Mask	255.255.255.0
MAC Address	d8:eb:97:34:ad:b4

DHCP Server Setting

DHCP Server	Enable
DHCP Start IP	192.168.10.101
DHCP End IP	192.168.10.199
DHCP Lease Time	1440 (minutes)
Local Domain Name	lan
Primary DNS Server	0.0.0.0
Secondary DNS Server	0.0.0.0

Apply **Reset**

TRENDNET AC2600 MU-MIMO WiFi Router
Firmware 8.2/DRU
New firmware is available

Local Area Network (LAN) Settings

This section allows you to modify the router's IP address settings. Typically, the router IP address settings do not need to be changed. In addition, this page allows you to configure the router's DHCP server settings or DHCP reservations which automatically assigned IP addresses to your wired and wireless devices that connect to your router.

LAN Interface Setting

IP Address	192.168.10.1
Subnet Mask	255.255.255.0
MAC Address	d8:eb:97:34:ad:b4

DHCP Server Setting

DHCP Server	Enable
DHCP Start IP	192.168.10.102
DHCP End IP	192.168.10.199
DHCP Lease Time	1440 (minutes)
Local Domain Name	lan
Primary DNS Server	0.0.0.0
Secondary DNS Server	0.0.0.0

Apply **Reset**

Online NAT Type Checker

Detect NAT

The website I used to check my nat was <https://www.checkmynat.com/>. I went to this site and both PCs and hit the button to 'Detect NAT' which gave me these results. These show that the network's NAT is working making it look like the PCs are at that IP.

Online NAT Type Checker

NAT type: **Port Restricted Cone**

Public IP: **73.130.245.69**

Detect NAT

Online NAT Type Checker

NAT type: **Port Restricted Cone**

Public IP: **73.130.245.69**

Detect NAT

To cloak my router and still be able to connect wirelessly to it. I first go into the online web of the router and sign in to it. I then go into wireless settings and set up my network like usual checking the box to disable broadcast network name that's circled in the image below. I then connected my phone it by typing in the network name and password, and can be seen to be connected in the image second image below.

