#2

U13157004

README

這程式使用 **VS CODE** 來完成 修改了 **LED** 的腳位和閃燈的時長 並且在 **While(1)**迴圈裡增加 **printf("Hello, world! MCUT U13157004** 吳秉彥**\n");**


src > main.cpp > mainTask(void *)
void mainTask(void *params){
gpio_init(ledPad);
gpio_set_dir(ledPad, GPIO_OUT);
while (true) { // Loop forever
gpio_put(ledPad, 1);
vTaskDelay(DELAY);
gpio_put(ledPad, 0);
vTaskDelay(DELAY);
printf("Hello, world! MCUT U13157004 吳秉彥\n");
}
}
/***
* Launch the tasks and scheduler
*/
void vLaunch(void) {
//Start blink task
TaskHandle_t task;
xTaskCreate(mainTask, "MainThread", configMINIMAL_STACK_SIZE, NULL, TASK_PRIORITY, &task);
/* Start the tasks and timer running. */
vTaskStartScheduler();
}
/***
* Main
* @return
*/
int main(void)
PROBLEMS
OUTPUT
DEBUG CONSOLE
TERMINAL
PORTS
MEMORY
XRTOS
SERIAL MONITOR
Open an additional monitor
Monitor Mode
Serial
View Mode
Text
Port
COM3 - USB 序列裝置 (COM3)
Baud rate
115200
Line ending
None
Stop Monitoring
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Type in a message to send to the serial port.
Send Ctrl + C
U13157004
吳秉彥
電子工程系
ASUS


main.cpp
src > main.cpp > mainTask(void *)
/***
* Demo program to flash an LED attached to GPIO PAD 0.
* Uses FreeRTOS Task
* Jon Durrant
* 15-Aug-2022
*/
//U13157004 吳秉彥
#include "pico/stdlib.h"
#include "FreeRTOS.h"
#include "task.h"
#include <stdio.h>
//Standard Task priority
#define TASK_PRIORITY (tskIDLE_PRIORITY + 1UL)
//LED PAD to use
#define LED_PAD 25
//Blink Delay
#define DELAY 202
/***
* Main task to blink external LED
* @param params - unused
*/
void mainTask(void *params){
printf("Main task started\n");
const uint ledPad = LED_PAD;
PROBLEMS OUTPUT DEBUG CONSOLE TERMINAL PORTS MEMORY XRTOS SERIAL MONITOR
Open an additional monitor
Monitor Mode Serial View Mode Text Port COM3 - USB 序列裝置 (COM3) Baud rate 115200 Line ending None
Stop Monitoring
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Hello, world! MCUT U13157004 吳秉彥
Type in a message to the serial port.
Send Ctrl + C
U13157004
吳秉彥
電子工程系
ASUS