

-
-
-
-
-

Chapter 4

Reports



Documentation Prints and Reprints

Print and reprint facilities are available for load sheets and bills of lading.



Note: Load sheets provide a driver's manifest and list all drops to be undertaken for each load. Load sheets are also used to marshall goods and despatch notes onto their appropriate transport loads prior to despatch. Bills of lading provide a more formal document detailing the load contents and are generally produced for selected external carriers only.

These facilities are available from the Drinks Transport Planning Reports menu.

Bills of Lading (Print / Reprint) Report



1&2/DTR

Bills of lading provide a formal document detailing the load contents according to the bill of lading format code specified on the load header.



Note: If the load requires automatic or manual rating, the load status is updated as printed, i.e. 'awaiting rating'.



Note: If rating is not applicable and confirm despatch is required, the load status is updated as rated i.e. 'awaiting confirm despatch'.



Note: If rating was not applicable and confirm despatch is not required (as defined to the transport centre) the load status is updated such that it can be dropped to history, i.e. the production of the bill effectively completes the processing of the load.

You may choose the option to print bills of lading or to reprint already printed sheets.

Bills of Lading Print Selection Screen



Select the Bills of Lading (either print or reprint) option.

At the top of the screen, the text 'print bills of lading' or 'reprint bills of lading' will be displayed, depending on the option chosen.

The planner is able to control the number of requirements presented via a range of ship dates together with one of the following criteria:

- Route/drop range *or*
- Particular carrier *or*
- Origin and optionally destination.

TP810	HW - Handy Wholesalers Ltd	USER GALBRAIJ	2/10/95
	Handy Wholesaler Depot 001		15:36:56
Print bills of lading			
Ship date..... 3/10/95			
Route.....?.. _____			
OR			
Carrier.....?.. _____			
OR			
Origin.....?.. _____			
Destination.....?.. _____			
OR			
Load number..... _____			
Print load sheets..... 1 (0=No,1=Yes)			
Load sheet sequence... 1 (1=Ascending 2=Descending)			
F3=Exit F4=Prompt F8=Submit F16=Released loads			
05-25 SF MW KS IM II PLYM400A PED171S1			

Fields:

Ship Date

Ship date for which loads are to be reviewed - defaults to the current date plus the planner's time fence days for planning.

Route

Enter the route for which loads are to be printed.

Or

Carrier

Enter the carrier for which loads are to be printed.

Or

Origin

Enter the origin (start point) for which loads are to be printed. This must be a valid Transport Node.

And

Destination

Enter the destination (end point) for which loads are to be printed. This must be a valid Transport Node.

Or

Load Number

Enter a particular load reference for which documentation is to be printed.

Print/Reprint Load Sheets

Indicates if load sheets are to be printed/reprinted (according to the original selection) in addition to the bill of lading documentation.

Load Sheets Sequence

- 1 - Ascending. Print load sheets in ascending drop sequence within route.
- 2 - Descending. Print load sheets in descending drop sequence within route.

Functions:

F16

Released loads.



Note: This displays load headers that conform to the selection criteria. The screen shown is the Select Load Screen and is described in Enquiries.



Note: For the reprint option, only load headers that are already printed are displayed, and the document itself clearly displays 'Reprint'.



Note: If a load has been printed, then reset to 'pending' for amendment and subsequently released again, the print option (rather than reprint) should be used.



Press **F8=Submit** to submit the report to print.

Load Sheet Report



3 & 4/DTR

Load sheets provide a driver's manifest detailing the drops and orders for each load. Drops can be printed in descending or ascending sequence for the route.



Note: If Bill of lading documentation is not required, the load is updated as follows:

- If the load requires automatic or manual rating, the load status is updated as printed, i.e. 'awaiting rating'.
- If rating was not applicable and confirm despatch is required, the load status is updated as rated i.e. 'awaiting confirm despatch'.
- If rating was not applicable and confirm despatch is not required (as defined to the transport centre) the load status is updated such that it can be dropped to history, i.e. the production of the load sheet effectively completes the processing of the load.



Note: The load sheet serves three major purposes:

- As a marshalling document for all despatch notes that are included on the load sheet, particularly if the notes are from more than one stockroom.
- As an aid for loading the vehicle in the 'best' sequence for dropping.
- To be taken by the driver as an action and confirmation list.



You may choose the option to print load sheets or reprint already printed sheets.

Load Sheet Report Selection Screen

 Select the either Print Load Sheets, or Reprint Load Sheets options.

At the top of the Screen, the text 'print load sheets' or 'reprint load sheets' will be displayed, depending on the option chosen.

The planner is able to control the number of requirements presented via a range of ship dates together with one of the following criteria:

- Route/drop range *or*
- Particular carrier *or*
- Origin and optionally destination.

TP822

HW - Handy Wholesalers Ltd

User GALBRAIJ

2/10/95

Reprint Load Sheets

Handy Wholesaler Depot 001

16:10:33

Ship date

3/10/95

Route

?

OR

Carrier

?

OR

Origin

?

OR

Destination

?

Load number

Load sheet sequence. 1

(1=Ascending,2=Descending)

F3=Exit

F4=Prompt

F8=Submit

F16=Released loads

05-23

SR

HW

KS

IM

II

PLYM400A PED171S1

Fields:

Ship Date

Ship date for which loads are to be reviewed - defaults to the current date plus the planner's time fence days for planning.

Route

Enter the route for which loads are to be printed.

Or

Carrier

Enter the carrier for which loads are to be printed.

Or

Origin

Enter the origin (start point) for which loads are to be printed. This must be a valid Transport Node.

And

Destination

Enter the destination (end point) for which loads are to be printed. This must be a valid Transport Node.

Or

Load Number

Enter a particular load reference for which documentation is to be printed.

Load Sheet Sequence

- 1 - Ascending. Print load sheets in ascending drop sequence within route.
- 2 - Descending. Print load sheets in descending drop sequence within route.

Functions:

F16

Released loads. This displays load headers that conform to the selection criteria. The screen shown is the Select Load Screen and is described in Enquiries.

For the reprint option only, load headers that are already printed are displayed and the load sheet itself clearly displays 'Reprint'.



Note: If a load has been printed, reset to 'Pending' for amendment, and subsequently released again, then the print option (rather than reprint) should be used.



Press **F8=Submit** to submit the report to print.

Printing Reports

Planning and status reports are provided in order to aid the planner when reviewing either outstanding order requirements that must be assigned to loads or reviewing loads in order to assess the capacity commitment and availability.

These reports are accessed from the Drinks Transport Planning Reports menu.

Outstanding Orders Report



13/DTR

The outstanding orders report provides the planner with details of all order requirements that are yet to be assigned to loads, with capacity totals per route and date. This report - designed for use in conjunction with the Build Loads function - is sequenced by route/drop within the required ship date, and provides details of capacity requirements.

Outstanding Order Report Selection Screen

 Select the Outstanding Orders option.

This screen enables the selection of the outstanding order on which the report is to be based.

TP000	HW - Handy Wholesalers Ltd	User GALBRAIJ	2/10/95
	Handy Wholesaler Depot 001		16:59:27
Outstanding Orders Report			
	From	To	
Ship date	0/00/00	3/10/95	
Route	?		
F3=Exit F4=Prompt F8=Submit			
07-26	SP	MW	KS IM II PLYM400A PED171S1

Fields:

Ship Date From

Ship date from which orders are to be reviewed - defaults to 0/00/00. If this field is left unchanged all outstanding orders up to the 'to' date will be included in this report.

Ship Date To

Ship date up to which orders are to be reviewed - defaults to the current date plus the planner's time fence days for planning. It is matched against the order line despatch date.

Route From

Optionally enter the route from which orders are to be reviewed.

Route To

Optionally enter the route up to which orders are to be reviewed.



Note: If route from and to are both left blank, then details for all routes are selected. If 'route from' is specified and 'route to' is left blank, all details are selected with route codes matching or 'greater' than the 'route from'.

 Press **F8=Submit** to submit the report to print.

Load Status Report



14/DTR

The load status report provides the planner with summary information for the total capacity requirements of outstanding orders together with a view of current loads. The report is sequenced by route/drop within the required ship date and provides a direct comparison between outstanding requirements and current loads that are applicable to those requirements i.e. for the same route and ship date. This report is designed for use in conjunction with the outstanding orders report and the build loads function, in order to assess and action over/under capacity commitments to loads prior to assigning further requirements.

For example, all routes where there appears to be enough commitment to justify a load, and not enough to overload it, then the planner will build these loads immediately. Otherwise, he/she may use the outstanding orders report for under/over committed routes to determine which orders are to be reassigned during the build loads function.

Load Status Report Selection Screen

 Select the Load Status option.

This screen enables the selection of the load status on which to base the report.

TP005

HW - Handy Wholesalers Ltd
Handy Wholesaler Depot 001

User GALBRAIJ

2/10/95
17:14:39

Load Status Report

From

To

Ship date.....

2/10/95

3/10/95

Route.....?..

F3=Exit

F4=Prompt

F8=Submit

07-26

SF

MW

KS

IM

II

PLYM400A PED171S1

Fields:

Ship Date From

Ship date from which orders are to be reviewed - defaults to the current date. If this field is left unchanged, all loads from the current date up to the 'to' date will be included in this report.

Ship Date To

Ship date up to which orders are to be reviewed - defaults to the current date plus the planner's time fence days for planning. It is matched against the load ship date.

Route From

Optionally enter the route from which loads are to be reviewed.

Route To

Optionally enter the route up to which loads are to be reviewed.

 Press **F8=Submit** to submit the report to print.

Load Details Report



15/DTR

The load details report provides the planner with details of all order requirements that are currently assigned to loads. The report is sequenced by route / drop within the required ship date, and provides details of capacity requirements. This report is designed for use in conjunction with the load status report and maintain loads function in order to assess and action over / under capacity commitments to loads.

Load Details Report Selection Screen

 Select the Load Details option.

This screen enables the selection of the load details for the report.

TP830 HW - Handy Wholesalers Ltd User GALBRAIJ 2/10/95
Handy Wholesaler Depot 001 17:15:26

Load Details Report

From To

Ship date 2/10/95 3/10/95

Route?..

F3=Exit F4=Prompt F8=Submit

07-26 SF MW KS IM II PLYM400A PED171S1

Fields:

Ship Date From

Ship date from which orders are to be reviewed - defaults to the current date. If this field is left unchanged all loads from the current date up to the 'to' date will be included in this report.

Ship Date To

Ship date up to which orders are to be reviewed - defaults to the current date plus the planner's time fence days for planning. It is matched against the load ship date.

Route From

Optionally enter the route from which loads are to be reviewed.

Route To

Optionally enter the route up to which loads are to be reviewed.

 Press **F8=Submit** to submit the report to print.