

-
-
-
-
-

Chapter 5

Enquiries



Maintenance Enquiries

The Maintenance Enquiries are a series of standard enquiries provided to view the warehouse maintenance setup data. These cover:

- The Warehouse profile.
- Area profiles and dimensions.
- Item/warehouse profiles.
- Packaging types.
- Location types.

All the enquiries are selected from the Drinks Warehousing Maintenance menu.

DWM	ZM - Multi-Currency Company	User GALBRAIJ	14/03/96 09:15:14
Warehousing Maintenance Menu			
1. Warehouse profile		Batch Maintenance	
2. Area profile		21. Determine access points	
3. Area dimensions		22. Create location check digits	
4. Item/warehouse profile		Enquiries	
5. Packaging types		31. Warehouse profile	
6. Location types		32. Area profile/dimensions	
7. Warehouse map		33. Item/warehouse profile	
8. Location rules by item		34. Packaging types	
9. Location rules by area		35. Location types	
10. Resource codes		90. Signoff	
11. Location check digit codes			
12. Descriptions			
13. Warehouse list profile			
Option			
Search			
F3=Exit F4=Prompt F6=Messages F12=Previous F16=Change company F18=Prints			
21-11 S2 MW KS IM II PLYM400A PED171S1			

Warehouse Profile Enquiry



31/DWM

This option displays the data set up for the Warehouse profile selected. It includes details of the warehouse policies, such as check digit usage, the locations defined for marshalling and receiving, and the defaults set for item/warehouse profiles. Further details of the individual fields on the screens can be found in the Drinks Warehousing Maintenance section of this product information.

Warehouse Profile Enquiry Selection Screen

 Select the Warehouse Profile option.

Fields:

Stockroom

Enter the stockroom code.

 Press **Enter**. Once the warehouse has been selected, the operational and item default information is displayed.

Warehouse Profile Enquiry Screen 1



This screen is displayed when you have entered a valid stockroom into the Warehouse Profile Enquiry Selection Screen.

This screen displays the warehouse defaults. The details are for display purposes only and cannot be amended.

WH200	ZM - Multi-Currency Company	USER GALBRAIJ	14/03/96 9:25:04
Warehouse Profile Enquiry			
Stockroom..... W1 Warehouse #1			
Default sequence for Picking list..... 1		1=Order 2=Account code	
Putting away..... 1		3=Journey 4=Despatch date	
Moving..... 1		5=Operation start date	
Default date for committing..... 1		1=Receipt at warehouse	
		2=Receipt at location	
		3=Expiry	
System to generate locations..... 1		0=No, 1=Yes	
Are location check digits to be entered at confirmation..... 0		0=No, 1=Yes	
Are confirmation updates to be performed interactively..... 1		0=No, 1=Yes	
Allow default confirmation..... 0		0=No, 1=Yes	
F3=Exit F12=Previous			
01-02	SP	MW	KS IM II PLYM400A PED171S1



Press **Enter** to display Warehouse Profile Enquiry Screen 2.

Warehouse Profile Enquiry Screen 2



This screen is displayed when you have pressed
Enter on Warehouse Profile Enquiry Screen 1.

This screen displays the standard receiving and marshalling points. The details
are for display purposes only and cannot be amended.

WH200	Drinks US System Test Company (U1)	USER PGMR1	24/03/97 15:08:23
Warehouse Profile Enquiry			
Stockroom..... W1 Warehouse #1			
Receiving location.....		AA	
Marshalling location for production.....		A01A	
Marshalling location for sales.....		AB	
Serious error monitoring			
Message to show if a location is not recommended... No Location			
User to receive error messages.....		GBJBAD0B	
Work station to receive error messages.....		JJB1	
F3=Exit F12=Previous			
01-02		MW	KS IM II KENB20A PET007S2



Press **Enter** to display Warehouse Profile
Enquiry Screen 3.

Warehouse Profile Enquiry Screen 3



This screen is displayed when you have pressed Enter on the Warehouse Profile Enquiry Screen 2.

This screen displays the item / warehouse profile defaults. The details are for display purposes only and cannot be amended.

WH200	ZM - Multi-Currency Company	USER GALBRAIJ	14/03/96 9:26:47
Warehouse Profile Enquiry			
Stockroom..... W1 Warehouse #1			
The following values are used to default the corresponding entries on the item/warehouse profile.			
	Whole packs	Split packs	(0=No, 1=Yes)
Fixed locations	1	1	
Putting away			
Multiple rotation dates.....	1	1	
Multiple LOTS.....	1	0	
Picking location.....	1	1	
Committing			
Rotation date.....	1	1	
Minimise LOTS.....	0	0	
Picking location.....	0	1	
F3=Exit F12=Previous			
01-02	SP	MW	KS IM II PLYM400A PED171S1



Press **F3=Exit**.

Area Profile / Dimensions Enquiry



32/DWM

This option displays the area definition, the proximity variables, the location code structure and dimension values. For further details of individual fields, refer to the Maintenance section.

Area Profile / Dimensions Enquiry Select Area Screen



Select the Area Profile / Dimensions option.

This screen enables the area in the default warehouse to be selected for enquiry.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Area Profile Enquiry			
Area.....?.. <u>MS</u>			
F3=Exit F4=Prompt			

Fields:

Area

Enter the code of the area to be enquired upon. A prompt is available.



Having selected the area, pressing **Enter** will display the Area Profile / Dimensions Enquiry Definition and Location Code Structure Screen.

Area Profile / Dimensions Enquiry Definition and Location Code Structure Screen



This screen is displayed when you press **Enter** on the Area Profile / Dimensions Enquiry Select Screen.

Once the area code has been selected the area profile details are displayed.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Area Profile Enquiry

Area..... MS Main Store

Unit of Measure - to define maximum capacities of the locations in the Area

- Length.....
- Weight.....
- Volume.....

Dimension	Name	Code Length
1	Aisle	1
2	Bay	1
3	Row	1
4		

F3=Exit F12=Previous F14=Proximity details F15=Area dimensions

Functions:

F14

Display the proximity details set up for the area.

F15

View selected dimension codes that are used to create the location code.



Press the function key required to display the details you want to view.

Area Profile / Dimensions Enquiry Proximity Details (F14)



This screen is displayed when you press **F14=Proximity Details** on the Definition and Location Code Structure Screen and displays the measures of proximity used to determine the relative distance between locations in the selected area.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Area Profile Enquiry			
Area..... MS Main Store			
Control data for proximity putting away and committing rules			
Dimension:	1	2	3
Name.....	Aisle	Bay	Row
Distance to be moved between access points in the dimension.	10	1	5
The number of positions that can be accessed from access point.	2	1	1
Number of positions at the first access point.	1	1	1
F3=Exit F12=Previous			



Press **F12=Previous** to return to the previous screen, or **F3=Exit**.

Area Profile / Dimensions Enquiry Select Dimension Screen (F15)



This screen is displayed when you press
F15=Area Dimensions on the Definition and
Location Code Structure Screen.

The dimension to be enquired upon may be selected from this screen.

WH205	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Enquire on Area Dimensions			
Area..... MS Main Store			
Select Dimension..... <u>1</u> (to review codes individually)			
F3=Exit F12=Previous			

Fields:

Select Dimension

Enter the number of the dimension to be enquired upon. For example, to display the codes used in the first dimension enter a '1' and press **Enter**.



Having selected the dimension, press **Enter** to
display a screen showing the codes used in the
dimension.

Area Profile / Dimensions Enquiry Area Dimension Values



The dimension number of the required dimension must be entered on the Area Profile / Dimensions Enquiry Select Dimension Screen. Once the dimension has been selected the list of allowable code values is displayed. This list is for display only and cannot be amended.

WH205		Z1 - Demonstration Company		USER SP1		01/09/94	
		Central Warehouse				12:00:00	
Area Profile Enquiry - Area Dimensions							
Area..... MS		Main Store					
Dimension.... 1		Aisle		Code length		1	
Line	Code	Dlt	Line	Code	Dlt	Line	Code
0001	A						
0002	B						
0003	C						
0004	D						
0005	E						
0006	F						
F3=Exit F12=Previous							



Press **F3=Exit**.

Item / Warehouse Profile Enquiry



33/DWM

This option displays the parameters that have been set up for an item that allows it to be processed in the warehouse. For further details of individual fields, refer to the Maintenance section of this product information.

Item / Warehouse Profile Enquiry Selection Screen



Select the Item / Warehouse Profile option.

The system will display the Selection Screen, for your default warehouse.

Fields:

Item

Enter an item code.



Press **Enter** to display the Item / Warehouse Profile Enquiry Packaging Screen.

Item / Warehouse Profile Enquiry Packaging Screen



This screen is displayed when you have entered a valid item code into the Item / Warehouse Profile Enquiry Selection Screen.

Once the item has been selected, the stock rotation rules and the item packaging details on the following screen are displayed.



*This screen is also displayed if **F19=Packaging** is pressed from any of the other item/warehouse profile enquiry screens.*

WH210	ZM - Multi-Currency Company	USER	GALBRAIJ	14/03/96
	Warehouse #1			9:31:17
Item/Warehouse Profile Enquiry				
Item.....	A12345	Ballantine's 35x24		
Date to be used for stock rotation....	0	(0=None; 1=Receipt into W/H; 2=Receipt into loc; 3=Expiry)		
Warehouse activity, stocking and packaging units of measure				
Conversion factor to measure	warehousing activity..... 1.00000			
Unit of measure.....	CA	Cases of		
Default pack.....	PAL	Standard Pallet		
Line	Warehouse pack	Description	Quantity/pack	
0001	24P	24 pack	10.000	
F3=Exit	F12=Previous	F15=Fixed locations	F16=Put away details	
F17=Commitment details	F18=Picking information			
01-02	82	MW KS IM	II PLYM400A PED171S1	

Functions:

F15

View the fixed locations set up for the item.

F16

View the put away details set up for the item.

F17

View the commit details set up for the item.

F18

View the picking details set up for the item.



Use the function keys to display the information you want to view.

Item / Warehouse Profile Enquiry Fixed Locations Screens (F15)



This screen displays the fixed locations set up for an item and can be accessed by pressing **F15=Fixed Locations** or any of the other item / warehouse profile enquiry screens.



Note: This screen is for display purposes only and cannot be amended.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry - Fixed Locations			
Item.....	5006	Ballantine's 35x24	
Line	Location	Whole packs	Split packs
0001	FE1	1	1
F3=Exit F12=Previous F16=Put away details F17=Commitment details F18=Picking information F19=Packaging information			



Use the function keys to display any further screens you want to view, or press **F3=Exit**.

Item / Warehouse Profile Enquiry Put-away Details Screen (F16)



This screen displays the put-away details set up for an item. This can be accessed by pressing **F16=Put Away Details** on any of the other item / warehouse profile enquiry screens.



Note: This screen is for display purposes only and cannot be amended.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry			
Item..... 5006		Ballantine's 35x24	
Putting away		Whole packs	Split packs
Multiple rotation dates.....	1	1	0 = No;1 = Yes
Multiple LOTS per location....	0	0	0 = No;1 = Yes
Picking location.....	0	1	0 = No;1 = Yes
Putting away rules			
Whole packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
Split packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
F3=Exit F12=Previous		F15=Fixed locations F17=Commitment details	
F18=Picking information		F19=Packaging information	



Use the function keys to display any further screens you want to view, or press **F3=Exit**.

Item/Warehouse Profile Enquiry Committing Screen (F17)



This screens displays the committing details set up for an item. This can be accessed by pressing **F17=Commitment Details** on any of the other item / warehouse profile enquiry screens.



Note: This screen is for display purposes only and cannot be amended.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry			
Item.....	5006	Ballantine's 35x24	
Committing stock			
By rotation date.....	0	Whole packs	Split packs
Minimise LOTS.....	0	0	0 = No;1 = Yes
Picking location.....	0	1	0 = No;1 = Yes
Committing rules			
Whole packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
Split packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
Allow commit at any location..	1	0 = No;1 = Yes	
F3=Exit F12=Previous F15=Fixed locations F16=Put away details			
F18=Picking information F19=Packaging information			



Use the function keys to display any further screens you want to view, or press **F3=Exit**.

Item / Warehouse Profile Enquiry Picking Information Screen (F18)



This screen displays the picking details set up for an item. This can be accessed by pressing **F18=Picking Information** from any of the other item/warehouse profile enquiry screens.



Note: This screen is for display purposes only and cannot be amended.

WH210	Z1 - Demonstration Company	USER	SP1	01/09/94
	Central Warehouse			12:00:00
Item/Warehouse Profile Enquiry				
Item.....	5006	Ballantine's 35x24		
Picking face details				
Picking location.....	BC3			
Maximum quantity to be picked from				
picking location.....		15.000		
Replenishment of picking face				
Minimum quantity at picking location.....		3.000		
Replacement quantity for picking location..		16.000		
Default resource code at				
picking location.....	TR			
F3=Exit	F12=Previous	F15=Fixed Locations	F16=Put away details	
F17=Commitment details	F19=Packaging information			



Use the function keys to display any further screens you want to view, or press **F3=Exit**.

Packaging Types Enquiry



34/DWM

This option displays the characteristics set up for a packaging type.

Packaging Types Enquiry Selection Screen



Select the Packaging Types option.

Fields:

Packaging Code

Enter a valid packaging code.



Press **Enter** to display the Packaging Types Enquiry Details Screen.

Packaging Types Enquiry Details Screen



This screen is displayed when you have entered a valid packaging code into the Packaging Types Enquiry Selection Screen

For further details of individual fields, refer to the Maintenance section.



Note: This screen is for display purposes only and cannot be amended.

WH215	ZM - Multi-Currency Company	USER GALBRAIJ	14/03/96 9:35:10
Packaging Code Specification Enquiry			
Packaging code..... BOT Bottle (75CL or 1Ltr)			
Unit of measure for check against			
location size.....	Weight.....	BT	Bottles of
	Length.....	BT	Bottles of
	Volume.....	BT	Bottles of
Packaging capacity... Weight.....			
Volume.....			
Packaging specification and sizes			
Tare Weight.....			
Length.....			
Height.....			
Depth.....			
Processing by label number..... 0 (1=Yes; 0=No)			
F3=Exit F12=Previous			
01-02		MW	KS IM II PLYM400A PED171S1



Press **F3=Exit**.

Location Types Enquiry



35/DWM

This option displays the location type characteristics and the relationships between the location type and the packaging types.

For further details of individual fields, refer to the Maintenance section.

Location Types Enquiry Selection Screen



Select the Location Types option.

The location type to be enquired upon may be selected from this screen.

Fields:

Location Type

Enter the location type to be enquired upon. The **F4=Prompt** is available.



Having made a selection, press **Enter** to display the Location Types Enquiry Details Screen.

Location Types Enquiry Details Screen



This screen is displayed when you have selected a valid Location Type on the Location Types Enquiry Selection Screen.

This screen is for display purposes only and cannot be amended. A list of package types allowed for this location type is displayed with the maximum number of those packs which can be stored at one time and the resource associated with moving the pack.

```

WH220                ZH - Multi-Currency Company    USER GALBRAIJ    14/03/96
                    Warehouse #1                      9:37:04

Location Type Enquiry

Location type..... PI    Picking location

Maximum storage constraints          Length..
                                Volume..    Height..
                                Weight..    Depth...

Cost of storage.....

Allowed warehouse packing
Line W/house pack Description          Packs/location Resource
0001 BOT Bottle (75CL or 1Ltr)         60      MAN
0002 CN carton                        999      MAN
0003 C06 cases of 6 bottles            500      MAN
0004 C1L Case - 1Ltr                  160      MAN
0005 C12 cases of 12 bottles           250      MAN
0006 C75 Case - Standard 75CL          250      MAN
0007 LCP Label Controlled Pallet        2      FLT
0008 PAL Standard Pallet                2      FLT +

F3=Exit  F12=Previous

01-02    S2    MW    KS    IM    II    PLYM400A PED171S1

```



Press **F3=Exit**.

General Warehousing Enquiries

Enquiries provide a fast and convenient way of obtaining information about a warehouse. The general enquiries in Drinks Warehousing fall into three groups:

- Status: Where are items located? Are they committed? etc.
- Action: What items are to be moved? What items are to be put away? etc.
- History: What movements have taken place? What serious errors have occurred?

Status information can be obtained using the options:

- By Item.
- By Location.

Action information can be obtained using the options:

- Items to be moved.
- Items to be put-away.
- Items to be picked.
- Orders awaiting despatch.
- Items to be picked for production.

History information can be obtained using the options:

- Warehouse movements.
- Serious errors.

All these options can be taken from the Drinks Warehousing Enquiries menu.

DWE	ZM - Multi-Currency Company	User GALBRAIJ	14/03/96 14:36:11
Warehousing Enquiry Menu			
Warehouse Enquiries			
1. By item		Action History Enquiries	
2. By location		21. Warehouse movements	
Action List Enquiries		22. Serious errors	
11. Items to be moved		90. Signoff	
12. Items to be put-away			
13. Items to be picked			
14. Orders awaiting assembly			
Option	_____		
Search	_____		
F3=Exit F4=Prompt F6=Messages F12=Previous F16=Change company F18=Prints			
21-11 SE MW KS IM II PLYM400A PED171S1			



Note: All enquiries show issue units.

Enquiry By Item



1/DWE

This option allows you to answer questions relating to a particular item's location and status. The questions may be asked in terms of:

- Picking Location.
- Fixed Locations.
- In Rotation Date sequence.
- In the Item Rule sequence.
- In Area Rule sequence.
- Range of Location.
- An area.
- Warehouse.

Enquiry by Item Initial Selection Screen



Select the By Item option.

This screen provides a range of methods for selecting and sequencing the locations occupied by an item. The possible selection and sequencing criteria are displayed.

```

WH300          ZM - Multi-Currency Company   USER GALBRAIJ  14/03/96
                Warehouse #1                 14:43:50

Warehouse Enquiry by Item

Item.....?..  B001
Lot.....?..
OR
Label number...?..

Enquire by..... 8

1=Pick location
2=Fixed locations
3=Rotation date
4=Location rule by item
5=Location rule by area
6=Range of locations
7=Area
8=Warehouse

F3=Exit  F4=Prompt  F5=Refresh

05-20  SF  MW  KS  IM  II  PLYM400A PED171S1
  
```

Fields:

Item

The item code for the enquiry.

Lot Number

A valid Lot Number for the item.

Label Number

A valid Label Number.



Note: Either the Item and Lot number may be entered or the label number, but not both.

Enquire by:

- Pick location. Only check the pick location defined for the selected item.
- Fixed locations. Only check the fixed locations defined for the selected item.
- Rotation date. Display the item's locations in the warehouse in rotation date order.
- Location rule by item. Only check the locations defined by an Item rule. You will be prompted for the item rule to use.

- Location rule by area. Only check the locations defined by an area rule. You will be prompted for the area rule to use.
 - Range of locations. Only a selected range of locations will be checked. You will be prompted for the 'from' and 'to' location that limit the range.
 - Area. Only check the locations with a selected area. You will be prompted for an area code.
 - Warehouse. All locations are checked within the default warehouse.
-  After the secondary screens or prompts are displayed, and an appropriate selection made, the resultant qualifying locations are then displayed.

Enquiry By Item Range of Locations Screen



This screen displays the locations selected in the sequence defined in the Enquiry By Item Selection Screen.

The item and lot number or label number followed by a list of locations which meet the defined criteria is displayed. The contents of each location is listed in terms of the items characteristics, e.g. lot number, rotation date, pack type, etc.. A characteristic is only displayed when it changes for a particular location.

WH330		ZM - Multi-Currency Company		USER GALBRAIJ		14/03/96	
		Warehouse #1				14:44:02	
Warehouse Enquiry - Range of Locations							
By Item.....		DB001		Vodka			
Lot number.....							
				Rotation			
S	Ar	Location	Lot number	Date	Pack	Label	Available
■	BU	C10A		10/08/95	C12		60.000
-				11/08/95	C12		120.000
-				12/08/95	C12		120.000
-				13/08/95	C12		120.000
-				14/08/95	C12		156.000
-	MA	MA		1/08/95			.000
-				2/08/95			.000
-				3/08/95			.000
-				4/08/95			.000
-				5/08/95			.000
-				6/08/95			.000
-				7/08/95			60.000 +
1=Select							
F3=Exit F5=Refresh F12=Previous							
F14=Item/location details F15=Location details F16=Location contents							
10-02		Sr	MW	KS	IM	II	PLYM400A PED171S1

Fields:

Ar

Area.

Location

Location Code.

Lot Number

The batch/lot/serial number.

Rotation Date

- Rotation date for the item.
- Expiry Date.
- Date received at Warehouse.
- Date booked to location.

Pack

The pack type associated with the item.

Label

The unique label number assigned to the pack.

Available

Quantity of the item that is available for committing. This is calculated as physical minus (committed plus frozen).

Functions:**F14**

Display item/location details for the selected locations.

F15

Display details of the locations.

F16

Display location contents.



Further details may be obtained for a particular location by entering a '1' against the line and pressing the appropriate function key.

Enquiry By Item, Item / Location Details Screen (F14)



This screen is displayed when you press **F14=Item / Location Details** on the Enquiry By Item Range of Locations Screen.

It displays the details of the particular set of characteristics for the item in the selected location. The upper part of the screen defines the item characteristics including lot number and pack details. The lower part displays the current stock level details.

WH305		ZM - Multi-Currency Company		USER GALBRAIJ	14/03/96
		Warehouse #1			14:46:12
Warehouse Enquiry - Details of the Item					
Item.....	DB001	Vodka			
Lot number.....					
Rotation date..	10/08/95				
Pack type.....	C12	cases of 12 bottles			
Label number...					
Area.....	BU	Bulk Store			
Location.....	C10A	Location type... PI Picking location			
Current stock position		Source information			
Physical stock.....	60.000	Located date... 14/08/95			
Committed to sales.....	.000	Located time... 20:03:34			
Committed to production..	.000	Expiry date.... 10/08/95			
Committed to transfers..	.000				
Committed to moves.....	.000				
Frozen stock.....	.000				
Available stock.....	60.000				
Planned in.....	.000				
F3=Exit F5=Refresh F12=Previous F15=Location details F16=Location contents 01-02 MW KS IM II PLYM400A PED171S1					

Functions:

F15

Display details of the locations.

F16

Display location contents.



Press **Enter** to display the next selected item / location.

Enquiry By Item Location Details Screen (F15)



This screen is displayed when you press
F15=Location Details on the Enquiry By Item
Range of Location Screen.

It displays summary information for the selected location. The screen is split into three sections. The first section provides information about the location.

The second section shows the storage capacity of the location and the dates on which various transaction types were last performed. The definitions of capacity are not used by the module but are provided for memorandum purposes.

The last section of the screen provides information relating to the current state of the location.

WH310	ZM - Multi-Currency Company	USER GALBRAIJ	14/03/96
	Warehouse #1		14:46:55
Warehouse Enquiry - Location details			
Area..... BU Bulk Store			
Location.. C10A		Location type.. PI Picking location	
Status.... Active		Multiple items allowed 1 Yes	
Maximum storage constraints		Dates	
Volume...	.000	Last counted....	0/00/00
Weight...	.000	Last issue.....	14/08/95
Length...	.000	Last receipt....	18/08/95
Height...	.000	Last emptied....	14/08/95
Depth....	.000	Last selected...	14/08/95
Current state:			
Pack type.....		Multiple pack types	
Empty/full.....	2	Full Location	
Number of issues.....		56	
Number of receipts.....		58	
F3=Exit F5=Refresh F12=Previous F16=Location contents			
01-02 SP MW KS IM II PLYM400A PED171S1			

Functions:

F16

Display location contents. All items at the location.

Enquiry By Item Location Contents Screen (F16)



This screen is displayed when you press
F16=Location Contents on the Enquiry By Item
Range of Locations Screen.

It displays all items at the location, and shows the batch / lot / serial numbers, stock rotation date, pack types, physical stock and available stock. The upper part of the screen displays the characteristics of the location.

The lower part displays details of the items contained in the location.

```

WH315                ZM - Multi-Currency Company      USER GALBRAIJ      14/03/96
                    Warehouse #1                      14:47:47

Warehouse Enquiry - Location Contents

Area..... BU      Bulk Store
Location.. C10A      Location type.. PI      Picking location
Status.... Active
Multiple items per location... 1      Yes

S Item              Lot              Date      Pack      Physical      Available
- BEER_CARTON      0/00/00      PAL      500.000      500.000
- DB001            10/08/95      C12      60.000      60.000
- DB001            11/08/95      C12      120.000      120.000
- DB001            12/08/95      C12      120.000      120.000
- DB001            13/08/95      C12      120.000      120.000
- DB001            14/08/95      C12      204.000      156.000

1=Select
-----
F3=Exit      F5=Refresh      F12=Previous      F13=Extended details
F15=Location details

      11-02      SE      MW      KS      IM      II      PLYM400A PED171S1

```

Fields:

Select

If an item line is selected by entering a '1' alongside the item number, the item / location details are displayed as described previously.

Functions:

F13

Display extended details - item pack descriptions are displayed below each line.

F15

Location details.



Press **Enter**.

Enquiry by Location



2/DWE

Displays a selected range of locations in a nominated sequence showing the items contained within them and the quantity available.

Enquiry by Location Selection Screen



Select the By Location from the Warehouse Enquiries area of the Enquiries Screen.

This screen allows you to select either the range and status of locations, or a single location for the enquiry. Either select the status or the range of locations for the enquiry by entering values in the following fields:

WH302	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Warehouse Enquiry by Location			
Empty/full..... 0	0=All locations 1=Empty only 2=Not empty		
Enquire by..... 5	1=Location rule by item 2=Location rule by area 3=Range of locations 4=Area 5=Warehouse		
OR			
Location.....?.. _____			
F3=Exit F4=Prompt F5=Refresh			

Fields:

Empty / Full

This field determines which locations from those selected will be included in the enquiry based on their status. Possible values are:

- 0 - All locations, whether empty or full.
- 1 - Empty locations only.
- 2 - Only non empty locations.

Enquire By

This field determines which locations will be included in the report. Possible values are:

- 1 - Location rule by item. The locations are selected using an item rule. You will be prompted for the item rule and, if the datum location for the rule is set to be the picking location, you will also be prompted for the datum location that indicates where in the warehouse the rule is to start selecting locations from.
- 2 - Location rule by area. The locations are selected using an area rule. You will be prompted for the area rule to be used.

3 - Range of locations. This option allows you to select a range of locations for the enquiry. You will be prompted for a 'from' location and a 'to' location which define the limits of the range.

4 - Area. This option selects all the locations in a chosen area. You will be prompted for an area code.

5 - Warehouse. All the locations in the warehouse are used for the enquiry.

OR

Select a single location to enquire.

Location

Enter a valid location code.



Note: This field is used to select a single location within the warehouse for the enquiry. If this option is required, the fields 'Empty/full' and 'Enquire by' must be left blank.



Note: The contents of the special receiving and marshalling locations can only be displayed when the single location is explicitly selected.



Having made your selection, press **Enter** to display the enquiry results.

Enquiry By Location Selected Locations Screen



This screen displays the selected locations in the sequence requested on the Enquiry By Location Selection Screen. A list of selected locations is displayed.

WH342		Z1 - Demonstration Company		USER SP1	01/09/94
		Central Warehouse			12:00:00
Warehouse Enquiry - Selected Locations					
S	Ar Location	Item	Lot	Rotation Date	Available
-	MS AC4	*** empty ***			.000
-	MS AC5	*** empty ***			.000
-	MS AD1	*** empty ***			.000
-	MS AD2	5016	L001	20/08/94	16.000
-	MS AD3	5016	L001	20/08/94	16.000
-	MS AD4	5016	L001	20/08/94	16.000
-	MS AD5	5016	L001	20/08/94	8.000
-	MS AE1	5013	B002	15/11/94	.000
-	MS AE2	5016	L001	20/08/94	16.000
-	MS AE3	*** empty ***			.000
-	MS AE4	*** empty ***			.000
-	MS AE5	*** empty ***			.000
-	FL A1	** Receiving **			.000
-	MS BA1	*** empty ***			.000 +
T=Select					
F3=Exit F5=Refresh F12=Previous					
F14=Item/location details F15=Location details F16=Location contents					

Fields:

Ar

The area containing the location.

Location

The location code.

Item

The item code of the item stored in the location.

Lot

The lot/batch/serial number associated with the item.

Rotation Date

The rotation date of the item.

Available

The quantity available to be committed. This is calculated as physical stock minus (committed plus frozen).

Functions:

F14

Display item / location details. This screen is the same as the one detailed under Enquiry By Item.

F15

Location details. This screen is the same as the one detailed under Enquiry By Item.

F16

Location contents. This screen is the same as the one detailed under Enquiry By Item.



Further details may be obtained for a particular location by entering a '1' against the line and pressing the appropriate function key as outlined below.

Items To Be Moved Enquiry



11/DWE

This option enables you to display the status of outstanding move lists.

Items To Be Moved Enquiry Select List Screen

 Select the Items to be moved option.

This screen allows the selection of a move list for the enquiry.

Fields:

List Number

Enter the number of the required move list for the enquiry.

 Press **Enter** to display the Items To Be Moved Enquiry List Details Screen.

Items To Be Moved Enquiry List Details Screen



This screen is displayed when you have entered a valid list number into the Items To Be Moved Enquiry Select List Screen.

This screen displays the current status of the selected list. The top of the screen contains the list header information.

WH280	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Enquire on Items to be Moved			
List number	4	Date created	28/08/94
Instructions	3	Complete	0
Item	Description	Quantity	Location fm
Rotation date	Label		Lot no.
			Location to
			Status
5006	Ballantine's 35x24	10.000	FE2
5016	Ballantine's 24x24	16.000	DE2
5019	Grapefruit Juice x 24	25.000	AE5
			FE1
			L001
			AC3
			B001
			AA2

F3=Exit F5=Refresh F12=Previous

Fields:

List number

The move list number.

Date created

The date the move list was created.

Instructions

The number of actions on the list

Complete

The number of actions that have been carried out and confirmed.



The list is a two-line display containing the following:

Line 1:

Item

Item code of the item.

Description

Item Description.

Lot No.

Lot / batch / serial number of item to be moved.

Line 2:

Rotation Date

The rotation date for the item.

Label

The label number associated with the packaging.

Quantity

The quantity to be moved.

Location Fm

The location code of the location the item is being moved from.

Location To

The location code of the location the item is being moved to.

Status

If 'PEND' is displayed the requested move has been confirmed, but the database has not yet been updated. This will occur if the option 'Are confirmation updates to be performed interactively' in the warehouse profile is set to '0'. In this situation the status will remain pending until the 'Confirmation updates' sub-system utility is started.



Press **F3=Exit**.

Items To Be Put-Away Enquiry



12/DWE

This option enables you to display the status of the put away lists.

Items To Be Put-Away Enquiry Select List Screen

 Select the Items To Be Put-Away option.

This screen allows the selection of a put-away list for the enquiry.

Fields:

List Number

Enter the number of the required put away list for the enquiry. A prompt is available.

 Press **Enter** to display the Items To Be Put-Away
Enquiry List Details Screen.

Items To Be Put-Away Enquiry List Details Screen



This screen is displayed when you enter a valid list number onto the Items To Be Put-Away Enquiry Select List Screen.

This screen displays the current status of this selected list.

WH285	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Enquire on Items to be put-away			
List number	1	Date created 28/08/94	Instructions 15 Complete 0
Item	Lot	Quantity	Label
Description		Expiry date	Rotation date
5013	B002	1.000	AE1
5006		32.000	FE1
5006		16.000	BC4
5006		2.000	BB4
5019	B001	25.000	AC1
5019	B001	25.000	AA2
5019	B001	25.000	AA3
5019	B001	25.000	AA4
5019	B001	25.000	AA5
5019	B001	25.000	AB2
5019	B001	25.000	AB3
5019	B001	25.000	AB4
5019	B001	25.000	AB5
5019	B001	25.000	AC2
			+
F3=Exit F5=Refresh F12=Previous F13=Extended display			

Fields:

List number

The put-away list number.

Date created

The date the move list was created.

Instructions

The number of actions on the list.

Complete

The number of actions that have been carried out and confirmed.



The list may be a one or two line display. The second line of details can be requested by pressing **F13** for 'Extended display'.

Line 1:

Item

Item code of the item.

Lot

The lot / batch / serial number.

Quantity

Quantity to be put away.

Label

The Label number associated with the packaging.

Location Status

The location where the item is to be put away. If no location could be recommended for put away, the serious error message defined in the warehouse profile will be displayed.

Status

If 'PEND' is displayed the requested action has been confirmed but the database has not yet been updated. This will occur if the option 'Are confirmation updates to be performed interactively' in the warehouse profile is set to '0'. In this situation the status will remain pending until the 'Confirm Despatch Updates' sub-system utility is started.

If no location could be recommended the status will be 'LOC.INVLD'.

Line 2:



*Note: Optional - displayed by pressing
F13=Extend display.*

Description

Item Description.

Rotation Date

The rotation date for the item.

Items To Be Picked Enquiry



13/DWE

This option enables you to display the status of the picking lists for sales.



Note: This function is used for sales pick lists only. For production pick lists use the 'items to be picked for production' option.

Items To Be Picked Enquiry Select List Screen



Select the Items To Be Picked from the Action
List Enquiries area of the Enquiries Screen.

This screen allows the selection of a pick list for the enquiry.

Fields:

Picking List Number

Enter the number of the required pick list for the enquiry.



Press **Enter** to display the Items To Be Picked
Enquiry List Details Screen.

Items To Be Picked Enquiry List Details Screen



This screen is displayed when you enter a valid picking list number into the Items To Be Picked Enquiry Select List Screen.

This screen displays the current status of the selected list.

WH290	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Enquire on Items to be Picked for Sales			
List number	5	Date created 28/08/94	Instructions 2 Complete 0
Item	Lot number	Rotation	Quantity Location Status
5006		0/00/00	2.000 FE1
5019	B001	20/08/95	20.000 AC1
F3=Exit F5=Refresh F12=Previous F13=Extended display			

Fields:

List number

The pick list number.

Date created

The date the pick list was created.

Instructions

The number of actions on the list.

Complete

The number of instructions that have been carried out and confirmed.



*Note: The list may be a one or two line display.
The second line of details can be requested by
pressing **F13=Extended display**.*

Line 1:

Item

Item code of the item.

Lot Number

The lot / batch / serial number.

Rotation

The rotation date for the item.

Quantity

Quantity to be picked.

Location

Location to be used if no location can be found, the error message defined in the warehouse profile is displayed here.

Status

If 'PEND' is displayed the requested action has been confirmed, but the database has not yet been updated. This will occur if the option 'Are confirmation updates to be performed interactively' in the warehouse profile is set to '0'. In this situation the status will remain pending until the 'Confirmation updates' sub-system utility is started.

Line 2:

Description

Item description is displayed under the Item Code. This is only displayed if required by pressing **F13=Extended display**.



Press **F3=Exit**.

Orders Awaiting Despatch Assembly Enquiry



14/DWE

This enquiry is used to display details of picking notes generated and awaiting confirmation of assembly. A prompt is provided to browse through outstanding notes. This shows all notes, not just the one related to the default warehouse. If further order information is required, the whole order enquiry may be accessed directly.

Orders Awaiting Assembly Enquiry Selection Screen



Select the Orders Awaiting Assemble option.

This screen enables you to select an order number and a picking note number for display.

```
0E240                ZM - Multi-Currency Company      USER GALBRAIJ  14/03/96
                                                           15:04:50
Orders Awaiting Assembly Enquiry
Order number.....?.. 0001049
Picking note number..?.. 00

F3=Exit F4=Prompt
05-27  Sf      MW      KS      IM      II  PLYM400A PED171S1
```

Fields:

Order Number

Enter the number of the order whose despatches you wish to enquire upon. A prompt of outstanding orders and associated pick notes is available.

Picking Note Number

Enter the number of the picking note you wish to enquire upon. A prompt is available after the 'Order number' has been entered.



Press **Enter** to display the selected picking note details.

Orders Awaiting Assembly Enquiry Display Screen



The details of the picking note are displayed when you have entered a valid order number and picking note number on the Orders Awaiting Assembly Enquiry Selection Screen.



Tip: The **F13=Whole order enquiry** can be used if further information is required.

```

E240          ZM - Multi-Currency Company      USER GALBRAIJ  14/03/96
                                           15:04:55

Orders Awaiting Assembly Enquiry

Order number..... 6001049   Customer.. MJA      000
Picking note number..... 00      Martin Ryland - back ords/part
                                   Unit 11 Green Lane
Date/time created..... 21/12/94 17:44:20      Studley
Delivery required on.... 21/12/94      Warwickshire
Status..... Pick note produced

Ln Item      Description      Quantity      Line
 1 5002      Grapefruit juice      18      Type
                                   Non-kit

F3=Exit  F5=Refresh  F12=Previous  F13=Whole order enquiry

01-02  SF  MW  KS  IM  II  PLYM400A PED171S1
  
```

Fields:

Order Number

Sales order number.

Picking Note Number

The picking note sequence number.

Customer

The 'deliver to' address code of the customer and the 'deliver to' name and address.

Date/Time Created

The date and time the document was created. (This is not the time it was printed.)

Delivery Required On

The customer required delivery date.

Status

Two messages may be displayed. These are:

Not processed - Only appears if Drinks Warehousing is attached for the stockroom, picking has been requested by the sales function, but the request has not yet been issued to warehouse personnel, or if pick notes are currently being produced for an order.

Pick note produced - All documentation has been generated, but despatch has not yet been confirmed.

Line Details

Ln

The sales order line number.

Item

The item code.

Description

The item description.

Quantity

The quantity to pick.

Line Type

There are three possible entries:

Parent - Parent of a kit.

Component - Component of a kit.

Non kit - all other types.

Functions:

F13

Whole Order Enquiry for the selected order.



Tip: If **F13=Whole Order Enquiry** is pressed, the Whole Order Enquiry screen is accessed. For further details of the Whole Order Enquiry see the Enquiries section of the Sales Order Processing Product Information.



Press **F3=Exit**.

Items to be Picked for Production Enquiry



15/DWE

This enquiry is used to display the items to be picked. This is only displayed if Manufacturing is attached.

Fields:

Picking List Number

Enter the number of the Picking List on which you wish to make the enquiry.



Select **Enter** to display details of the items, as in the previous enquiry screens. See 'Items to be picked for Sales'.

Warehouse Movements Enquiry



21/DWE

This option enables you to select and display a range of historical warehouse movements.

Warehouse Movements Enquiry Select Range Screen



Select the Warehouse Movements from the Action History Enquiries area of the Enquiries Screen.

As it is unlikely that the precise details of the movements you wish to enquire upon will be known, it is possible to enter key conditions such as date and item number or label number on which the enquiry will be based. The enquiry can be used in summary or detail. The summary will display a list of movements which meet the criteria, the detail will display the full details of each movement sequentially.

WH350	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Warehouse Movement Enquiry

Item?... 5006 _____

Lot?... _____

Rotation date .. 0/00/00 _____

Pack type ...?... _____

OR

Label?... _____

From date 0/00/00 _____

To date 0/00/00 _____

Summary/detail.. 1 1=Summary
 2=Detail

F3=Exit F4=Prompt F5=Refresh

Fields:

Item

The item code must be entered.

Lot

This is required if the item is lot/batch/serial controlled.

Rotation Date

Enter the rotation date of the item required.

Pack Type

To enquire on the movements of a specific pack enter the label number. If a label number is entered, then 'Item', 'Lot' and 'Rotation date' should not be entered.

Label

A valid label that has been put away.

From Date

First date in the selection of a range of dates. If left blank then all movements up to the 'to' date are included.

To Date

Last date in the selection of a range of dates. If both the 'from' and 'to' dates are left blank then all appropriate movements are selected.

Summary/Detail

- 1 - Summary list of all movements which satisfy the search criteria.
- 2 - Details. The full details of the movements which meet the criteria presented sequentially.



Press **Enter** to display the Warehouse
Movements Enquiry Summary Screen.

Warehouse Movements Enquiry Summary Screen



This screen is displayed when you have pressed Enter after making entries into the Warehouse Movements Enquiry Select Range Screen.

This screen displays a list of movements which meet the selection criteria. The item number and description are followed by a list of the movements. Every movement is between warehouse locations.

WH350	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Warehouse Movements Enquiry - Summary			
Item	5006	Ballantine's 35x24	
S Lot	Rotation date	Pack typ Label	From To Quantity
-	0/00/00	PAL	A1 FE1 .000
-	0/00/00	PAL	A1 FE2 16.000
-	0/00/00	PAL	A1 FE1 16.000
-	0/00/00	PAL	A1 BC4 16.000
-	0/00/00	PAL	A1 BB4 2.000
-	0/00/00	PAL	FE1 FE2 .000
-	0/00/00	PAL	FE1 FE3 5.000
-	0/00/00	PAL	FE1 FE4 5.000
1=Select			
F3=Exit F12=Previous			

Fields:

Lot

The lot / batch / serial number involved in the move.

Pack typ

The code and description of the pack type associated with the items moved.

Rotation date

The rotation date of the items moved.

Label

The label number of the pack moved.

From

The location the items were moved from.

To

The location the items were moved to.

Quantity

The quantity of the items moved.

Select

A '1' may be entered against a movement to display the movement detail screen.



Enter '1' into the Selection field to display the
Warehouse Movements Enquiry Movement
Detail Screen.

Warehouse Movements Enquiry Movement Detail Screen (Option 1)



This screen is displayed when you have entered a '1' next to a line in the Warehouse Movements Enquiry Summary Screen.

This screen displays the full details of the selected movement in the warehouse.

WH350	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Warehouse Movements Enquiry - Detail			
Item	5006	Ballantine's 35x24	
Lot			
Rotation date ..	0/00/00		
Pack type	PAL	Pallet	
Label number ...			
Reason	#1	Put-Away found in error	
Movement type ..	001	Internal Warehouse Movement	
Movement trans .	3	Sundry Movement Planned	
From location ..	FE1	Area.. Main Store	
To location	FE3	Area.. Main Store	
Quantity	5.000		
Event	5 / 2		
User	SP1	Date.. 28/08/94	
Workstation	VRTDSP06	Time.. 12:00:00	+
F3=Exit F12=Previous F14=Summary			

Fields:

Item

The code and description of the item involved in the movement.

Lot

The lot/batch/serial number of the item.

Rotation Date

The rotation date of the item.

Pack Type

The code and description of the pack type associated with the item moved.

Label Number

The label number associated with the pack type.

Reason

The reason code associated with the movement. Module generated movements, such as picked items being moved to the marshalling area do not have reason codes as they are not special case movements.

From Location

The location from where the item was moved. The area containing the location is also displayed.

To Location

The location the item was moved to. The area containing the location is also displayed.

Quantity

The quantity of the item moved. The quantity is measured in the Drinks Inventory Management issue units of measure defined for the item.

Event

An internal two part number relating to processing jobs. The first part is an incremental count number of the job, the second is a sequence number of the processes performed within this job.

User

The user id of the person who confirmed or recorded the movement.

Workstation

The address of the work station from where the movements were confirmed or recorded.

Date

The date the movement confirmed or recorded.

Time

The time the movement was confirmed or recorded.

Functions:

F14

Movement summary. Return to the summary screen.



Roll up and **Roll down** keys can be used to move backwards and forwards through the movements that satisfied the selection criteria.

Serious Errors Enquiry



22/DWE

When non-standard responses are received for instructions, an error condition is recorded. This enquiry shows the serious errors recorded by the system.

The recognition of errors is an important aspect of managing an efficient and effective warehouse.

Serious Errors Enquiry List Screen



Select the Serious Errors option.

This screen lists the current serious errors with the most recent first. The following details are displayed for each recorded error.

WH345	Z1 - Demonstration Company		USER SP1		01/09/94
	Central Warehouse				12:00:00
Serious Error Enquiry					
Sel	Date	Time	Item	User	Reason
-	30/08/94	15:20:40	5037	SP1	Put-Away found in error
-	30/08/94	15:20:38	5037	SP1	Instruction Overriden
-	30/08/94	14:50:33	5036	SP1	Put-Away found in error
-	30/08/94	14:50:30	5036	SP1	Instruction Overriden
-	30/08/94	14:45:28	5036	SP1	Put-Away found in error
-	29/08/94	14:09:04	5029	SP1	Instruction Overriden
-	29/08/94	14:09:04	5029	SP1	Put-Away found in error
-	29/08/94	14:08:47	5025	SP1	Instruction Overriden
-	29/08/94	14:08:47	5025	SP1	Put-Away found in error
-	29/08/94	14:08:25	5022	SP1	Put-Away found in error
-	29/08/94	14:08:24	5022	SP1	Instruction Overriden
I	29/08/94	11:47:45	5001	SP1	Commit found in error
-	29/08/94	11:47:45	5002	SP1	Instruction Overriden
-	29/08/94	11:47:45	5002	SP1	Commit found in error
-	29/08/94	11:47:45	5003	SP1	Instruction Overriden
1=Select					
F3=Exit F5=Refresh F12=Previous					

Fields:

Date

The date the serious error occurred.

Time

The time the serious error occurred.

Item

The item code of the item involved.

User

The ID of the user who actioned the error.

Reason

The reason description associated with the error. This usually gives an indication as to the nature of the error.

Select

Enter a '1' against all errors for which greater detail is required.



Press **Enter** to display details of the first selected error.

Serious Errors Enquiry Display Details Screen



This screen is displayed when you have made valid entries and pressed Enter on the Serious Errors Enquiry List Screen.

This screen displays all of the recorded information associated with the error condition.

WH345		ZM - Multi-Currency Company		USER GALBRAIJ		14/03/96	
		Warehouse #1				15:15:08	
Serious Error Enquiry							
Date.....		14/03/96		User.....		GALBRAIJ	
Time.....		12:33:03		Work station.....		PED171S1	
Event number.....		30 2					
Action list.....		13					
Reason.....		#1		Put-Away Override			
Item.....		100000		Beer			
Lot.....							
Rotation date....		0/00/00					
Pack type.....		C12		cases of 12 bottles			
Label number.....							
Location from....		Planned C04A		Actual C04A			
Location to.....		MA		MA			
Quantity.....		72.000		22.000			
F3=Exit F12=Previous							
01-02		SF		MW		KS IM II PLYM400A PED171S1	

Fields:

Date

Date the serious error occurred.

Time

Time the serious error occurred.

User

The user ID of the person who requested the action or submitted the batch job that caused the serious error, or the used ID of the person who amended action lists to override instructions.

Work Station

The address of the work station from where the user requested the action that caused the serious error. If the error occurred during the processing of a batch job this field displays the name of the job.

Event Number

An internal two part number relating to processing jobs. The first part is an incremental count number of the job, the second is a sequence number of the processes performed within this job.

Action List

The reference number of the action list that produced the serious error. For example, 'move list 2'.

Reason

The reason code relating to the serious error as set up in Inventory descriptions, major type WHRS. The code is followed on the right hand side of the screen with its description.

Item

The item code and description of the item that was involved in the error.

Lot

The lot, batch or serial number of the item.

Rotation Date

The rotation date relating to the item.

Pack Type

The pack type the item is stored in.

Label Number

The label number of the pack.

Location From

Planned - The planned location from where the items were to be moved.

Actual - The actual location from where the items were moved.

Location To

Planned - The planned location for the items.

Actual - The actual location for the items.

Quantity

The quantity involved.



Press **Enter** to display the next selected error.