

-
-
-
-
-

Chapter 1

Maintenance



Advanced Order Entry Maintenance Functions

In Advanced Order Entry Maintenance, you can set up Search Family Codes to group items together according to common characteristics, to allow enhanced item searches.

You can maintain Lot References and their Headers by directly accessing Inventory Management Lot Reference Maintenance facilities. In addition, for Lot controlled items, as well as specifying a particular lot number you can identify the specific characteristics of the Lot and apply a certificate number. This implies that a particular Lot conforms to certain characteristics. Refer to the individual sections for further information.

Search Family Codes



1/AOM

This facility is used to group items together according to common characteristics. The characteristics might be colour, pattern, brand, surface finish, thickness etc.



Warning: The same procedure is used to set up search family codes and Certificate Of Conformance (C Of C) codes, i.e. each code can be used for both a search family code and a C Of C.

Up to 10 characteristics can be defined and are identified by a Search Family Code.

The characteristics may be purely descriptive

for example: colour - red

or may be numeric:

for example: thickness - 0.002cm

The Search Family code can then be useful in two ways:

- For the enhanced item search facility
- To allow detail to be written against Certificates of Conformance



In Advanced Order Entry, the search family codes and descriptions are set up. In Inventory Management, Item Maintenance, the descriptions and values of the characteristics for the individual items may be defined.

Enhanced Item Search

By entering a Search Family Code the user can search for items on the basis of multiple characteristics, for example, you wish to look for items:

- Of a certain brand
- And of a certain colour
- And of a thickness greater than.....etc.

Search Family/C Of C Code Maintenance Screen

-  Select the Search Family Codes option.
-  The screen enables you to select the search family code or Certificate Of Conformance code to be maintained. Enter up to three characters to specify the code. This may be an existing code for amendment or a new code for addition. On pressing **Enter**, the maintenance screen is displayed for the selected code.

This screen enables the characteristics of the search family code or Certificate Of Conformance code to be defined.

IN200		Z1 - Demonstration Company		User SP1		22/09/94 12:34:28	
Search Family / Certificate of Conformance Code Maintenance							
Code.....		CRT					
Description.....		Lab Certificate - Food Content					
Sel	Present Seq	Characteristics Description	Number of decimals	Code (?)	No. of Values		
-	01	Fat Content g/100g	2	---			
-	02	Salt Content g/100g	2	---			
-	03	Carbohydrate g/100g	2	---			
-	04	Protein g/100g	2	---			
-	05	Preservative (Y/N)	-	PACK	Special packaging	002	
-	06	Sweetener (Y/N)	-	STOR	Storage	002	
-	07	Added Colour (Y/N)	-	UCM	Units of Measure	011	
-	---	---	-	---			
-	---	---	-	---			
-	---	---	-	---			
1=Select F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous							

Fields:

Code

This field displays the selected search family/Certificate Of Conformance code.

If the code has already been set up, then the code description is shown and the characteristics which have been defined for the code are listed. If the code has not been set up, these fields are blank awaiting the entry of data.

Description

Enter up to 30 characters which describe the search family/Certificate Of Conformance.

Sel

Select. Enter 1 to maintain the list of permitted values for that characteristic within this search family/Certificate Of Conformance code.



The Maintain Characteristic Values window is displayed.

Present Seq

This field specifies the sequence in which characteristics are presented.

Characteristics Description

Enter up to 20 characters which describe the characteristic you wish to define. Up to 10 characteristics can be defined for each code.

Number Of Decimals

If a characteristic is to have a numerical value, indicate this by keying the number of decimals it is to have in this field. Up to 5 decimals are allowed.

If a characteristic is purely descriptive leave this field blank.

Code

Each characteristic may be optionally defined to a characteristic code. This code must have been set up as a major type in Inventory Management Descriptions maintenance, and a P/V put in the P/V field.

The description codes set up for each major type are the permitted values that can be defined to the characteristic. In order to define a specific description to this characteristic, select it with a 1 in the Sel field.

A prompt is available on valid characteristic codes. The description of the code is displayed beside this field.

No. Of Values

This field shows the number of values currently available for the characteristic code (i.e. the number of description codes set up for the major type in Inventory Management descriptions).

These values can be made available for use with this characteristic by entering a 1 in the selection field. This option is described in Maintenance - Characteristic Values Window (Option 1).



When the required characteristics have been entered, press **F8=Update** to update the details.

Maintain Characteristic Values Window (Option 1)



This window allows the selection of a set of permitted values for the characteristic, within the search family/Certificate Of Conformance code currently being maintained, and is opened when a 1 is entered against a presentation sequence.

The list from which values are selected is the list of values set up for this characteristic code in Inventory Management Descriptions maintenance. This means that different sets of permitted values can be set up for the same characteristic code in different search family/Certificate Of Conformance codes.

Present Sel	Seq	Characteristics Description
-	01	Fat Content g/10
-	02	Salt Content g/l
-	03	Carbohydrate g/l
-	04	Protein g/100g
-	05	Preservative (Y/N)
-	06	Sweetener (Y/N)
I	07	Added Colour (Y/N)
-	-	-
-	-	-
-	-	-

UOM Seq	Units of Measure Code	Measure Description
-	CM	Centimetres
-	FT	Feet
-	GM	Grammes
-	GR	Grammes
-	IN	Inches
-	KG	Kilos
-	LB	Pounds
-	M	Metres
-	OZ	Ounces

F8=Update F12=Previous

1=Select
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous

Fields:

The following details are displayed for each line in the list:

Seq.

Characteristic values are selected by specifying the sequence in which they are to appear on display lists. Only codes with a sequence number will be displayed.

This sequence number must be entered with three digits i.e. 001, 004, 002, etc.

Code

Lists the available characteristic values for the characteristic code, as set up in Inventory Management descriptions maintenance.

Description

Text describing the characteristic value as defined in Inventory Management descriptions maintenance.



When the required values have been selected and sequenced, press **F8=Update** to update the details.

Lot Reference

2/AOM

This option enables access to Inventory Management, Lot Reference Maintenance facilities.



Select the Lot Reference option.



Enter a valid item number a lot reference to amend; or enter a unique number to create a lot reference. and press **Enter** to display the detail screen.



Note: The item number must be entered to prompt on associated lot reference numbers.

This screen enables the maintenance of the header details for the lot requested. Even if parts of the lot are located in different stockrooms the lot header details will be valid for all items included in the lot. If you wish to modify the details for a certain subset of the lot, see Lot Transformation.



Note: The visibility and maintenance of some of these fields is controlled by external flags or applications. (This is particularly relevant if Production is installed).

The lot header information will be held in the system until the lot number itself is purged using the Delete FIFO/lot utility.

The upper part of the screen identifies the item and lot number for which maintenance has been requested. The lower part lists the lot header details specifically required for this item.

The current data for the lot, if there is any, is displayed.

IN215	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	26/06/96
			10:51:34
Lot Header Maintenance			
Item.....	1352_LOT		
Lot reference.....	LOT02		
Production date.....	26/06/96	Time.....	10:37
Expiry date.....	26/02/08	Time.....	0:00
First available date....	26/06/96	Time.....	0:00
Last available date.....	26/02/98	Time.....	0:00
Stock status.....?	—		
Reason code.....?	—		
Potency.....	00.00000 %		
Grade.....	AVE Average Quality		
C-of-C reference.....	NER		
Suppliers Lot ref.....	_____		
F3=Exit F4=Prompt F12=Previous F13=Grades F14=Status F15=Potency			
F16=Adjust active ingredient F17=Cert of conformance F21=Text			
10-27 SF MW KS IM II KENB20A PET166S2			

Fields:

Production Date

This is the date on which the lot is manufactured or received. The field will default to be the current date but may be any previous date. If not entered it can be calculated back from the expiry date using the shelf life of the item.

If the lot is being received by the Purchase Management or Production applications then either production data or expiry date must be entered. If the lot is being received by the Inventory application the fields are not mandatory.

This only applies if the item lot is being received for the first time. Once the lot exists both the production and expiry dates are not maintainable.



Warning: The production, expiry and first and last available times are displayed if the 'Display Lot Time' field on the Lot Header Parameters screen, in Item Maintenance is set to 1.

Production Time

This cannot be changed once the lot has been created and is for memo purposes only.

Expiry Date

This is the date on which the shelf life of the item expires.

If not entered, it is calculated by adding the shelf life to the production date. If the lot is being received by the Purchase Management or Production Applications then either the production or expiry date must be entered. If the receipt is via the Inventory application the fields are not mandatory.

Once the lot exists, the production and expiry dates are not maintainable. Enter a date not less than today's date. If entered the production date can be calculated by subtracting the shelf life from the expiry date.

Expiry Time

The time at which the shelf life of the item expires.

First Available Date

This field is always maintainable. If entered it must be greater or equal to the production date.

All lots with the first available date greater than the current date will normally be automatically frozen. If not entered it will be generated by adding the release time into the production date.

First Available Time

Enter a valid time, this time is for memo purposes only. If the production date is equal to the first available date then the first available time must be equal to or greater than the production time.

Last Available Date

This field is always maintainable. If entered it must be greater than the first available date but less than or equal to the expiry date.

All lots with a last available date less than the current date will normally (if there is no stock status) be frozen automatically. If not entered, the date will be generated.

Last Available Time

Enter a valid time. If expiry date is equal to the last available date then last available time must be less than or equal to expiry time.

Status Code

Enter a stock status code chosen from those defined on the description file against major type STKS.

The stock status code is used as an override to the availability dates, to determine if a lot quantity is to be available or classed as frozen stock.

If stock status is left blank the availability dates will be used to move stock in and out of the frozen stock.

Stock statuses are divided into available or not available by use of the 7 digit 'limit' field held against the stock status descriptions codes on the descriptions file. If the seventh digit is set to 1 the stock status indicates that the lot will be made unavailable. If set to any other value the lot will be made available.

Reason Code

Enter a reason code chosen from those defined on the descriptions file against major type SSRC.

This code can only be entered if the stock status code is changed or is blank initially and indicates why the status of the lot was changed.

Potency

Potency is a percentage i.e. the potency you specify here is the number of parts of active ingredient per hundred parts. This is the potency of the whole lot irrespective of which stockroom the lot is located in.



*Note: This field is only displayed if the Potency
Required flag on the Lot Header Parameters
Maintenance screen is set to 1 (yes)*

Grade

A grade code chosen from those defined on the descriptions file against the major type GRAD. This is the grade of the whole lot irrespective of which stockroom the lot is located in.



*Note: This field is only displayed if the Grade
Required flag on the Lot Header Parameters
Maintenance screen is set to 1 (yes)*

C Of C Reference

Enter a Certificate of Conformance reference, to be assigned to this lot. The values for this C Of C are entered when the lot is first received into Inventory.

Supplier's Lot Reference

Enter up to 36 alphanumeric characters to specify the lot reference allocated by the supplier.

Functions:

F13

Grades. Enable lot grade history display

F14

Status. For an existing lot, display the Stock Status History Enquiry

F15

Potency. Displays lot potency history

F16

Adjust active ingredient

F17

Certificate of Conformance. Review Certificate Of Conformance details

F21

Text Entry. This displays the Maintain Text window where you enter or select a Usage Code and a Language Code for multi-lingual text entry. When you press **Enter**, the Item Text window is displayed. This is where you can enter text in the selected language to be displayed or printed on external documentation, for example, despatch notes, according to the usage code selected.



You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is available.



Note: Language codes do not need to be selected in order to print text in the native language.

Certificate Of Conformance



3/AOM

For lot controlled items, as well as specifying a particular lot number, you can identify the specific characteristics of the lot and apply a certificate number. This implies a particular lot conforms to certain characteristics, for example:

- It is guaranteed to be a specific shade
- The thickness must be at least XXmm
- The alcohol content must be at least 11%

During order entry, the user can then find the lot that best conforms to the customer requirements, and immediately allocate the stock to the lot specific customer order.

C Of C Maintenance Screen

The procedure enables you to maintain or create Certificates Of Conformance. A Certificate Of Conformance reference is assigned to a set of characteristics pertaining to a Certificate Of Conformance code. The values or descriptions of the characteristics are then defined. This reference may then be linked for enquiry or allocation purposes to one or more items that conform to the characteristic values entered.



Select the Certificate Of Conformance option.

This screen enables the selection of an existing Certificate Of Conformance for maintenance, or the assignment of a Certificate Of Conformance code to a new reference.

IN600	Z1 - Demonstration Company	User SP1	22/09/94 12:35:19
Maintenance : Certificate of Conformance Reference			
Certificate of conformance reference.. SCR3094			
Certificate of conformance code....?.. CRT			
F3=Exit F4=Prompt			

Fields:

Certificate Of Conformance Reference

Enter an existing reference to display the details of that Certificate Of Conformance or enter up to 15 characters to specify the reference for a new certificate.

Certificate Of Conformance Code

Leave blank if an existing Certificate of Conformance Reference is entered. To set up a new Certificate Of Conformance enter a code which has previously been set up using the Search Family/Certificate of Conformance Code Maintenance option.

This will indicate which Certificate Of Conformance code is to be assigned to the Certificate Of Conformance reference.



Press **Enter**, and on validation, a maintenance window is opened.

Maintain C Of C Reference Window



This window is opened when a Certificate Of Conformance reference and valid C Of C code are entered on the Maintenance screen.

The screen enables entry/maintenance of the values and descriptions of the Certificate Of Conformance characteristics.

Description	Code (?)
Fat Content g/100g	_____
Salt Content g/100g	_____
Carbohydrate g/100g	_____
Protein g/100g	_____
Preservative (Y/N)	_____
Sweetener (Y/N)	_____
Added Colour (Y/N)	_____

Fields:

Code

Enter the characteristic value. This must be in the format specified using the Search Family Codes option. This field may be prompted on to display valid values.

Functions:

F8

Update details as displayed

F21

Text Entry. This displays the Maintain Text window where you enter or select a Usage Code and a Language Code for multi-lingual text entry. When you press **Enter**, the Item Text window is displayed. This is where you can enter text in the selected language to be displayed or printed on external documentation, for example despatch notes, according to the usage code selected.



You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is

available.



Note: Language codes do not need to be selected in order to print text in the native language.

C Of C Maintain Text Window (F21)

You may define different categories of Certificate Of Conformance text depending on the use for which it is intended.

The screenshot displays a terminal window titled 'IN600 NR - Neil Radford and Co. Ltd User GBJBA1MS 20/06/96 13:43:12'. The main menu shows 'Maintenance : Certificate of Conformance Reference' with fields for 'Certificate of conformance reference.. DRT0001' and 'Certificate of conformance code....?.. NER'. A 'Maintain C-of-C reference' box is open, showing 'ADDITION' and a table with columns 'Description' and 'Code (?)'. Below this, a 'Maintain Text' box is open, showing 'Text Type..... D Certificate of Conformance txt', 'Text Reference.. DRT0001', 'Usage Code...?..', and 'Language Code?..'. At the bottom of the 'Maintain Text' box, function keys are listed: 'F4=Prompt F12=Previous F13=Select existing Text'. At the bottom of the terminal window, more function keys are listed: 'F3=Exit F4=Prompt' and 'F5=Refresh F4=Prompt F8=Update F12=Previous F21=Text'. The status bar at the bottom shows '14-44 SF MW KS IM II KENB20A PET166S2'.

Fields:

Text Type

The text type (i.e. Certificate Of Conformance text) is displayed here.

Text Reference

The Certificate Of Conformance reference number for which text is to be maintained.

Usage Code



Enter a valid usage code to maintain text associated with the Certificate of Conformance.

Enter or select a valid Usage Code (as defined against the major type USGC in Inventory Management Descriptions Maintenance). Usage codes specify where text is displayed or printed, and include:

E - External Text. This additional text will be printed on customer documents in Sales Order Processing. The first few words of external text will be included in the item description search facility when maintaining an item.

I - Internal Text. This text will be printed, if required, on any internal reports referencing this item.

Text may also be maintained against the following codes for memo purposes only:

B - Batch Reference Text

D - Certificate of Conformance

P - Transport Planner

Q - Quality Control

S - Sales Office Memo

T - Technical



Note: Some standard text usage codes are supplied with the Inventory application. Other usage codes may be defined in Inventory Descriptions Maintenance under major type USGC.



Note: To enter text in multiple languages enter a valid Language Code, in addition to the Usage Code, to display the Item Text window.

Language Code

Enter or select a valid language code, in addition to the Usage Code, if you want to enter multi-lingual text. The Item Text entry window is displayed where you can enter text in the language specified. This field is optional and may be left blank if you do not use multi-lingual text entry.



Tip: You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is available.



Note: Language codes do not need to be selected in order to print text in the native language.

Functions:

F13

Select existing text. This lists all currently defined Usage/Language code combinations for the entered text type/text reference. You can select the combination you want to use for entering multi-lingual text.

Maintain C Of C Text Window



This screen enables you to maintain text associated with the Certificate Of Conformance. Up to 198 lines of text may be entered. It is opened when a valid usage code is entered.

Enter new text or make any changes you require using the cursor keys to move to the required point in the text. The display may be started at any text line. Lines may be inserted or deleted.

IN600 NR - Neil Radford and Co. Ltd User GBJBA1MS 20/06/96 13:43:12

Maintenance : Certificate of Conformance Reference

Certificate of conformance reference.. DRT0001

Certificate of conformance code....?.. NER

Maintain

- Text Typ
- Text Ref
- Usage Co
- Language
- F4=Prompt

Maintain C-of-C reference

ADDITION

Certificate of Conformance txt

Lin	Batch	Reference	Text
1			
2			
3			
4			
5			
6			

Position to ___ Insert ___ after ___
Delete ___ from ___

F5=Refresh F8=Update F12=Previous
F13=Change usage/language

F3=Exit F4=Prompt

12-42 SF MW KS IM II KENB20A PET166S2

Functions:

F13

Change Usage/Language. This redispays the Maintain Text window where you can enter or select a Usage Code and a Language Code for entering multi-lingual text.