

-
-
-
-
-

Chapter 1

Maintenance



Introduction to Label Printing



Warning: The Maintenance menu option in Document Processing relates specifically to the Advanced Shipping module for printing shipping labels. The despatch and delivery note printing facility for the Sales Order Processing module is set up in the Processing menu option in Document Processing.



In Document Processing, select the Maintenance option.

The Document Processing Maintenance options relate specifically to the Advanced Shipping module for setting up barcode label printing. The Printer Driver Maintenance option is where you set up your dedicated barcode printer. The Document Format Maintenance menu option is where you set up the data stream sequence to be sent to the barcode printer to print your label design.

Document Format Maintenance



1/DYM



Select the Maintenance option in Document Processing.



Note: Before you can set up the Document Format, you must first have set up the printer driver. You do this in Printer Driver Maintenance.

Document Format Maintenance allows you to set up the required data stream that is sent to the dedicated barcode printer for printing shipping labels.

Document Format Maintenance Screen 1



This screen is displayed when you select Document Format Maintenance in Document Processing.

This screen is where you specify the type of document you want to set up for printing. You also enter or select the Format Code for the document type that will be attached to a specific shipping label design.

```
DY200          Z1 - UK Demonstration Company   User: GBUJA1MS   6/02/98
                                                    17:29:34

Document Format Maintenance

Document Type?... __
Format Code...?... __
Based on.....?... __

F3=Exit  F4=Prompt

5-21  SR  MW  KS  CL  IM  DM  II  STUD140  KB  PKH316S1
```

Fields:

Document Type

Enter the document type that you want to set up for printing. The default Document Type set up for the Advanced Shipping module is 30 AS Shipping Labels.

Format Code

Enter the name of the Format Code that you want to define for the shipping label layout.

Based On

If you are setting up a new Document Type/Format Code combination, you can enter the name of an existing Document Type that you want a new document type to be based on. The settings will be duplicated to the new name.



When you have entered the details you require, press **Enter** to display the second Document Format Maintenance screen.

Document Format Maintenance Screen 2



When you have entered the Document Format and Format Code on the first Document Format Maintenance screen, press **Enter** to display the second Document Format Maintenance screen.

This screen displays the printer queue, system library and the name of the dedicated barcode printer that has been set up on Printer Driver Maintenance screens 1 and 2. You can change these details if you require.

```
DY200          Z1 - UK Demonstration Company    User GBJBA1MS    6/02/98
                                           17:36:01

Document Format Maintenance

Document Type.... 30  AS Shipping Labels
Format Code..... C50  Test pack C50
Format Type..... 1   Data Stream
Output Queue..... QPRINT Library.. *LIBL
Printer Device?. INTERMECH AS Shipping Labels Intermec Printer

F3=Exit  F4=Prompt  F12=Cancel

8-21  SR  ML  KS CL IM DM II  STUD140  KB  PKH316S1
```

Fields:

Document Type

This is the document type you entered on the first Document Format Maintenance Screen. This is displayed for information only and cannot be changed.

Format Code

This is the format code you entered on the first Document Format Maintenance Screen. This is displayed for information only and cannot be changed.

Output Queue

This field displays the name of the print queue set up for your dedicated barcode printer. This is where the shipping labels will appear.

Library

This displays the system library set up for the output queue. The default is *LIBL but this can be changed if required according to your System Administrator set-up.

Printer Device

This displays the name of the dedicated barcode printer itself. This is set up in the Printer Driver Maintenance option.



Note: The printer device name is associated with a printer driver program set up in Printer Driver Maintenance. This driver program must be capable of converting the data stream into an appropriate format for the printer set up for the specified output queue.



When you have completed the required fields, press **Enter** to display Document Format Maintenance Screen 3.

Document Format Maintenance Screen 3



When you have pressed **Enter** on the second Document Format Maintenance screen, the third Document Format Maintenance Screen is displayed.

This screen is where you select fields from the displayed Data Dictionary that you want to include in the data stream that is sent to the specified dedicated barcode printer. You select the fields you require and specify the sequence in the data stream that the information is to be sent to the printer. The sequence must correspond with the order of the fields on the shipping label design.

This screen is divided into two halves:

The upper half displays the field selections you have made so far, and the number in the sequence you have specified for each field to be sent in the data stream.

The lower half displays all fields available in the Data Dictionary that can be included in the data stream.

DY200

Z1 - UK Demonstration Company

User GBJBA1MS

6/02/98
17:36:03

Document Format Maintenance

Document Type.... 30 AS Shipping Labels

Format Code..... C50 Test pack C50

Selected Fields

1

CNAM05

Customer Name

SLP05

2

CAD105

Customer Address Line 1

SLP05

3

NAME26

Name

FDEL

4

ADD126

Address Line 1

FDEL

5

CORF52

Consignee Reference Number

ASP52

+

Seq

Field

Len

Dec

Typ

Generic Field

—

NULL

001

0

A

Blank place holder

—

1

001

0

A

Number 1

—

CITD02

050

0

A

ACP02 Contract Header

—

CITM02

035

0

A

Customer's Item Description

—

Customer Item Number

+

Position to File

F3=Exit

F5=Refresh

F8=Update

F11=Delete

F12=Previous

21-64

SP

MW

KS

CL

IM

DM

II

STUD140

KB

PKH316S1

Fields:

Sequence (untitled)

This displays the sequence number in the data stream that the displayed field is to be sent to the dedicated barcode printer.

Selected Fields

This displays the code and description of the fields you have selected to be included in the data stream.



Tip: To include fields in the data stream, enter a sequence number alongside the field you require

from the data dictionary displayed in the bottom half of the screen, and press **Enter**. The field is then displayed in the top half of the screen.

Sequence

Enter a sequence number alongside the field that you want to include in the data stream to be sent to the dedicated barcode printer. The field is then displayed in the top half of the screen.

Field

This displays the JBA database design field name. For JBA purposes only.

Len

This displays the length of the displayed field. This is useful for label designers when arranging data to fit in a label's layout.

Dec

This displays the number of decimal places for the displayed field. This is useful for label designers when arranging data to fit in a label's layout.

Typ

This displays the field type:

P - Numerical field.

A - Alphanumeric field.

Generic Field

This displays the field's description.



Note: The field names and addresses are set up in the Advanced Shipping module.

Position to File

This is a quick search field to quickly scroll through the list of fields. Enter the initial letter of the field you want to locate to. This list automatically positions to the first name in the list that begins with the specified letter.



Tip: To select a field more than once, select the field, press **Enter** to refresh the top list, and then select the field again from the lower list.



When you have finished selecting fields and specifying their sequence in the data stream, press **F8=Update** to update your changes.

Printer Driver Maintenance



2/DYM



Select the Printer Driver Maintenance option in Document Processing.



Note: Before you can set up the Document Format in the Document Format Maintenance menu option, you must first have set up the Printer Driver.

The Printer Driver Maintenance option is where you set up the printer driver program for your specific dedicated barcode printer. You can add new printer drivers or maintain a printer driver that has already been set up.

You can also specify characters that you want to exclude from the data stream that is sent to the printer. This is for situations where characters are known to cause unpredictable results, or for characters that have specific meanings and would print incorrectly.

Printer Driver Maintenance Screen 1



Select the Printer Driver Maintenance option in Document Processing.

This screen is where you add a new printer driver or select an existing printer driver.

DY210	Z1 - UK Demonstration Company	User GBJBA1MS	6/02/98 17:30:14
Printer Driver Maintenance			
Sel	Printer Device	Driver Program	Program Library
			Description
	INTERMECH	DY300	*LIBL
	STEVE	DY300	*LIBL
			AS Shipping Labels Intermec Printer test driver
1=Select			
F3=Exit F6=Add			
8-4 SA MW KS CL IM DM II STUD140 KB PKH316S1			

Fields:

Sel

Enter 1 to select a printer device you want to maintain. This displays Printer Driver Maintenance Screen 3, where you can amend the details that have been set up.

Printer Device

This displays the name of a printer device that has already been added.

Driver Program

This displays the name of the printer driver program.



*Note: The default dedicated barcode printer driver program supplied by JBA for data streams is DY300, held in program library *LIBL.*

Program Library

This displays the program library where the printer driver program is held.



*Note: The default program library that holds the JBA supplied printer driver program for data streams is *LIBL.*

Description

This displays a description of the printer device that has been added.

Functions:

F6

Add. Adds a new printer driver.



Press **F6=Add** to add a new printer driver. This displays Printer Driver Maintenance Screen 2 where you can specify details for a new printer device.

Select a line with 1 to display Printer Driver Maintenance Screen 3 where you can maintain details already set up.

Printer Driver Maintenance Screen 2 (F6=Add)

 This screen is displayed when you press **F6=Add** on Printer Driver Maintenance Screen 1.

This screen is where you enter details about a new printer device. You can also specify characters that you want to exclude from the data stream.

DY210 Z1 - UK Demonstration Company User GBJBA1MS 6/02/98
17:30:25

Printer Driver Maintenance

Printer Device Type... _____

Driver Program..... _____ Program Library _____

Description..... _____

Field Identifiers..... 0 (1=Yes, 0=No)

Character Substitution Table

Char	Sub	Char	Sub	Char	Sub	Char	Sub
■	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-

F3=Exit F8=Update F12=Previous

13-3 SA MW KS CL IM DM II STUD140 KB PKH316S1

Fields:

Printer Device Type

Enter the name of the printer device you want to add.

Driver Program

Enter the name of the printer driver program you want to add.

Program Library

Specify the program library where the printer driver program is held.

 *Note: The default dedicated barcode printer driver program supplied by JBA for data streams is DY300, held in program library *LIBL.*

Description

Record a description of the printer device you are adding.

Field Identifiers

Select from one of the following to specify whether an entry will be mandatory in the Field Identifier field in Document Format Maintenance.

0 - Not mandatory. This is the default.

1 - Mandatory.



Note: Field identifiers are only necessary for those dedicated barcode printers that expect to receive an ID code alongside each piece of data that they receive.

Char

Enter the character that you want to exclude from the data stream.

Sub

Enter the substitution character you want to use to replace the character you specified in the corresponding Char field.



Press **F8=Update** to update the system with the changes you have made. The Printer Driver Maintenance Screen 1 is displayed.

Printer Driver Maintenance Screen 3

 This screen is displayed when you select a line with 1 on Printer Driver Maintenance Screen 1.

This screen is where you maintain details about a printer device that has already been set up. You can also add or delete characters that you want to exclude from the data stream.

DY210

Z1 - UK Demonstration Company

User GBUJA1MS

6/02/98
17:48:11

Printer Driver Maintenance

Printer Device Type...

INTERMECH

Driver Program.....

DY300

Program Library

*LIBL

Description.....

85 Shipping Labels Intermec Printer

Field Identifiers....

0 (1=Yes, 0=No)

Character Substitution Table

Char	Sub	Char	Sub	Char	Sub	Char	Sub
S	Q	-	-	-	-	-	-
&	Q	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-
-	-	-	-	-	-	-	-

F3=Exit F8=Update F11=Delete F12=Previous

13-3

SA

HW

KS CL IM DM II

STUD140 KB

PKH316S1

Fields:

For details of the fields displayed, refer to the field descriptions for Printer Driver Maintenance Screen 2.

User Device Overrides



3/DYM



Select the User Device Overrides option in Document Processing.

This is an optional function in the process for setting up dedicated barcode printer driver programs and specifying data streams. You may want to change the output print queue for a user if, for example, the user sits next to a printer.

User Device Overrides Maintenance Screen

1

 Select the User Device Overrides option in Document Processing menu.

This screen lists all user overrides that have been set up. You can select a user override line to amend override details that are set up, or you can add a new user override.

DY220

Z1 - UK Demonstration Company

User GBJBA1MS

6/02/98
17:30:37

User Device Overrides Maintenance

Sel	User	Doc Type	Format Code	Output Queue	Library
█	CAJBADDB	30	ABC	PRT01	*LIBL
-	GBJBALK0	30	C01	SAVPRT	*LIBL

1=Select

4=Delete

Position to

F3=Exit

F6=Add

8-4

SA

MW

KS

CL

IM

DM

II

STUD140

KB

PKH316S1

Fields:

Sel

Select a line with one of the following:

1 - To select a line to amend the user override details. This displays the User Device Overrides Maintenance Amend Window.

4 - To delete a user override. A message is displayed requesting confirmation of the deletion.

User

This displays the User ID of the user for whom the override is set up.

 *Note: This User ID is expected to be the same User ID the person uses to sign on to the host computer running System 21.*

Doc Type

This displays the type of document the Format Code relates to.

 *Note: The Document Type and Format Code are set up in Document Format Maintenance Screen*

1.

Format Code

This displays the name of the format code the override is set up for.

Output Queue

This displays the name of the override output queue.

Library

This displays the name of the library where the output queue is held.



*Note: The default program library that holds the JBA supplied printer driver program for data streams is *LIBL.*

Functions:

F6

Add. This adds a new override.



Press **F6=Add** to add a new user override. This displays the User Device Overrides Maintenance Add Window.

Select a line with 1 to display User Device Overrides Maintenance Amend Window to maintain user override details already set up.

User Device Overrides Maintenance Amend Window

 This window is displayed when you select a user override with option 1 on the User Device Overrides Maintenance Screen 1.

This window displays details recorded about the user device override. The Output Queue and the Program Library can be changed if required for the User/Format Code.

DY220Z1 - UK Demonstration CompanyUser GBJBA1MS6/02/9817:59:15

User Device Overrides Maintenance

Sel	User	Doc Type	Format Code	Output Queue	Library
1	CAJ				*AMEND
-	GBJ				

User ID..... CAJBADDB

Document Type .?. 30

Format Code.?. ABC

Output Queue..... PRI01Library..... *LIBL

Hold? 1 (1=Yes, 0=No)Save? 1 (1=Yes, 0=No)

Forms ID..... JUNK

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous

1=Select

F3=Exit F6=

15-35

SA

MW

KS CL IM DM II

STUD140 KB

PKH316S1

Fields:

User ID

This displays the User ID for whom the override is set up.

Document Type

This displays the type of document to which the Format Code relates.

 *Note: The Document Type and Format Code are set up in Document Format Maintenance Screen 1.*

Format Code

This displays the name of the format code to be overridden.

Output Queue

This displays the name of the output queue to override to.

Library

This displays the name of the library where the override output queue is held.



*Note: The default program library that holds the JBA supplied printer driver program for data streams is *LIBL.*

Hold?

Enter one of the following to specify whether the system should hold prints for the User/Format Code:

0 - Do not hold prints.

1 - Hold prints.



Note: The default is 0 - Do not hold prints.

Save?

Enter one of the following to specify whether the system should save prints for the User/Format Code:

0 - Do not save prints.

1 - Save prints.



Note: The default is 0 - Do not save prints.



Press **F8=Update** to update the system with the changes you have made and to display the User Device Overrides Screen 1.

User Device Overrides Maintenance Add Window

 This window is displayed when you press **F6=Add** on the User Device Overrides Maintenance Screen 1.

This window displays blank fields for you to specify the required user device override details.

DY220Z1 - UK Demonstration CompanyUser GBJBA1MS6/02/9817:30:37

User Device Overrides Maintenance

Sel	User	Doc Type	Format Code	Output Queue	Library
-	CAJ				
-	GBJ				

User ID.....

Document Type .?.

Format Code.?.

Output Queue.....Library.....

Hold? 0 (1=Yes, 0=No)Save? 0 (1=Yes, 0=No)

Forms ID.....

F3=Exit F4=Prompt F8=Update F12=Previous

1=Select

F3=Exit F6=

9-35

SA

MW

KS CL IM DM II

STUD140 KB

PKH316S1

Fields:

For details of the fields displayed, refer to the field descriptions for User Device Overrides Maintenance Amend Window.