

-
-
-
-
-

Chapter 1

Maintenance



Purchase Management Set Up Data

This section of the information is for use during the set-up of the system, and covers the configuration of Purchase Management and Master File maintenance procedures.

Company Profile

1/PMU

A Company Profile must be maintained for each company that you wish to use in Purchase Management.

This Company Profile controls the working environment by specifying such things as:

- The defaults for data entry used throughout Purchase Management.
- Details of other applications attached to Purchase Management.
- The numbering systems to be used for documentation.
- The company code of the Advanced General Ledger company with which this Purchase Management company is associated.
- Details used by Requisitioning and Advanced Receiving, if these applications have been installed.



Note: You should take care when amending existing profiles due to the effect that the amendment may have on data already in Purchase Management.

Maintain Profile Records Screen 1



Select the Maintain Company Profiles option to select the Purchase Management Company Profile you want to maintain.



To create a new Company Profile, enter the new code and press **Enter**.



Tip: It is recommended that new companies are created using the Copy Company facility as this method will normally result in you having to enter less set-up data.

This screen lists the Purchase Management companies for which you have authorisation. You choose the Company Profile which you wish to maintain by putting a 1 against it.

PM003	Purchasing Company Profile	User GBUAUP2	26/03/98 15:18:05
Maintain Profile Records			
Sel	Company		
1	ZZ GB - ALTERNATE DEMO CO.		
-	Z1 DEMONSTRATION COMPANY		
-	Z2 Demonstration Company		
-	Z3 Demonstration Company		
Enter New Company _			
1=Select			
F3=Exit			
5-3 SA MW KS CL IM DM II MARVIN KB PKH316S1			

Fields

Sel

To maintain a company profile, enter 1 against the company you require.

Company

Displays a list of the companies you have authorisation for.

Maintain Profile Records Screen 2



This screen is displayed when you have selected the company you wish to maintain and press **Enter** on the first screen.

This screen is where you specify the defaults to be used within the company you have selected.

PM003	Purchasing Company Profile		User SP1	31/08/94
Maintain Profile Records				
Company Code: Z1		Name: <u>Demonstration Company</u>		
Address 1..		<u>Demonstration Company</u>		
Address 2..		<u>Clews Road</u>		
Address 3..		<u>Oakenshaw</u>		
Address 4..		<u>Redditch</u>		
Address 5..		<u>England</u>		Post code.. <u>B98</u>
Telephone..		<u>0123 456 7890</u>	Fax Number.. <u>0123 456 7899</u>	
Address Defaults:				
Supplier Sales Office address sequence number...		<u>000</u>		
Receiving Address supplier		<u>PMSUP</u>		
Receiving Address default sequence number		<u>001</u>		
Purchasing Defaults:				
Delivery Instructions - Item Prefix.....		<u>1</u> 1=G,2=I,3=S		
Booking in point		<u>1</u>		
Output Queues:				
Reports.....	<u>QPRINT</u>	Hold 0=No,1=Yes	<u>1</u>	Library.... <u>QGPL</u>
Orders.....	<u>QPRINT</u>		<u>1</u>	
GRNs/Labels.	<u>QPRINT</u>		<u>1</u>	
Reject Note.	<u>QPRINT</u>		<u>1</u>	
F3=Exit (no update) F8=Update complete F12=Previous screen				

Fields:

Name

Enter a suitable name for this company. If a name has been set up in Application Manager it will appear here; otherwise enter a suitable name.

Address Lines Telephone & Fax Number

Enter the address and telephone numbers which are to be printed when orders are produced by Fax.

Supplier Sales Office Address Sequence Number

Each supplier account may have several addresses set up, each identified by a sequence number. Enter the sequence number which will most often be used.

Receiving Address Supplier

Receiving addresses are held in Purchase Management as dummy suppliers. Enter a supplier account code to be used to hold the receiving address.

Receiving Address Default Sequence Number

Each receiving address will have its own sequence number. Enter the sequence number which will most often be used.

Delivery Instructions Item Prefix

Prefix used by the system to store access Delivery Instructions. Enter any non-blank free text, for example, DELINS.

Booking In Point

Goods received in Purchase Management can be brought in to any one of three locations:

- 1 - Goods Inwards.
- 2 - Inspection.
- 3 - Stores.

The location chosen may be changed for individual receipts when they are entered at Goods Receipt. Specify the most commonly used to set the default. This default can be overridden at stockroom level

Output Queues

Enter the printer output queue required for Reports, Orders, GRNs/Labels and Reject Notes. Queues entered here will override any set up in Application Manager User Profiles.

For more information about Output Queues and Libraries see the Machine Manager section of the System Manager Manual.

Hold

- 0 - The output on the Output Queue is released automatically.
- 1 - The output on the Output Queue is held until you release it.

Library

The library in which the output queue resides.



Press **Enter**. On Pressing **Enter** the System Tailoring screen is displayed (Maintain Profile Records screen 3).

Maintain Profile Records Screen 3 (System Tailoring)



This screen is displayed when you have completed the fields you require and pressed **Enter** on Maintain Profile Records Screen 2.

This screen allows you to specify which other applications are attached to the Purchase Management system and to control the way in which Purchase Management works for this company.

PM003	Purchasing Company Profile	User: GBJBANB4	26/02/98 09:26:37
Maintain Profile Records			
Company Code: Z1 Name: Demonstration Company			
System Tailoring:			
Do you wish to access the Accounts Payable log?.....		1 (0=No,1=Yes)	
Retain Accounts Payable log dissections?.....		0 (0=No,1=Yes)	
Goods Received Notes to print?.....		1 (0=No,1=Yes)	
Goods Received Labels to print?.....		1 (0=No,1=Yes)	
Invoice Match Inhibit if goods NOT in Stores location?..		0 (0=No,1=Yes)	
Update Current Price at:- Order Creation?		1 (0=No,1=Yes)	
Invoice Match?.....		1 (0=No,1=Yes)	
Blank Supplier after Order Entry?		0 (0=No,1=Yes,2=All)	
Print Invoice Matching detail?		1 (0=No,1=Yes)	
Item Receipts - Enter the number of days forward of due date that delivery will be accepted.....		030	
General Ledger Company Code		Z1	
Allow transfer/adjustment issues from warehouses?.....		1 (0=No,1=Yes)	
F3=Exit (no update) F8=Update complete F12=Previous screen			

Fields:

Do You Wish To Access The Accounts Payable Log?

If Accounts Payable is in use, enter:

0 - If purchase receipts are not to be matched against invoices on the Accounts Payable Log.

1 - If purchase receipts are to be matched against invoices on the Accounts Payable Log.

Retain Accounts Payable Log Dissections?

0 - To overwrite those details with dissections entered in Purchase Management invoice matching.

1 - To retain the original Accounts Payable log details entered from the supplier's invoice

Goods Received Notes To Print?

0 - To disable the printing of GRNs.

1 - To enable the printing of GRNs.

Goods Received Labels To Print?

- 0 - To disable the automatic printing of Labels at receipt time.
- 1 - To enable the automatic printing of Labels at receipt time.

Invoice Match Inhibit If Goods Not In Stores Location?

- 0 - To allow matching of all receipts.
- 1 - To inhibit the matching of receipts with invoices while goods are in goods inward or inspection.

Update Current Price At Order Entry? / Invoice Match?

If the price of an item is altered during Order Entry or Invoice Matching then:

- 0 - Doesn't update the Item/Supplier file.
- 1 - Automatically updates the Item/Supplier file.

Blank Supplier After Order Entry?

- 0 - To retain the supplier details from the previous order.
- 1 - To discard the supplier details from the previous order.

Print Invoice Matching Detail?

- 0 - If you do not require an automatic print out. In this case it can be done manually via Accounts Payable.
- 1 - Invoice matching details are printed automatically when the invoices are matched.

Item Receipts

Enter the number of days early that delivery of ordered goods will be accepted.

General Ledger Company Code

Enter the company code of the Advanced General Ledger company with which this Purchase Management company should be associated.



Note: If the Advanced General Ledger company is entered, it must be a valid Advanced General Ledger company. Purchase Management will use the default base currency code of this company and will determine whether it is multi-currency.



Note: The Accounts Payable company used by this Purchase Management company is determined by the selection of this Advanced General Ledger company code. A Purchase Management company will use any Accounts Payable company which interfaces to the Advanced General Ledger company specified here.

Allow Transfer/Adjustment Issues From Warehouse

Enter one of the following:

0 - If you do not want Purchase Management to perform stock updates to Warehousing.

1 - If you do want Purchase Management to perform stock updates to Warehousing.



Press **Enter** to display the Maintain Profiles
Records screen 4 (Profile numbering screen).

Maintain Profile Records Screen 4 (Profile Numbering)



This screen is displayed when you have completed or amended the system tailoring fields on Maintain Profile Records Screen 3 and pressed **Enter**.

This screen allows you to enter information including Automatic Order Numbering for Purchase orders, Goods Received Notes, Rejection Notes and also Currency Defaults.

PM003	Purchasing Company Profile	User SP1	31/08/94 10:38:23
Maintain Profile Records			
Company Code: Z1 Name: Demonstration Company			
Order Numbering:			
Automatic Order Numbering?.....		1	(0=N,1=Y)
Start Number... 000000		Ending	999999
Last Order number used.....			000002
Order Number Prefix.....			-
Goods Received Note Numbering:			
Automatic Goods Received Notes numbering?.....		1	(0=N,1=Y)
Start Number... 0000000		Ending	9999999
Last GRN number used.....			0000000
Rejection Note Numbering:			
Rejection Notes to print?.....		1	(0=N,1=Y)
Start Number... 00000		Ending	99999
Last Rejection Note number used..			
Currency Defaults:			
Which Conversion Rate		Orders?..	PERD Receipts ?.. PERD
Code defaults are used?			
F3=Exit (no update) F4=Prompt F8=Update complete F12=Previous screen			

Fields:

Automatic Order Numbering?



Note that a system generated order number may be overridden during order entry.

0 - To enter unique order numbers manually.

1 - To generate order numbers automatically.

Start Number

The first Order number to be used.

Ending

The last permissible Order number.

Last Order Number Used

The last Order number generated.

Order Number Prefix

A single character used to prefix the order number should be entered here if automatic numbering is specified. This can be useful in a multi-company environment, so that orders for different companies can be easily distinguished; or to distinguish sales from purchase orders.

Automatic Goods Received Note Numbering?

0 - To enter unique GRN numbers manually.

1 - To generate GRN numbers automatically.

Start Number

The first GRN number to be used.

Ending

The last permissible GRN number.

Last GRN Number Used

The last GRN number generated.

Rejection Notes To Print?

0 - No rejection notes are produced for return of goods.

1 - The system produces rejection notes for return of goods.

Start Number

The first Rejection Note number to be used.

Ending

The last permissible Rejection Note number.

Last Rejection Note Number Used

The last Rejection Note number generated.

Which Conversion Rate Code Defaults Are Used?

Enter the rate code (set up in the Advanced General Ledger) to be used for the conversion from prime currency to base currency on Orders and Receipts.



On selecting update, the current values on the screen, and previous screens, are written back to the Company Profile record. Update can be selected on this screen or subsequent screens. When you press **Enter**, the Maintain Profile Records Screen 5 (Ranges Screen) is displayed.

Maintain Profile Records Screen 5 (Ranges)



This screen is displayed when you have completed the numbering fields on Maintain Profile Records Screen 4 and pressed **Enter**.

This screen allows you to enter the Company Profile ranges required.

PM003	Purchasing Company Profile	User SP1	31/08/94 10:38:28
Maintain Profile Records			
Company Code: Z1 Name: Demonstration Company			
Purchasing Officer Range:			
Purchase Officer to be mandatory? (0=N,1=Y).... 0			
Indicate the Purchasing Officer range associated with this company:-			
Starting Purchasing Officer.. Ending.. 99999			
Item Class Range:			
Indicate the Item Class range associated with this company:-			
Starting Item Class.. Ending..			
F3=Exit (no update) F8=Update complete F12=Previous screen			

Fields:

Purchase Officer To Be Mandatory?

0 - A Purchase Office is not mandatory.

1 - A Purchase Officer must be entered.

Starting Purchasing Officer

The first Purchasing Officer Number to be used.

Ending

The last Purchasing Officer number permissible.

Starting Item Class

The first item class code.

Ending

The last permissible item class.



When you select update, the current values on the screen, and previous screens, are written back to the Company Profile record.

Update can be selected on this, or on subsequent, screens.



When you press **Enter**, the Maintain Profile Records Screen 6 (Requisitions screen) is displayed, if the Purchase Requisitioning application is being used. If Purchase Requisitioning is not being used, the procedure will be completed.

Maintain Profile Records Screen 6 (Requisitions System Options)



This screen is displayed when you have completed or amended the range fields on Maintain Profile Records Screen 5 and pressed **Enter**.

This screen allows you to enter selection criteria for the Requisitions System Options.

PM003	Purchasing Company Profile	User SP1	31/08/94 10:38:30
Maintain Profile Records			
Company Code: Z1 Name: Demonstration Company			
Requisitions System Options:			
Order class for sourced requisitions..... 1 1 - 4			
Release flag value on creation of requisition... 1			
New order flag default value..... 1 (0=No,1=Yes)			
New order created on change of Purchase Officer. 1 (0=No,1=Yes)			
Requisition Numbering			
Start number..... 0000000 Ending number... 9999999			
Last number used... 15			
Authorisation required for modified sourced requisitions..... 1 (0=No, 1=Yes)			
F3=Exit (no update) F8=Update complete F12=Previous screen			

Fields:

Order Class For Sourced Requisitions

Enter the order class to be assigned to requisitions when they are converted to purchase orders. Since these requisitions are for stock items the order class must be 1, 2, 3 or 4.

For more information about order classes see the Parameters and Miscellaneous Codes section of this manual.

Release Flag Value On Creation Of Requisition

The value entered here will be used as the release flag value on any requisition generated from Inventory, MPS, MRP or DRP. The value can then be amended for individual requisitions, as required



Tip: The next two fields determine how purchase order lines are generated when requisitions are converted to purchase orders:

New Order Flag Default Value

0 - Requisitions are added to the end of, existing, unreleased purchase orders, where supplier/ despatch address/ order class/ stockroom/(purchase officer) match. If a match cannot be found a new order will be created.

1 - Requisitions will force a new order to be created for each combination of supplier/despatch class/stockroom/(purchase officer).

New Order Created On Change Of Purchase Officer

If the New order flag default value (above) equals 0 then:

0 - Do not include purchase officer in the match above.

1 - Include purchase officer in the match above.

If the New order flag default value equals 1 then:

0 - Do not include purchase officer in the combination above.

1 - Include purchase officer in the combination above.

Start Number

The first requisition number to be used.

Ending Number

The last permissible requisition number.

Last Number Used

The last requisition number generated.

Authorisation Required For Modified Sourced Requisitions

This applies to requisitions generated from Inventory, Master Production Scheduling (MPS), Material Requirements Planning (MRP) and Distribution Requirements Planning (DRP).

0 - If no authorisation is required.

1 - If requisitions need to be authorised after amendment.



Select **F8=Update complete**, the current values on the Maintain Profile Records screens are then written to the Company Profile record.

Press **Enter** when you have completed or amended the requisitions system options fields. The Maintain Profile Records (Advanced Receiving Company Profile Window) will be displayed.

Maintain Profile Records (Advanced Receiving Company Profile Window)



This window is displayed when you have completed or amended the requisitions system options fields on Maintain Profile Records Screen 6 and pressed **Enter**.

This window allows you to maintain the Advanced Receiving company profile. It is the final window displayed in the series of screens that make up the purchase management company profile.

PM003	Purchasing Company Profile	User: GBJBALTW	24/10/97 9:43:31
Maintain Profile Records Company Code: Z1 Name: Demonstration Company			
Requisitions System Options:			
Order class for sourced Release flag value on cr	Advanced Receiving Company profile		
New order flag default u New order created on cha	Manual ASN alpha code..... <u>A</u> Next manual ASN number..... <u>23823</u>		
Requisition Numbering Star Last	Allowed delivery time fence.... <u>2</u> Use P/O default landed costs... <u>1</u> (0/1) Accept warehousing defaults... <u>0</u> (0/1)		
Authorisation required f sourced requisitions....	Send major exception messages.. <u>0</u> (0/1) Major exception warning user... <u>GBJBAGL0</u>		
F3=Exit (no update) F8=	Received goods report outq.... <u>QPRINT</u> Library..... <u>QGPL</u>		
F8=Update F12=Previous			
9-63 * MW KS IM DM II EDN400A KB ST0672S1			

Fields:

Manual ASN Prefix

This is a mandatory field. This field determines the starting letter of the automatically generated manual Advanced Shipping Note (ASN) numbers. It can be any value from A to Z.

Next Manual ASN Number

This is a mandatory field. This is the next numeric portion of the manual Advanced Shipping Note (ASN) code.

Allowed Delivery Time Fence

This is a mandatory field. This is the number of days before the delivery is expected, that a receipt is allowed to take place. This is used to ascertain the severity of a receipt exception.

Use P/O Default Landed Costs

This is a mandatory field. This flag determines whether, when a purchase order has attached landed costs, to take them as is or to put the goods into inspection so that further charges to the costs can be made later.

0 - Take as is

1 - Put goods into inspection.

Accept Warehousing Defaults

This flag indicates if you want to accept the defaults set up in the Warehousing application.

0 - Do not accept Warehouse defaults.

1 - Accept Warehouse defaults.

Send Major Exception Messages

This flag determines whether major exception messages should be sent to the user entered in the following field.

0 - No

1 - Yes

Major Exception Warning User

This is a mandatory field. Enter the user profile to be informed when a major exception has taken place. This will allow them to deal with the problem.

Received Goods Report Outq

This is a mandatory field. This determines the output queue that receives the details of the goods that have been delivered.

Library

This is a mandatory field. This determines the library that receives the details of the goods that have been delivered.



Press **F8=Update** to update the database.

Parameter and Miscellaneous Codes

1... **2...** 1/PM

Purchase Management makes extensive use of codes. These codes or parameters serve two purposes:

- Tailoring the system to particular requirements.
- Reducing the amount of keying in of data and improving the accuracy of entries made.

Areas in Purchase Management where these parameters are primarily used are:

- Order entry.
- Returns and adjustments.

The parameters are grouped together in family units. For example all the units of measure are grouped together and all the scrap reasons are grouped together. Each family is identified by its parameter type. Each family member is defined by its parameter detail.

All parameters, whether detail parameters or parameter types, are identified by a parameter ID


For example: Order Class is a parameter type with the parameter ID ORDC The parameter details are the various order classes or different types of order, with parameter IDs from 1 to 8.

Parameter type IDs

Parameter detail IDs

Values

Groups



The standard parameter types needed are:

GUMC

Group Unit of Measure Code (see example above).

ORDC

The order classification defines the type of items ordered. It is specified at Order Header level. Order classes are:

1-4 - Stock orders. Such as orders for Inventory Items into Inventory stockrooms.

5, 7, 8 - Non stock orders. Such as orders for items not defined to Inventory, furniture, paper clips etc.

6 - Service orders.

SCRC

Scrap Reason Codes. These define a reason for returning goods to a supplier, or scrapping goods.

STYP

Schedule Type. Schedule Types define a purchase order as being scheduled, that is the goods ordered on a single order line are to be delivered in more than one drop, on more than one date, according to the schedule defined on the orders. Set up:

- B - Blanket Order.
- S - Scheduled Order.

UOMC

Unit of Measure Code

This allows the processing of non-stock orders, where the price is expressed in a different unit of measure, such as 2 x BX of pens at a price of 2 pence per EA.

XDEF

A user-defined field for an order header prompt, which has one detail parameter, IPRI. The description that you set up will appear on the order header entry/amendment screen. The description displayed and any entry you make in the field beside this description will not be validated and is for memo purposes only. You might want to use this field as a way of separating and selecting purchase orders when running queries.

An audit report showing the changes made is automatically generated when any parameters are updated.

Deleting Parameter Types And Details



Note: Before a parameter type can be deleted all of its associated parameter details must already be deleted.

To delete a parameter detail select it for maintenance.



Press **F11** twice to delete the parameter detail.

To delete a parameter type select it for maintenance.



Press **F11** twice to delete the parameter type.

Parameter File Maintenance Report

When alterations are made to the parameters file a Parameter File Maintenance Report is automatically produced, showing the changes that have been made.

Unit Of Measure Codes

The Unit of Measure Code, UOMC is a parameter type, which works in a slightly different way to all other parameter types.

The parameter details for this type are the various units of measure required for purchasing and receiving of non-stock items. Purchasing units for stock items are set up in Inventory Management.

Each parameter detail within the parameter type UOMC must be associated with a parameter detail from the parameter type Group Unit of Measure Code, GUMC. The group unit of measure code allows us to convert between one unit of measure and another and also to separate from each other units which are not comparable.

To set up units of measure:

- set up the parameter type GUMC.
- add parameter details within type GUMC, one for each group of units required: for example, unit (UN), length (LT) or weight (WT).
- set up the parameter type UOMC, remembering to select Value Required with 1.

Add the required parameter details within the parameter type UOMC, entering the correct group and conversion rate for each one.

Parameter File Maintenance Screen 1



Select Parameters & Miscellaneous Codes from the Purchase Management Maintenance Menu

A list of valid parameter types and their descriptions are displayed for the company.

PM008	Z1 - Demonstration Company	User SP1	31/08/94 10:38:52
Parameter File Maintenance			
Parameter Type...		<u>PTDS</u> Enter PTDS to define new type	
Parameter I.D.:		<u>GUMC</u>	
Type	Description		
GUMC	Group Unit of Measure		
ORDC	Order Classification		
SCRC	Scrap Reason Code		
STYP	Schedule Description		
UOMC	Unit of Measure		
XDEF	User Defined Field		
F3=Exit			

Fields:

Parm Type

You can enter:

PTDS To maintain a parameter type or create a new one. In this case you then enter an existing Parameter Type (for example, UOMC) in the Parm ID field.

An existing Parameter Type such as UOMC. You must then enter an existing Parameter ID (such as EA) in the Parm ID field.

Parm Id

You can enter:

- A new or existing Parameter Type to create or amend , if PTDS has been entered in the Parm Type field.
- A valid Parameter ID if an existing Parameter Type has been entered in the Parm Type field.

Parameter File Maintenance (Parameter Type) Screen 2

This screen allows you to amend / insert details for the parameter types previously entered.

PM008	Z1 - Demonstration Company	User SP1	31/08/94 10:39:05
Parameter File Maintenance			
Parm Type	PTDS		
Parm I.D	GUMC	AMENDMENT	
Description Size (Maximum)....:	30		
I.D. Size....:	4 & Format....: C (C=Character,N=Numeric)		
Description..:	Group Unit of Measure Max size 30		
Value required....:	1=Yes/Blank=No		
F3=Exit F11=Delete F12=Previous			

If amending a parameter type AMENDMENT is displayed at the top right hand of the screen; if adding a new parameter type, INSERTION is displayed.

Fields:

Description Size

Enter the maximum length required for the description of any parameter details within this type. The maximum allowed is 30 characters.

Id Size

The number of characters required for the IDs of parameter details within this parameter type, for example, ORDC is 1, SCRC is 2. The maximum ID size for any parameter is 4 characters.

Format

Enter C if the identifier for this parameter type is alphanumeric, that is A - Z plus 0 - 9. Enter N if only numerics are allowed .

Description

A description for this parameter type. This cannot be left blank. It appears on the list of types on the initial select screen.

Value Required

- 1 - If the parameter has an associated value to be maintained.
- 0 - The parameter does not have a value to be maintained.



Press **Enter**.

Parameter File Maintenance (Parameter ID) Screen 3

This screen allows you to enter a description for the Parameter Type and ID. For an existing parameter AMENDMENT is displayed at the top right hand of the screen. If the parameter is a new one INSERTION is displayed.

PM008	Distribution V3 -> V3 Financials			User GBJBAMV1	8/12/95
	Parameter File Maintenance				10:35:47
Parm Type	GUMC	Group	Unit of Measure Code		
Parm I.D	DF		INSERTION		
Description.:	~~~~~				Max size 30
F3=Exit	F12=Previous				
12-18	SA	MW	KS	IM	II KENB20A PET129S1

Fields:

Parm Type

From select screen.

Parm Id

The parameter code to be updated, from the select screen.

Description

Enter a Description for this parameter detail. Note that the Max. size is indicated.



Press **Enter**.

Purchasing Officer Names

1... **2...** 2/PMM

- This option allows you to maintain codes and names for Purchasing Officers and/or Planners in the company.

Purchasing Officer Maintenance Screen 1



Select the Purchasing Officer Names option.

```
PM167          NR - Neil Radford and Co. Ltd   User GBJBA1MS   23/07/96
                                           9:47:36

Purchasing Officer Maintenance

Enter Purchasing Officer number...?...  _____

F3=Exit  F4=Prompt

05-42    SF      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Purchasing Officer Number

Enter the number of the Purchasing Officer number you wish to amend or create and press Enter. If you do not know the number you require, placing a question mark (?) in the field and pressing Enter, or pressing **F4=Prompt**, displays a list of all Purchasing Officer Numbers already on the system. Select the number you require from the list, by placing 1 against it.



Once an entry is made and **Enter** pressed, the details screen is displayed.

Purchasing Officer Maintenance Screen 2 (Details screen)

This screen enables you to update details for the selected Purchasing Officer.

If the selected Purchasing Officer is found, his/her details are displayed together with AMENDMENT at the top right hand of the screen. Otherwise, a blank screen is displayed with ADDITION.

The Purchasing Officer Number entered on the previous screen is displayed.

PM167	Distribution V3 -> V3 Financials	User GBJBAMV1	8/12/95
			10:50:54
Purchasing Officer Maintenance			AMENDMENT
P.Officer Number...	1		
P.Officer Name.....	Matt Davage		
Extension Number...	246		
F3=Exit F11=Delete F12=Previous [To Select]			
08-35	SA	MW	KS IM II KENB20A PET129S1

Fields:

P Officer Number

From the previous screen.

P Officer Name

Enter the name of the Purchasing Officer. This field cannot be left blank.

Extension Number

Enter the telephone extension number for the Purchasing Office. This field is optional.



Once validation is complete, pressing **Enter** writes the screen details to the Purchasing Officer file, and returns you to the Purchasing Officer Select screen.

Item Supplier Profile



3/PMM

The Item/Supplier Profile keeps the following details of the stock items purchased from each supplier.

- Total quantity of all orders that have been placed with this supplier for this item.
- Total quantity received against these orders.
- Most recent price and discount, or price structures based on quantity bought.
- Lead time.
- Supplier's item reference.
- Various memo fields relating to ordering rules.
- Landed cost details.

The Item/Supplier Profile can be updated in three ways:

- Directly by the user, from the maintenance option.
- At order entry, when a new price is entered.
- At invoice match, when there is a new price on the invoice.

Item Supplier Profile Maintenance Select Screen



Select Item Supplier Profile.

PM165	Z1 - Demonstration Company	USER SP1	22/09/94 17:53:28
-------	----------------------------	----------	----------------------

Item Supplier Profile Maintenance	
Item	?.. 5001
Supplier.....	?.. GS01

F3=Exit	F4=Prompt
---------	-----------

Fields:

Item

Enter the item to be updated. The item must already exist on the item master file in Inventory Management.

Supplier

Enter the supplier code. This must be an existing code in Accounts Payable.



Press **Enter**. The details screen is displayed.

Item Supplier Profile Maintenance Details Screen

This screen allows you to enter Supplier Profile Maintenance Details for the item and supplier entered previously.

PM165	Z1 - Demonstration Company	USER SP1	31/08/94
			10:49:44
Item Supplier Profile Maintenance		AMENDMENT	
Item..... 5001	Suncream Factor 4 225ml		
Supplier.. GS02	Coles Commercial Chemicals Ltd		
	Unit 10		
	Technology Business Park		
	Western Road		
	Thetford		
	Norfolk, Engalnd		
* Profile text exists *			
Current Price..	60.00000	GBP UoM. CA	
Discount.. 10.00	% Lead time in days.. 000	Receipts to date...	.000
Supplier Item CCC01		Orders to date.....	205.000
----- Ordering Rules -----			
Create PO's via requisitions in purchase unit of measure? (0,1) <u>1</u>			
% Basis.. .00	Minimum....	Maximum..	
	Multiples..		

F3=Exit	F11=Delete	F12=Previous	
F13=Price Structures	F14=Landed Costs	F21=Text	

Fields:

Item

The Item Code from the previous screen.

Supplier

The Supplier Code from the previous screen, together with the supplier name and address from the Supplier Master File.

The following details are displayed if the item/supplier combination is found, and AMENDMENT is displayed at the top right of the screen.

If the item supplier combination is not found these fields are blank and INSERT is displayed.

Price

Enter the item's purchasing price in the item's purchasing UOM.



Note: If catchweight is active for this company, enter the item's purchasing price for the unit of measure entered in the UOM field, as follows:

Catchweight items set up as types 1 and 2 must be priced by a secondary UoM.

Catchweight items set up as type 3 and non-catchweight items with a secondary UoM can be

priced by either a primary or secondary UoM.

Non catchweight items are always priced by one of the primary UOMs defined to the item.

UOM

The purchasing unit of measure defined for the item is displayed.



Note: You can enter a valid UOM for the item in this field only if catchweight is active for this company. You can prompt this field to display a list of the valid UoMs that have conversions previously defined in Inventory Management Maintenance. Only the valid UoMs for the item's catchweight type are displayed.

Receipts To Date

Total quantity of this item received from this supplier, in purchase units.

Orders To Date

Total quantity of this item ordered from this supplier, in purchase units.

Current Price

Enter the current price or use **F13=Price** Structures to set up a price structure. This is the price per unit for the purchase unit of measurement displayed.

Currency Code

Displays the supplier's default currency code. This can be changed when the item/supplier profile is first set up. It cannot be subsequently changed.

*

A flashing asterisk is displayed if there is a current price structure in existence.

Discount

The standard discount on this item from this supplier. This discount provides the default for the first line discount on the purchase orders line.

Lead Time In Days

Enter the lead time in days for delivery of this item from this supplier. This value is used in calculations of supplier performance.

Supplier Item

Enter the supplier's item code or reference for this item.

Create Purchase Orders Via Requisitions In Purchase Unit Of Measure

When purchase orders are created through Requisitioning, the unit of measure is the issue unit of measure. If you wish purchase orders to be in the purchase unit of measure, you must convert your quantities from issue units to purchase units. The options are:

0 - No conversion. Purchase Order lines created from Requisitioning will be expressed in the Item Master Issue unit.

1 - Convert to the Item Master Purchasing unit when the Purchase order line is created from Requisitioning.

% Basis

This and the three fields below may be entered for memo purposes only.

- Minimum.
- Maximum.
- Multiples.

Functions:

F13

Review price structures.

F14

Maintain landed costs.

F21

Opens a window which allows text to be set up for this item/supplier.

Item Supplier Profile Maintenance Price Structures Window



F13=Price Structures on the Item Supplier Profile Maintenance screen displays this window.

If no price structures have been set for this item supplier combination, or if a new price structure is selected from the Item Supplier Price Structure Maintenance screen by pressing **F10=Add New Structure**, effectivity dates are requested using the Enter Effectivity Dates window.

PM165	Z1 - Demonstration Company	USER SPI	31/08/94 10:41:15
Item Supplier Profile Maintenance			
		AMENDMENT	
Item..... 5001	Suncream Factor 4 225ml		
Supplier.. GS02	Coles Commercial Chemicals Ltd		
	Unit 10		
	Technology Busine		
	Western Road		
	Thetford		
	Norfolk, Engalnd		
Enter Effectivity Dates From... 010194 To... 311294 F12=Previous			
Current Price..	52.00000	GBP UoM.	CA Last price change..
Discount.. 10.00	% Lead time in days.. 000	Receipts to date...	.000
Supplier Item CCC01		Orders to date.....	205.000
----- Ordering Rules -----			
Create PO's via requisitions in purchase unit of measure? (0.1) 1			
% Basis.. .00	Minimum....	Maximum..	
Multiples..			
F3=Exit F11=Delete F12=Previous			
F13=Price Structures F14=Landed Costs F21=Text			

Fields:

Effective From Date

The date from when the structure becomes active, in the format DDMMYY.

Effective To Date

Last date the price structure is active, in the format DDMMYY.



Note: If requesting a new price structure from the price structure details screen, the entered effectivity dates must not overlap any existing price structures for this item supplier combination.



Press **Enter** to display the Price Structures screen.

Price Structures Maintenance Screen

If you are setting up a new structure, the screen will display with the message 'There are no Quantity Breaks defined for this Structure'.

After the displayed effectivity date range:

- **** EXPIRED **** is shown for an expired price structure.
- **** CURRENT **** is shown for an active price structure.
- **** PENDING **** is shown for a price structure which will become active in the future.

PM171	Z1 - Demonstration Company	USER SP1	31/08/94 10:45:19
Item/Supplier Price Structure Maintenance			
Item.....	5001	Suncream Factor 4 225ml	
Supplier.....	GS02	Coles Commercial Chemicals Ltd	
		Unit 10	
		Technology Business Park	
		Western Road	
		Thetford	
Effective From...	1/01/94	To	31/12/94 ** CURRENT **
Ref	Quantity Break	Price	
001	100.000	60.00000	
002	500.000	52.00000	
003	1,000.000	48.00000	
004	99,999,999.999	45.50000	
Ref.. Quantity.. CA Price... GBP			
F3=Exit F8=Update F10=Add New Structure F11=Delete F12=Previous			
F13=Next Structure F14=Next Item F15=Change Effectivity Dates			

Fields:

Ref.

If amending a price structure, the reference number displayed against each line may be entered to display the line to be amended.

When entering a new price structure your system automatically allocates the reference number. Enter the details in the Quantity and Price fields, and press enter. The new structure will be displayed, with a reference number against it. This field is protected once a line has been selected for amendment.

Quantity

The quantity up to which the associated price will be charged, if the order quantity falls on or below this quantity and above any previously entered quantity.



Note: Quantities entered must be in ascending order and the last quantity in any structure must be set to '99999999.999'.

Price

The price associated with the quantity. It must be in descending sequence, unless the quantity is equal to all 9s'. In this case the price can equal the preceding price.



Note: For catchweight item types, any purchasing price breaks set up are by the primary amount ordered.



Note: When amending a current price structure line, both quantity and price details may be changed. The changed quantity and price must fall between the previous and subsequent quantity and price values.

The details on this screen are written to the Item Supplier Price Structures file once the update function key is taken.



Press **Enter**.



When you have finished creating or amending price structures select **F8=Update**. Press **RESET** and select **F12=Previous** to return to the item/supplier profile:

Functions:

F10

Add new structure.

F13

Next Structure (for this item/supplier combination).

F14

Next Item (for this supplier, even if expired).

F15

Change of Effectivity Dates

Item Supplier Profile Maintenance Landed Costs Screen (F14)



F14 on the Item Supplier Profile Maintenance screen displays the Landed Costs Entry facility.

PM095	Z1 - Demonstration Company	USER SP1	31/08/94 10:47:44
-------	----------------------------	----------	----------------------

Landed Costs Entry

Item..... 5001 Suncream Factor 4 225ml
 Supplier.. GS02 Coles Commercial Chemicals Ltd
 UoM..... CA Cases of
 Currency.. GBP Pounds

Cost Code	Description	Landed Cost	Perc/ Value (1/0)	Cmpd Ind (1/0)	Price Dependent (1/0)
07	Insurance	1.00000	1	0	1
08	Assembly	.25000	0	1	0

F3=Exit F4=Prompt F8=Update F12=Previous

Fields:

Cost Code

Enter a valid landed cost code or use the landed cost code prompt to select a valid code. These are set up in the landed cost codes option in the Purchase Management Maintenance menu. Up to 10 landed cost codes may be entered against an item supplier profile.

Description

Enter a meaningful description of the Landed Cost.

Landed Cost

Enter a percentage or value to be used in the cost calculation. This is expressed in the UOM displayed in the screen. For all items, actual landed costs are calculated by primary UOM.

Perc / Value

This indicator is read from the Landed Cost file, but may be overridden

1 - The Landed Cost is a percentage added to the item cost.

0 - The Landed Cost is a value added to the item cost.

Cmpd Ind

Percentages and values can be compounded. For percentage costs, this indicates whether to compound or accumulate them when applying to the price.

1 - To compound the percentages.

0 - To accumulate the percentages.

For value costs, this indicates whether the value cost is accumulated with the price before applying the percentages, or after

1 - To apply before.

0 - To apply after.

Price Dependent

Price dependent means that the accumulated costs will be calculated and added to the price, giving a value on which the non-price dependent values may be accumulated and calculated.

1 - To specify price dependent.

0 - To specify non-price dependent.



Press **F8=Update** to update the Landed Costs.



Note: The landed costs specified are automatically attached to any purchase order line for the item supplier. You can override the landed costs for a purchase order line if required.

Item Supplier Profile Maintenance Text Window (F21)



To maintain text information for the selected item/supplier combination, press **F21-Text** on the Item Supplier Profile Maintenance Details screen.

This text is used for memo purposes only. You can enter up to 99 lines of text for this Item/Supplier combination.

PM165	ST - JBA System Test Company	USER GBJBARW2	27/10/95 10:06:10
Product Supplier Profile Maintenance			
Product... LADYSH/1		Ladies Shoe 1	AMENDMENT
Supplier.. FS05		Thierry SA 15 Rue de Louvre 75012 Paris Fra	
Current Price. _____			
Discount. _____ % Lea			
Supplier Product.. _____			

% Basis.. _____ .00		Minim Multi	
F3=Exit F11=Delete			
F21=Text			
14-S6		SA MW KS IM II KENB20A PET170S2	

Supplier FS05 Thierry SA
LADYSH/1

1	The supplier despatches items in a pre-
2	packed state
3	
4	
5	
6	

Position to _____ Insert _____ after _____
Delete _____ from _____

F5=Refresh F8=Update F12=Previous

Fields:

Supplier

Supplier Code and name already entered..

Item

The Item Code already entered.

Any existing text for this Item/Supplier combination is displayed.

The following details may be entered:

Position To

The line number at which the display is to start.

Insert/After

The number of text lines to be inserted after the entered line number.

Delete/From

The number of text lines to be deleted starting from the entered line number.



On selecting **F8= Update**, the text lines on the screen are written to the Item/Supplier text file.

Functions:

F5

Refresh the screen to the position first displayed. Text after line 6 is lost unless **F8=Update** is pressed.

F8

Update the Item/Supplier text, and return to the item details screen.

F12

Display the previous screen (no text update).

Delivery Instructions



4/PMM

This procedure maintains a set of delivery instructions for the company. These instructions are assigned to an order in Order Entry and Order Maintenance, and appear on purchase order prints.

Delivery instructions are set up on the Item Specification file using an item created from the 12-character prefix (identified on the Company Profile), and a three-character suffix entered through this maintenance option.

The entry of an existing code permits maintenance and deletion of data. The entry of a new code permits addition of new Delivery Instructions.

Delivery Instructions Maintenance Select Screen



Select Delivery Instructions.

You can select the code for the set of delivery instructions to be maintained.

PM163

Z1 - Demonstration Company

User SP1

31/08/94
10:59:56

Delivery Instructions Maintenance

Code.....?.. 2

Select Delivery Instruction Code

	Code	Description
1	000	On arrival, follow signs to 'Good
-	001	On arrival, report to duty Stores
-	002	Only complete orders will be acce

1=Select

F5=Refresh F12=Previous

F3=Exit F4=Prompt

Fields:

Code

Select or enter an existing code to be update or delete delivery instructions for.
Enter a new code to add a new set of delivery instructions.

A list of valid delivery instruction codes may be prompted on.

Once an entry is made in the code field, the Delivery Instructions Maintenance
Detail screen is displayed.

Delivery Instructions Maintenance Detail Screen

This enables you to maintain the Delivery Instructions for the selected code.

If the code is found, the existing instructions are displayed, with AMENDMENT displayed on the top right hand of the screen. If the code is a new one, the instructions are blank, and INSERTION is displayed.

PM163	Z1 - Demonstration Company	User SP1	31/08/94 11:00:10
Delivery Instructions Maintenance		AMENDMENT	
Code 000			
Delivery Instructions	line 1	On arrival, follow signs to 'Goods Inwards'.	
	line 2	All deliveries must be received before 12.00 noon.	
	line 3		
F11=Delete F12=Previous (Re-select)			

Fields:

Code

The delivery instructions code from the previous screen is displayed.

Delivery Instructions Lines 1 To 3

Enter the instructions pertaining to the code. Three lines of 50 characters may be entered.

On entering the instructions, the item specification file is updated with the code and text.

Functions:

F11

Delete the Delivery Instructions and the related code.

F12

Display the previous screen.

Receiving Addresses

1... **2...** **5/PMM**

To maintain a set of receiving addresses for the company.

Receiving addresses are assigned to an order in Order Entry and Order Maintenance, and appear on purchase order prints.

Receiving addresses are set up on the Supplier Master file using a dummy supplier, identified on the Company Profile, and a three-character code entered through this maintenance option. Receiving addresses can be entered against this account. This can either be done in Accounts Payable or using a separate option in Purchase Management.

Each receiving address is allocated a sequence code and a default code can be entered on the Company Profile to indicate the most usual receiving address. This code will then appear on the order header but can be replaced with another one where appropriate

Entry of an existing code permits maintenance and deletion of addresses. Entry of a new code permits addition of a new Receiving Address.

Receiving Addresses Maintenance Select Screen



Select Receiving Addresses.

You can select the receiving address to be maintained.

PM259 Z1 - Demonstration Company User SP1 31/08/94
11:00:46

Receiving Address Maintenance

Code.....?.. ?__

Select Receiving Address Code

Code	Description
1 001	Demonstration Company (Midlands)
- 002	Demonstration Company (Northern)
- 003	Demonstration Company (Southern)
- 004	Demonstration Company (France)

I=Select

F3=Exit F4=Prompt F5=Refresh F12=Previous

Fields:

Code

Enter or select an existing code for a receiving address to be updated or deleted.

Enter a new code to add a new receiving address.

A list of valid Receiving Address Codes may be prompted on.



Once an entry is made in the code field, the Receiving Address Maintenance Detail screen is displayed.

Receiving Address Maintenance Details Screen

This enables you to maintain the Receiving Address for the selected code.

If the code already exists, the address is displayed, and AMENDMENT is displayed at the top right hand of the screen. If the code is new, the address is blank and INSERTION is displayed.

PM259	Z1 - Demonstration Company	User SP1	31/08/94 11:00:52
Receiving Address Maintenance		AMENDMENT	
Code 001			
ADDRESS - Name		Demonstration Company (Midlands)	
1st line		892 Wheelers Avenue	
2nd line		Edgbaston	
3rd line		Birmingham	
4th line		West Midlands	
5th line		UK	
Post Code		B15	
F11=Delete F12=Previous (Re-select)			

Fields:

Code

The receiving address code from the previous screen is displayed.

Address Name

A name and up to five lines of address with post code may be entered in this and the two fields following

- Lines 1 To 5.
- Post Code.



Press **Enter**.

On entering the name and address the Supplier Master File is updated with the entered details.

Supplier External Text



6/PMM



Select Supplier External Text from the Purchase Management Maintenance Menu.

To maintain external text for a supplier to be optionally printed on the purchase order form.

Supplier External Text Maintenance Select Window

This screen enables you to select the supplier whose external text is to be maintained. Supplier External Text can be printed on purchase orders. The standard Purchase Management search on supplier name is available in order to select the correct supplier.

 *Note: Supplier internal text is set up in the Accounts Payable application.*

PM260Z1 - Demonstration CompanyUser SP131/08/9411:01:15

Supplier External Text Maintenance

Supplier.....?... ?

Supplier Selection

Supplier Search

More: +

A/C Code	CC	Seq	Name and Address
1 FS01	FRF	000	Gaz de Sevres Sud Rue de Maison Rouge Sevres Sud 75017
- FS02	FRF	000	Guy Rolland Pharmaceutique SARL Courcelleur 3 2 Rue de D
- FS03	FRF	000	Michel Brunet Chemicals SA 2 Rue Curmoussy 75006 Paris
- FS04	FRF	000	Thierry Industrie SARL 100 Rue de Marshal Nee Paris Nor
- FS05	FRF	000	Thierry SA 15 Rue de Louvre 75012 Paris France

1=Select
F12=Previous F13=Expand

Fields:

Supplier

Must be a valid supplier code on the supplier master file.

On entering a valid supplier code the external text detail screen is displayed.

 Press **Enter**

Supplier External Text Maintenance Details Window

This enables you to maintain the external text details for the selected supplier.

Any external text found for the supplier will be displayed.

You can enter up to 99 lines of external text for the selected supplier.

PM260 Z1 - Demonstration Company User SP1 31/08/94 11:01:15

Supplier External Text Maintenance

Supplier.....?.. ?

Supplier Text to Print on Order.

Supplier FS01 Gaz de Sevres Sud

1	Please acknowledge receipt of order.
2	
3	
4	
5	
6	

Position to ___ Insert ___ after ___
Delete ___ from ___

F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous

Fields:

Supplier

The Supplier Code from the previous screen

Name

The supplier's name from the Supplier Master File.

Position To

The line number at which the display is to start.

Insert/After

The number of text lines to be inserted after the entered line number.

Delete/From

The number of text lines to be deleted starting from the entered line number.



On selecting **F8=Update** the details are written to the Text File.

Supplier Fax Numbers

1... **2...** 7/PMM

If you have the Cobwebb Fax module it is possible to send your purchase orders by fax transmission rather than printing and posting.

This procedure allows you to maintain as many fax numbers as you wish against the delivery addresses of the supplier. Screens in this procedure are:

- Select
- Details

Supplier Fax Number Maintenance Select Screen

 Select Supplier Fax Numbers.

You can select the supplier you wish to maintain fax numbers for. The Supplier Fax Number Maintenance select screen displays the following field:

Fields:

Supplier

Enter the supplier code for the supplier you wish to maintain fax numbers for.

 Press **Enter**. The Supplier Fax Number Maintenance details screen is displayed.

Supplier Fax Number Maintenance Details Screen

This screen allows you to select the fax number to maintain.

PM261 DB - DB Education Company User VIP 14/07/97 15:22:28

Supplier Fax Number Maintenance

Supplier... GS01 Premier Food and Drug Supplies

Sel.	Add cde.	Fax Number	Description
-	000	01216061399	Head Office Fax

Add cde. 000 Fax. 01216061399 Desc. Head Office Fax

F3=Exit F8=Update F11=Delete F12=Previous

21-21 SF MW KS IM II EDN400A PE9106S2

Fields:

Supplier

The Supplier Code from the previous screen

Name

The supplier's name from the Supplier Master File.

Sel.

Enter 1 to select a current fax number for update or deletion.

Add Cde.

The address code for the supplier.

Fax Number

The fax number, including codes, without any blanks or dashes.

Description.

A description for the fax number. This is particularly useful if the supplier has more than one.



Press **F8=Update** to write the details to the Supplier Fax Numbers file.

User Authority Parameters



8/PMM

This procedure allows you to maintain user-specific authorisation values.

These are used in Goods Receiving and Invoice Matching to check that the user has sufficient authority to confirm a difference in value (under or over), from the original order.

If either the absolute value or percentage of order line value, maintained in this option, are exceeded then the user is prevented from confirming the acceptance.

Screens used in this procedure are:

- Select
- Details

Over Receipts

When a user tries to accept an over receipt the system calculates its value and compares it with the user's authority value. It also calculates the value of the over receipt as a percentage of the original value of the order line and compares this with the user's authority percentage. If either of the calculated values is higher than the user's authorities, the over receipt cannot be completed.

Examples: 100 items are ordered at £1 each but 105 are delivered the system calculates $5 \times £1 = £5$ and $£5 / £100 = 5\%$ and then compares these with the user's authority values.

Considered Complete

When receipts are being entered against an order the user may wish to log an order as complete, even when the goods received are less than those on the original order. When a user tries to do this the system calculates the value by which the receipt is below the original order line value and compares this with the user's authority value.

It also calculates the value of this under-receipt as a percentage of the original value of the order line and compares this with the user's authority percentage. If either of the calculated values is higher than the user's authorities, the order cannot be considered complete.

Examples: 100 items are ordered at £1 each but only 95 are delivered the system calculates $5 \times £1 = £5$ and $£5 / £100 = 5\%$ and then compares these with the user's authority values.

Invoice Matching Authority Value

At invoice match the value on the invoice is often found to be different to that on the original order. When a user tries to amend a value the system calculates the difference between the invoice and the order value and compares this with the user's authority value.

It also calculates the difference as a percentage of the original value of the order line and compares this with the user's authority percentage. If either of the

calculated values is higher than the user's authorities, the invoice match cannot be completed.

This option also involves the selection of a default stockroom for the user.

User Authority Parameters Maintenance Select Screen



Select User Authority Parameters.

This enables you to select the user profile to be maintained. The user profile must have been previously defined to Application Manager.

PM012	Z1 - Demonstration Company	User SP1	31/08/94 11:04:42
User Authority Parameters Maintenance			
Enter User Profile: <u>SP1</u> & Press ENTER to continue.			
F3=Exit			

Fields:

User Profile

The user ID of the user profile you wish to maintain.



Press **Enter**. The details screen is displayed.

User Authority Parameter Maintenance Details Screen

You can update the value and/or percentage of order line value which the user can confirm as an acceptable difference (in Goods Receiving and Invoice Matching).

PM012	Z1 - Demonstration Company	User SP1	31/08/94 11:04:42
-------	----------------------------	----------	----------------------

User Authority Parameters Maintenance

AMENDMENT

Enter authority parameters and default stockroom for User Profile SP1

Authority Value 300.00

Percentage 25.00 %

Default Stockroom ...?.. 01 Central Stockroom

Press Enter to Update File:

F3=Exit F4=Prompt F11=Delete F12=Previous

Fields:

Authority Value

The maximum difference in value that the user can accept.

Percentage

The maximum percentage difference of a line value that the user can accept as a difference.

Either authority value, percentage, or both, may be entered. Both entries cannot be left blank.

Default Stockroom

The normal stockroom at which this user will record purchasing receipts, transfers and adjustments.



Press **Enter**.

Landed Cost Codes



9/PMM



Select Landed Cost Codes from the Purchase Management Maintenance Menu.

This procedure enables you to maintain landed cost code details.

Landed costs are purchasing costs incurred over and above the basic purchase price of goods or services. Each code set up within this option represents a category of landed cost, for example, transportation costs, insurance or excise duty.

Landed costs are used in item supplier maintenance, order line entry/amend and Inventory Management item/stockroom maintenance.

This procedure contains the following:

- Select
- Detail

Landed Cost Code Maintenance Select Screen

You can select the landed cost code to be maintained.

PM098

ST - JBA System Test Company

User GBJBARW2

27/10/95
10:42:14

Landed Cost Code Maintenance

Landed Cost Code?.. ED

F3=Exit

F4=Prompt

05-42

SF

MW

KS

IM

II

KENB20A

PET178S2

Fields:

Landed Cost Code

The Landed Cost Code you wish to maintain.

Placing a ? in the field and pressing Enter, or pressing F4, displays a window list of Landed Cost Codes. Enter 1 against the Code you wish to select. The window will be removed from display and the code you have selected will be entered into the Landed Cost Code field.

 Press **Enter** to display the details screen.

Landed Cost Code Maintenance Detail Screen

You can create and amend details against the selected Landed Costs Code.

PM098	Z1 - Demonstration Company	User SP1	31/08/94 11:05:16
Landed Cost Code Maintenance		AMENDMENT	
Landed Cost Code.....	01		
Description.....	<u>Post & Packaging</u>		
Percent/Value (1/0).....	<u>1</u>		
Compound Indicator (1/0)..	<u>1</u>		
Price Dependency (1/0)....	<u>1</u>		
F3=Exit F11=Delete F12=Previous (To Select)			

Fields:

Landed Cost Code

From the previous screen.

Description

A meaningful description of up to 30 characters. Blank entries are not permitted.

Percent/Value

A Landed Cost Code can be calculated as a percentage or value.

1 - Denotes a percentage of the item cost will apply.

0 - Denotes a cost value per unit of measure for the order line will apply.

Compound Indicator

Percentages and values can be compounded. For percentage costs, this will indicate (when other percentage cost elements are used) whether to compound or accumulate them when applying to the price.

1 - To compound the percentages.

0 - To accumulate the percentages.

For value costs, this will indicate whether the value cost is to be accumulated with the price before applying the percentages, or after

1 - To apply before.

0 - To apply after.

Price Dependency

Price dependent costs will be added to the item costs. This gives a value on which non-price dependent costs will be added and calculated.

1 - To specify price dependent

0 - To specify non-price dependent.



Press **Enter** to accept and display the initial selection screen.

Stockroom Defaults



10/PMM



Select Stockroom Defaults from the Purchase Management Maintenance Menu.

Stockrooms are defined in the Inventory Management Company Profile.


You set up the processing defaults for purchased goods on the Purchase Management Company Profile.

Some defaults may be overridden for individual stockrooms by setting up stockroom default profiles in this option.

You can create and amend the stockroom name, address, phone/fax numbers, contact name and receiving address. You can also use this option to deal with goods received note generation, numbering and printing.

Stockroom Default Maintenance Select Screen

You can select the stockroom for which defaults are to be maintained.



```
PM265                Z1 - Demonstration Company    User SP1          31/08/94
                                                           11:05:31
Stockroom Default Maintenance
Stockroom .....?.. 01
F3=Exit  F4=Prompt
```

Fields:

Stockroom

A valid stockroom code. A list of valid stockrooms may be prompted on.



Enter a stockroom code and press **Enter**. The Stockroom Defaults Maintenance details screen is displayed.

Stockroom Defaults Maintenance Details Screen

This screen allows you to enter details for the stockroom already entered.

PM265	Z1 - Demonstration Company	User SP1	31/08/94 11:05:39
Maintain Stockroom Details			
Stockroom Code.....	01 Central Stockroom	Amendment	
Address.....	892 Wheelers Avenue		
	Edgbaston		
	Birmingham		
	West Midlands		
	UK		
Post Code...	B15		
Telephone Number...	0121 123 4567	Fax Number.....	
Contact Name.....	Ron Johnstone		
Receiving Address Code.....	?.. 001	Booking in Point.. 1 (1,2,3)	
Company/Stockroom GRN Generation.....	0	(0=Company, 1=Stockroom)	
Automatic Goods Received Note Numbering..	1	(0=No, 1=Yes)	
Start Number....	End Number....	9999999	
Last GRN Number used.....			
Goods Receipt Note to Print.....	1	(0=No, 1=Yes)	
Goods Receipt Labels to Print.....	1	(0=No, 1=Yes)	
GRN/Label Print Queue..	QPRINT	Hold 0=No, 1=Yes	1 Library.. QGPL
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Stockroom Code

The stockroom code entered on the select screen.

Address / Post Code Telephone Number / Fax Number / Contact Name

You can enter and amend the stockroom address, Telephone and Fax number and Contact name.

Receiving Address Code

The default receiving address code, which is set up in Maintain Company Profiles, will be displayed here.

It can be overwritten so that you can enter a different receiving address.

Booking In Point

Enter the default location into which receipts are to be booked. When setting the defaults for a stockroom for the first time, the defaults defined in the Maintain Company Profiles option will be in this field. This may be changed for each receipt.

- 1 - Goods Inwards.
- 2 - Inspection.
- 3 - Stores.

If you book directly into stores, stock levels in Inventory Management will be automatically updated. If you book into goods inwards or inspection (options 1 or

2), they will have to be transferred to stores (in the Transfer Goods Location option), before stock levels are updated.

Company / Stockroom GRN Generation.

- 1 - Goods received notes are generated at stockroom level.
- 0 - Goods received notes are generated on a company level.

Automatic Goods Received Note Numbering

- 1 - For automatic generation of GRN numbers.
- 0 - To enter your own unique GRN numbers at order entry time.

Start Number

If you are using automatic numbering key in the first permissible GRN number.

End Number

The last permissible GRN number.

Last GRN Number Used

The last GRN number used will be updated by the system, as each receipt is confirmed.

Goods Receipt Note To Print

- 1 - To enable printing of GRNs.
- 0 - To inhibit printing of GRNs.

Goods Receipt Labels To Print

- 1 - To enable the automatic printing of labels at receipt time.
- 0 - Inhibit automatic printing of labels at receipt time.

GRN/Label Print Queue

Enter the printer output queue required for GRNs/Labels. For information about Queues and Libraries see the Machine Manager section of the System Manual.

Hold

- 0 - The output on the GRN/Label Print Queue is released automatically.
- 1 - The output on the GRN/Label Print Queue is held until you release it.

Library

The library in which the output queue resides.

A separate range of GRN numbers can be used for each stockroom.



Press **F8=Update**.

Application Maintenance File Prints

File prints are available from the File Lists section of the Purchase Management Maintenance menu.

- Parameters & Miscellaneous Codes.
- Purchasing Officer Names.
- Receiving Addresses.
- Delivery Instructions.
- User Authority Parameters.

Each of these tasks submits a batch job to the system, as soon as the appropriate option is selected. These prints consist of a listing of the current records in each file and are particularly useful during the setting up of the system to check that all the correct entries have been made. See the Reports section of this information for further details.