

-
-
-
-
-

Chapter 1

Maintenance



Introduction to Fixed Assets Maintenance

Certain system entities must be set up before Fixed Assets can be of use to you.

The Company Profile

A company profile must be set up for each company used in the Fixed Assets application.

The company profile establishes the application environment, sets control parameters and default options for use in other parts of the application.

Once established, the company profile is not often changed. Access to this facility should be restricted to prevent unauthorised changes.

Book Profiles

A company may wish to account for an asset in a variety of different ways. For example:

- statutory accounts
- management accounts
- corporate reporting
- taxation accounting

A set of financial views or books corresponding with these objectives can be established using the Book Profiles option. Each asset, as it is established, can then be connected to as many of these books as is relevant.

Each book or financial view that is set up can be linked independently to the General Ledger.

The simplest requirements may lead to the creation of two books

- a cost book
- a depreciation book

These are, in fact, all that are allowed in the basic version of the system.


Each book has a valuation method which is related to the accounting purpose for which the book is set up, e.g.

- original cost
- replacement value
- index-linked revaluation
- management revaluation

These values may be further affected by external funding.

The book value can, if required, include the cost of all dependants of the asset in question.

If a book is used for depreciation, you select one depreciation method to be associated with it.



Period Calendar

A calendar for each financial year is required so that depreciation calculations that use working days in a period, or calendar days in a period have a basis for the calculation.

A common period calendar can be set up in the skeleton company ##, or each company may have a separate calendar.

System Reference Codes

The system reference codes are a part of the maintenance data.

The system reference codes are used widely throughout Fixed Assets. The description of each can be changed.

Hierarchy Codes

Hierarchies enable you to group assets by analysis code, or by existing hierarchy.

Example 1

Two assets, one of which is defined as having a location ('LOC') of London, the other of Oxford, can be grouped in a hierarchy of 'South-east region'.

Example 2

A sales hierarchy can contain a group of cost centres ('COS').

Example 3

A computer has been installed in the finance department of the Birmingham office. It will have the following analysis codes:

Asset Type ('ATP') - COMP

Cost Centre ('COS') - 040

Location ('LOC') - BHAM

This asset can be included in the 'Midlands' region and the 'Admin' business function hierarchy.

General Ledger Links

In order to understand this subject you need to be thoroughly familiar with the principles and practice of chart of accounts design and creation.

Each financial book that is set up can be linked to either fiscal or to memorandum accounts. Whether linking is undertaken or not depends on the link indicator within the financial book.

The General Ledger accounts to which postings are made can be generated from the asset analysis codes.

For example, the General Ledger account which holds the monthly depreciation value for computer equipment in Birmingham might be:

43COMPBHAM

This is a sub-ledger account controlling up to a profit and loss ledger account. Monthly depreciation would be debited to the above account and credited to a balance sheet sub-ledger account for depreciation this year. This is account:

5COMPBHAM

The Structured GL Accounts option allows these account numbers to be generated for each asset, if necessary differently for each asset, depending on which financial book is attached to the asset. The depreciation transaction that is created in this way is known as a financial transaction and is one of the General Ledger account type codes grouped together under the reference code 'ACTY'.

Accounting for Assets

In order to see exactly how to set up the structured General Ledger accounts we must go back to basic accounting. Recognising that there are many different ways of achieving an objective within overall professional guidelines, what is presented below is only one way in which accounts might be established and set up in the structured GL accounts facility.

Suppose that in the balance sheet we have set up the following accounts and sub-ledgers:

Account	Account Number	Sub-Ledger
Assets Historic Cost	130	FA1
Asset Additions	230	FA2
Asset Disposals	330	FA3
Accumulated Depreciation	430	FA4
Depreciation This Year	530	FA5
Depreciation Disposals This Year	630	FA6
Creditors Control	700	
Debtors Control	800	
Asset Control A/C Debit	880	
Asset Control A/C Credit	881	
Opening Balance A/C	890	
Contras Suspense A/C	895	
Fut/Prior Period Susp.	899	
Asset Pstgs Susp - DR	990	
Asset Pstgs Susp - CR	991	
General Suspense A/C	998	
Rounding Errors A/C	999	
Rounding Errors - Memo	99M	

If you look at the chart of accounts list for the balance sheet, you will see that most of these accounts are post inhibited because they are controlling sub-ledgers. Within the asset accounts sub-ledgers the accounts are broken down by:

- Account group
- Asset category
- Location

Suppose the profit and loss ledger has the following accounts:

Account	Account Number	Sub-Ledger
Net Profit Memo A/C	M880	
Period Depreciation	4300	DEP
Sale of Assets	8000	DIS
Suspense A/C Debit	9000	
Suspense A/C Credit	9100	

The first two are also in practice, sub-ledger control accounts, in whose sub-ledger the depreciation and disposal postings can be broken down by:

- Account group
- Asset category
- Location

The Life Cycle of an Asset

The life of an asset might be illustrated by the following diagrams (bold figures are the postings for the current transaction).

ACQUISITION

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C	
ASSET ADDITIONS A/C £1000		SALE OF ASSETS A/C	
ASSET DISPOSALS A/C			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C			
DEPREC DISPOSALS THIS YR A/C			
ASSET CONTROL A/C £1000			
DEBTORS CONTROL A/C			
CREDITORS CONTROL A/C			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

RECEIPT OF SUPPLIERS INVOICE (WITH PURCHASE LEDGER INSTALLED)

GENERAL LEDGER BALANCE SHEET LEDGER	
DR	CR
HISTORIC COST A/C	
ASSET ADDITIONS A/C £1000	
ASSET DISPOSALS A/C	
ACCUMULATED DEPREC A/C	
DEPRECIATION THIS YR A/C	
DEPREC DISPOSALS THIS YR A/C	
ASSET CONTROL A/C £1000	£1000
DEBTORS CONTROL A/C	
CREDITORS CONTROL A/C	£1000

GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR
MONTHLY DEPREC A/C	
SALE OF ASSETS A/C	

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

PERIOD DEPRECIATION

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C £107.14	
ASSET ADDITIONS A/C £1000		SALE OF ASSETS A/C	
ASSET DISPOSALS A/C			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C £107.14			
DEPREC DISPOSALS THIS YR A/C			
ASSET CONTROL A/C £1000	£1000		
DEBTORS CONTROL A/C			
CREDITORS CONTROL A/C £1000			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

DISPOSAL - FIXED ASSETS

GENERAL LEDGER BALANCE SHEET LEDGER	
DR	CR
HISTORIC COST A/C	
ASSET ADDITIONS A/C £1000	
ASSET DISPOSALS A/C £1000	
ACCUMULATED DEPREC A/C	
DEPRECIATION THIS YR A/C £107.14	
DEPREC DISPOSALS THIS YR A/C £107.14	
ASSET CONTROL A/C £1000 £800	£1000
DEBTORS CONTROL A/C	
CREDITORS CONTROL A/C £1000	

GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR
MONTHLY DEPREC A/C £107.14	
SALE OF ASSETS A/C £1000	£107.14 £800

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

DISPOSAL - SALES LEDGER INVOICE

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C £107.14	
ASSET ADDITIONS A/C £1000		SALE OF ASSETS A/C £1000 £107.14 £800	
ASSET DISPOSALS A/C £1000			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C £107.14			
DEPREC DISPOSALS THIS YR A/C £107.14			
ASSET CONTROL A/C £1000 £1000 £800 £800			
DEBTORS CONTROL A/C £800			
CREDITORS CONTROL A/C £1000			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

YEAR END TRANSACTIONS

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C £1000	£1000	MONTHLY DEPREC A/C £107.14	
ASSET ADDITIONS A/C £1000	£1000	SALE OF ASSETS A/C £1000	£107.14 £800
ASSET DISPOSALS A/C £1000	£1000		
ACCUMULATED DEPREC A/C £107.14	£107.14		
DEPRECIATION THIS YR A/C £107.14	£107.14		
DEPREC DISPOSALS THIS YR A/C £107.14	£107.14		
ASSET CONTROL A/C £1000 £800	£1000 £800		
DEBTORS CONTROL A/C £800			
CREDITORS CONTROL A/C £1000			

Having followed the progress of an asset through a set of accounts, the following example process adds on the financial transactions code that the Fixed Assets system creates at each stage.

The financial transaction number is shown followed by the description as defined in the General Ledger account types reference code (ACTY). You can change those descriptions to others that are more appropriate or familiar to you, by maintaining reference code ACTY.

ACQUISITION (WITH FINANCIAL TRANSACTION CODES)

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C	
ASSET ADDITIONS A/C £1000[002]		SALE OF ASSETS A/C	
ASSET DISPOSALS A/C			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C			
DEPREC DISPOSALS THIS YR A/C			
ASSET CONTROL A/C £1000[002]			
DEBTORS CONTROL A/C			
CREDITORS CONTROL A/C			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

RECEIPT OF SUPPLIERS INVOICE (WITH PURCHASE LEDGER INSTALLED)

GENERAL LEDGER BALANCE SHEET LEDGER	
DR	CR
HISTORIC COST A/C	
ASSET ADDITIONS A/C £1000	
ASSET DISPOSALS A/C	
ACCUMULATED DEPREC A/C	
DEPRECIATION THIS YR A/C	
DEPREC DISPOSALS THIS YR A/C	
ASSET CONTROL A/C £1000[frPL]	£1000
DEBTORS CONTROL A/C	
CREDITORS CONTROL A/C £1000[frPL]	

GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR
MONTHLY DEPREC A/C	
SALE OF ASSETS A/C	

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

MONTHLY DEPRECIATION (WITH FINANCIAL TRANSACTION CODES)

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C £107.14[325]	
ASSET ADDITIONS A/C £1000		SALE OF ASSETS A/C	
ASSET DISPOSALS A/C			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C £107.14[325]			
DEPREC DISPOSALS THIS YR A/C			
ASSET CONTROL A/C £1000			
DEBTORS CONTROL A/C			
CREDITORS CONTROL A/C £1000			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

DISPOSAL - FIXED ASSETS (WITH FINANCIAL TRANSACTION CODES)

GENERAL LEDGER BALANCE SHEET LEDGER	
DR	CR
HISTORIC COST A/C	
ASSET ADDITIONS A/C £1000	
ASSET DISPOSALS A/C £1000[101]	
ACCUMULATED DEPREC A/C	
DEPRECIATION THIS YR A/C £107.14	
DEPREC DISPOSALS THIS YR A/C £107.14[421]	
ASSET CONTROL A/C £1000 £800[200]	£1000
DEBTORS CONTROL A/C	
CREDITORS CONTROL A/C £1000	

GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR
MONTHLY DEPREC A/C £107.14[325]	
SALE OF ASSETS A/C £1000[101]	£107.14[421] £800[200]

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

DISPOSAL - SALES LEDGER INVOICE (WITH FINANCIAL TRANSACTIONS)

GENERAL LEDGER BALANCE SHEET LEDGER		GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR	DR	CR
HISTORIC COST A/C		MONTHLY DEPREC A/C £107.14	
ASSET ADDITIONS A/C £1000		SALE OF ASSETS A/C £1000 £107.14 £800	
ASSET DISPOSALS A/C £1000			
ACCUMULATED DEPREC A/C			
DEPRECIATION THIS YR A/C £107.14			
DEPREC DISPOSALS THIS YR A/C £107.14			
ASSET CONTROL A/C £1000 £1000 £800 £800[frSL]			
DEBTORS CONTROL A/C £800[frSL]			
CREDITORS CONTROL A/C £1000			

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

YEAR END (WITH FINANCIAL TRANSACTIONS)

GENERAL LEDGER BALANCE SHEET LEDGER	
DR	CR
HISTORIC COST A/C £1000[001]	£1000[003]
ASSET ADDITIONS A/C £1000	£1000[001]
ASSET DISPOSALS A/C £1000[003]	£1000
ACCUMULATED DEPREC A/C	£107.14[323]
DEPRECIATION THIS YR A/C £107.14[323]	£107.14
DEPREC DISPOSALS THIS YR A/C £107.14	
ASSET CONTROL A/C £1000 £800	£1000 £800
DEBTORS CONTROL A/C £800	
CREDITORS CONTROL A/C	£1000

GENERAL LEDGER PROFIT & LOSS LEDGER	
DR	CR
MONTHLY DEPREC A/C £107.14	
SALE OF ASSETS A/C £1000	£107.14 £800

SALES LEDGER	
DR	CR

PURCHASE LEDGER	
DR	CR

General Ledger Accounts

In order to maintain the structured General Ledger accounts, you now need to be clear about:

- the number of financial books (or views), you wish to create
- how you might link one or more to each asset you create (in the basic version you can create and link only the cost book and one depreciation book)
- which General Ledger accounts need to have been set up
- which General Ledger postings you might wish to generate.

Company Profile



Select Fixed Assets company profile, enter the required company in the selection field, and press **Enter** to see the first Maintain Company Profiles screen.

Maintain Company Profiles Screen 1

When you have selected the company you wish to set up or maintain, press **Enter** to see this screen.

FA005 Maintain Company Profiles.		USER FAF8	26/10/95 16:16:14
Company Code.....	F8		
Company Name.....	Fixed Assets V3 Company - F8		
Periods in year.....	12	Year end.....	12
Current period.....	9511	May be used for based on...	1 (0/1)
		Ref Codes include skeleton.	1 (0/1)
Generate Refs.....	1 (0/1)	Last Generated Reference...	00000130
		Last Generated Dep'n Ref...	00000000
GL installed.....	1 (0/1)	GL Company code.....	F8
PL installed.....	0 (0/1)	PL Company code.....	—
SL installed.....	0 (0/1)	SL Company code.....	—
Multi Book.....	1 (0/1)		
F3=Exit F5=Refresh F12=Previous			
07-27 S MW KS IM II EDN400A PED169S1			

Fields:

Company Name

The company name cannot be changed once set up, except via Application Manager.

Periods In Year

Up to 99 periods can be defined for each accounting year. Normally 12 or 13 would be entered.

If this Fixed Assets company is linked to the GL, then the number of periods must be the same as the General Ledger company.

Year End

Enter the period number of the calendar period in which the financial year ends. It must not be greater than the number of periods in the year and must be the same as the fiscal year end on the General Ledger to which it is linked.

Current Period

Enter the accounting period (YYPP) when you want this company to go live. Once set up this value is changed by the period end procedure and should not be changed manually.

May Be Used For Based On

1 - Other companies can access this company's asset data, as a basis for creating their own assets.

0 - No such access is to be allowed.



Note: If you are currently maintaining the skeleton company '##' the system automatically puts 1 in this field.

Ref Codes Include Skeleton

1 - Application reference data codes (not specifically set up for this company) can be selected from the skeleton company '##'.

0 - Codes must be specifically defined for this company.

Generate Refs

1 - The system is to automatically generate a document reference for every transaction. You will not be able to enter your own references.

0 - User-defined references are used.

Last Generated Reference

The latest reference number generated by the system. You can reset this to whatever starting number is required.

Last Generated Dep'n Ref

If automatic reference number generation is not used (i.e. 'Generate Refs' is set to 0), then the system will generate its own reference for each depreciation transaction. The starting number can be set by you. The number can also be reset.

This reference number field is also used for generating references for periodic lease payment transactions.

GL Installed

1 - The General Ledger is installed and is used by Fixed Assets.

0 - General Ledger is not installed.

GL Company Code

If the GL is installed, a GL company must be entered. This is the GL company to which postings will be made if and when initiated through the links established in the financial books. (This is described in the Enquiries and Utilities sections).

PI Installed

1 - Accounts Payable is installed and is used by this application.

PI Company Code

Enter the company against which data is validated.

SI Installed

1 - Accounts Receivable is installed and is used by this application.

SI Company Code

Enter the company against which data is validated.

Multi-Book

1 - This company is to hold multiple depreciation books for its assets. This feature is not available in the basic version of Fixed Assets.

0 - The company is limited to one cost book and one depreciation book for all assets.



Press **Enter** to continue to the second Maintain Company Profiles screen.

Maintain Company Profiles Screen 2

This screen enables you to set up certain defaults. For example, the system can:

- prompt you to maintain one or several of the six facets of asset data.
- prompt you to maintain for each book the depreciation details alone or both these and the revaluation details and/or to create a depreciation journal, whenever the asset is maintained.

The defaults entered here can be overridden later, when entering that task.

FA005		Maintain Company Profiles.		USER FAF8		26/10/95 16:16:40	
Company Code.....		F8					
Company Name.....		Fixed Assets V3 Company - F8					
Major Analysis Types.?		ATP Asset Type					
..?		LOC Location		Mandatory		1 (0/1)	
..?		COS Cost Centre				0 (0/1)	
Base Asset Facilities : Required Default.?							
Base Asset		3		1/3		(0 = no)	
Analysis Types.....		1		0-3		(1 = yes if addition)	
Notepad.....		1		0-3		(2 = yes if amendment)	
Financial Details....		1		0-3		(3 = yes if add or amend)	
External Funding....		1		0-3			
Lease Details.....		1		0-3			
Book Maint. Defaults :							
Details		2		0/2			
Revaluation.....		0		0/2			
Depreciation Journal		0		0/2			
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous							
06-26 SF MW KS IM II EDN400A PED169S1							

Fields:

Major Analysis Types

Up to three major analysis types can be entered. The first code is mandatory and has to be entered. If the second or third analysis types are used, you can choose whether or not to force the person maintaining the asset to input an analysis detail code.

There are a number of typical analysis types provided with the system. It is normally possible to choose your major analysis types from this list.

If the code you enter is already set up on the system, a description will appear when you press **Enter**.

Mandatory

Applies to the second and third major analysis types only.

1 - You must select a detail code from this type.

0 - The entry of the detail code is optional. In this event you can change the major analysis code at entry point.

Base Asset Maintenance Defaults

- 1 - If addition.
- 3 - If addition or amendment.

Analysis Types Required

- 1 - You require the system to prompt you for this aspect of asset maintenance.
- 0 - You do not require an automatic prompt.

Analysis Types Maintenance Defaults

All the aspects of asset maintenance have the choice of the same range of maintenance default indicators.

- 0 - No prompt required.
- 1 - Prompt normally required for a new asset record.
- 2 - Prompt normally required for amendments only.
- 3 - Prompts required for additions and amendments.

Notepad Required

- 1 - You require the system to prompt you for this aspect of asset maintenance.
- 0 - You do not require an automatic prompt.

Advanced only.

Notepad Maintenance Defaults

All the aspects of asset maintenance have the choice of the same range of maintenance default indicators.

- 0 - No prompt required.
- 1 - Prompt normally required for a new asset record.
- 2 - Prompt normally required for amendments only.
- 3 - Prompts required for additions and amendments.

Notepad Default

If notepad is selected, enter here the default notepad type you would normally use.

Financial Details Required

- 1 - Prompting is required for financial details.

It is likely that these will be required

Financial Details Maintenance Defaults

All the aspects of asset maintenance have the choice of the same range of maintenance default indicators.

- 0 - No prompt required.
- 1 - Prompt normally required for a new asset record.
- 2 - Prompt normally required for amendments only.
- 3 - Prompts required for additions and amendments.

External Funding Required

1 - External funding details are normally required with asset maintenance. If used, note that financial details are also required

Advanced only.

External Funding Maintenance Defaults

All the aspects of asset maintenance have the choice of the same range of maintenance default indicators.

0 - No prompt required.

1 - Prompt normally required for a new asset record.

2 - Prompt normally required for amendments only.

3 - Prompts required for additions and amendments.

Lease Details Required

1 - Lease details are required. If used, note that financial details are also required.

Advanced only.

Lease Details Maintenance Defaults

All the aspects of asset maintenance have the choice of the same range of maintenance default indicators.

0 - No prompt required.

1 - Prompt normally required for a new asset record.

2 - Prompt normally required for amendments only.

3 - Prompts required for additions and amendments.

Book Maint. Defaults Details

0 - No prompt required.

2 - Prompt if amending the book.

This entry determines the prompt that you will automatically receive for each financial book when maintaining an asset.

The financial books are established to accommodate the varieties of valuation and depreciation rules and the consequent links with the General Ledger that you wish to use.

When adding or amending an asset, you can attach none, one or several (in the advanced version) books to each asset. Each book represents a different valuation or depreciation method that you may from time to time wish to employ.

This field is optional, but as it controls depreciation and the GL link it is usually required.

Book Maint. Defaults Revaluation

0 - No prompt required.

2 - Prompt if amending the revaluation details

This field is optional. If used, the 'Book Maint Defaults - Details' field must be 2.

Book Maint. Defaults Depreciation Journal

0 - No prompt required.

2 - Prompt if amending the depreciation journal.

This field is optional. If used, the 'Book Maint Defaults - Details' field must be 2.



Press **Enter** and then press **F8** to accept the data and update the company profile.

Company Profile Report



Select Fixed Assets (Company Profile Reports) to see the Company Profile Print screen.

```
FA605P          Company Profile Print          User FAF0          27/10/95
                                                    11:28:05

Company Code..... F8

1. Print Current Status
2. Print History of Movements

Select Option..... 1

For option 2, enter:-

    From Date.. █      Leave blank to obtain first movement
    To Date.... █      Leave blank to obtain last movement

F3=Exit
- 16-23  SF  MW  KS  IM  II  EDN400A  PED169S1
```

Fields:

Company Code

Enter the company whose details you wish to print.

Select Option

1 - Current status report.

2 - An audit report listing the history of changes and accesses to the company profile.

This includes information about:

- type of access e.g. *ADD, *CHANGE
- user identity
- terminal identity
- date and time

Date Range

For option 2, you must enter the date range (in the format DDMMYY) over which you require a print of movements. Leave the fields blank to obtain all details.

Book Profile



Select Book Profile and press **Enter** to display the first Book Profile Maintenance screen.

Book Profile Maintenance Screen 1

This screen enables you to select the book you wish to maintain.

Book.... <u>CST</u> (to add or change)		Based on Book...	in Company...		
Sel	Book Description	Cost Book	Include Dependents (0=No 1=Yes)	GL Link G/L	D/S
-	CST Cost Book	1	0	1	0
-	D01 Deprecn. Str.line Annual %	0	0	1	0
-	D02 Deprecn. Str/L Ann % - inc.dep	0	1	1	0
-	D03 Deprecn - Str.line Asset Life	0	0	1	0
-	D04 Deprecn.Str/L Ass Life-inc.dep	0	1	1	0
-	D05 Deprecn.Str/L Annual % by days	0	0	1	0
-	D06 Deprecn. Str/L Ann % on Revaln	0	0	0	0

F3=Exit

05-56  MW KS IM II EDN400A PED169S1

Fields:

Book

Enter the code of the book you wish to add or amend.



Note that to amend a book, you can select it from the list of existing codes.

Based On Book

If you are entering a new book, it may initially be based on an existing book of the same type (i.e. cost or depreciation) which can exist in another company.

In Company

Enter the company in which the based on book is found.

Sel

Enter 1 against a book you wish to amend.

Cost Book

1 - Cost book

0 - Depreciation book

Include Dependants

1 - The book includes dependent assets.

0 - The book does not include dependent assets.

GL Link

1- Linked to the GL

0 - Not linked to the GL

D/S Link

0 - Batches of transactions are posted in detail to the GL

1 - Batches of transactions are summarised by GL account.



Press **Enter** to display the second Book Profile
Maintenance screen.

Book Profile Maintenance Screen 2

A cost book is required only in order to link an asset acquisition to the General Ledger. If you are maintaining a cost book rather than a depreciation book, only a few of the fields are relevant. These fields are indicated in the field descriptions below.

FA006	F8 - Fixed Assets V3 Company - F8	USER FAF8	26/10/95 16:18:04
Book Profile Maintenance			
Book.....	CST		
Book description.....	Cost Book		
Cost Book.....	1 (0/1)		
Valuation Method.....?			
Valuation Index.....?			
Depreciate on net.....	0 (0/1)		
Funding Adjustments.....	0 (0/1)		
Include dependents.....	0 (0/1)		
Default Depreciation Method.?			
Additional Activity Codes....	0 (0/1)		
Default Depreciation Rate....			
GL Link active.....	1 0 = No Link, 1 = Link is Fiscal 2 = Link is Memo		
GL Details			
Debit Suspense Account...?	990		
Credit Suspense Account...?	991		
Detail/Summary Posting....	0 0 = Detail, 1 = Summary		
F3=Exit F4=Prompt F5=Refresh F12=Previous			
06-33	SA	MW KS	IM II EDN400A PED169S1

Fields:

Book Description

Enter a description of up to 30 characters.



Note: It may help to try to create a book description which includes as much information as possible about the characteristics of the book.

This field is relevant if you are maintaining a cost book.

Cost Book

1 - A cost book. This is the default.

0 - A depreciation book.



Note: This field cannot be further maintained after the initial update.

Valuation Method

Any method entered must have been set up as a reference code (BVAL).



Note: The system responds only to a code whose first digit is 1, 2 or 3.

Enter '100' for valuation at asset cost

Enter '200' for valuation at replacement value

Enter '300' for valuation at revaluation value (this defaults to asset cost when used in asset creation)

Valuation Index

If the valuation method 'revaluation' has been used, enter the valuation index that applies to this book. The index must have been previously created by use of the Valuation Index option.

Depreciate On Net

1 - Depreciation is to be based on book cost less residual value.

0 - Depreciation is to be based on book cost.

Funding Adjustments

1 - Depreciation is to be based on book cost less funding adjustment.



Note: Funding such as grants is often split into a capital component and a revenue component. The asset maintenance option allows for this distinction. It is therefore only the capital part of the funding that is taken into account in making the reduction in book value.

Include Dependants

1 - Book values of parent assets are to include dependants. If this is done, the dependants cannot then have this depreciation book record.

It may be of assistance if your book description can include some reference to this feature.

Default Depreciation Method

Enter an established depreciation method.

Additional Activity Codes

1 - 'Dérogatoire' depreciation methods will appear in the structured General Ledger accounts screen (activity codes 326 and 327). These are used in some European countries and relate to a reducing balance reverting to a straight line method of depreciation.

Default Depreciation Rate

Enter a default rate.

Both method and rate can be changed on the asset record.

GL Link Active

0 - No link

1 - Fiscal (financial accounts) link

2 - Memorandum accounts link

Where this field is 1 or 2 the 'Detail / Summary Postings' field must be set.

This field is relevant if you are maintaining a cost book.

Debit Suspense Account

Enter the GL account to be used for a debit transaction posted through this financial book which does not find a valid account from the asset record. Entries in these fields are validated against the GL chart of accounts in the correct company.

This field is relevant if you are maintaining a cost book.

Credit Suspense Account

Enter the GL account to be used for a credit transaction posted through this financial book which does not find a valid account from the asset record. Entries in these fields are validated against the GL chart of accounts in the correct company.

This field is relevant if you are maintaining a cost book.

Detail / Summary

0 - Detail posting

1 - Summary posting

This field is relevant if you are maintaining a cost book. This field will normally be 0 for a cost book.



Press **Enter** to update and return to select another book.

A book can be deleted provided that there are no assets which use the book.

Period Calendar



Select Period Calendar, and press **Enter** to see the first Financial Period Calendar screen.

Financial Period Calendar Screen 1

This is the calendar selection screen.

FA007	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95 16:29:29
Financial Period Calendar			
Enter Calendar for Year..... <u>96</u>		Based on Year.. <u>95</u> in Company.. <u> </u>	
Or Select from below.			
Sel Year		Sel Year	
- 95			
F3=Exit			
05-72		MW	KS IM II EDN400A PED169S1

Fields:

Calendar For Year

Enter either a new year to be set up, or one of the existing years from the list.

Based On Year

If a new calendar is to be created, the year can be based on a year already created.

In Company

If a new calendar is to be created, the year can be based on a year already created in another company. Enter that company here.

Sel(ect)

Enter 1 to select an existing calendar.



Press **Enter** to see the second Financial Period Calendar screen.

Financial Period Calendar Screen 2

The period descriptions are displayed in accordance with the way in which they have been set up in the 'PRDN' analysis code. The descriptions can only be altered by changing the PRDN codes.

FA007	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95 16:29:54
Financial Period Calendar			
Calendar for Year 96		Based on Company F8	Year 95
Start date.....		1/01/96	
Prd	End date	Description	Days
01	31/01/96	January	20
02	28/02/96	February	18
03	31/03/96	March	23
04	30/04/96	April	20
05	31/05/96	May	19
06	30/06/96	June	20
07	31/07/96	July	23
08	31/08/96	August	20
09	30/09/96		19
10	31/10/96		23
11	30/11/96		20
12	31/12/96		18
F3=Exit F5=Refresh F8=Update F12=Previous			
07-37	SF	MW KS IM II	EDN400A PED169S1

Fields:

Start Date

Enter the first day of the new year.



Note: If the year does not end on 31/12/YY, then the start date will be the beginning of a month other than January.

End Date

Enter the date of the last day of the period.

Days

Enter the number of accounting days in the period. If the depreciation methods using number of days in the period are not to be used, then the days field can be left blank or zero.



Complete the calendar which is shown as part-complete as in the screen on the previous page. Choose your own number of days for the remaining months. Press **Enter** and F8 to confirm changes.



Note: It is only possible to delete the calendars for the first and last years in the file.

System Reference Codes

Each reference code can have a number of three-character codes contained within it. Some reference codes, such as 'ACTY' (General Ledger account types), have system-defined codes which cannot be added to or deleted, although the description can be changed. The system-defined reference codes are:

ACTY	General Ledger account types (activity codes)
BVAL	Valuation method
DEPM	Depreciation methods
ITYP	Item types
NXTE	Next enquiry type
NXTM	Next maintenance type
PROV	Provisional depreciation type (advanced only). A - actual, P - provisional. The code A or P is printed on the depreciation report.
SKIP	Asset maintenance skips
SSTS	Session status codes 1 - Failed 2 - In preparation 3 - Completed
STYP	Session type 10 - Asset maintenance 14 - Elementary asset maintenance 15 - Asset journals 36 - Asset disposal 41 - Depreciation posting 48 - Lease posting 49 - Year end posting


User-defined reference codes are:

ANHR	Analysis hierarchy (alternative analysis code groupings)
ANTY	Analysis type (examples of common codes might be 'ATP' for asset type, 'LOC' (location)).
AUOM	Asset unit of measure
DUOM	Depreciation unit of measure
NPTY	Notepad type (advanced only). This is for text entries (e.g. 'ACQ' for acquisitions).
PRDN	Period descriptions
REAS	Reason codes
VALN	Valuation index

Some reference codes have a two tier structure in which each three character code listed within the reference code can have a user-defined six character analysis detail code.

The reference codes with this structure are:

ANHR	Analysis hierarchy
ANTY	Analysis type
VALN	Valuation index (3 character detail code)



The following is a list of activity codes (reference code 'ACTY'), showing the code (transaction number), description and definition, and divided into the different kinds of transaction.

Cost Book Transactions

001	Historical asset cost	Total asset cost to date at previous year end
002	Asset additions	Cost of asset additions and amendments for this year
003	Asset disposal year end transfer	Asset disposals transfer - year end transaction
005	External funding - capital	Asset value offset - capital
006	External funding - revenue	Unaffected asset value - revenue

009	Replenishment reserve	Replacement value less asset cost
Cost Book Transfers		
012	Asset value transfer out	Book value of asset at transfer out
013	Asset value transfer out year end roll	Asset transfer out - year end roll over transaction
022	Asset value transfer in	Book value of asset at transfer in
023	Asset value transfer in year end roll	Asset transfer in - year end roll over transaction

Leased Assets Transactions

030	Leased asset periodic payments	Net periodic lease payment
031	Lease interest previous year	Journal to post lease interest
032	Lease interest year to date	Journal to post lease interest
033	Lease capital previous year	Journal to post lease capital
034	Lease capital year to date	Journal to post lease capital
035	Lease interest payments	Lease posting for calculated interest payments
036	Lease capital payments	Lease posting for calculated capital payments
037	Lease total interest payable	Lease posting - total interest payable
038	Lease total capital payable	Lease posting - total capital payable
039	Lease interest year end transfer	Year end posting of interest to previous years interest
040	Lease capital year end transfer	Year end posting of capital from current year

Miscellaneous (Transactions that do not generate GL postings)

905	Residual value	The anticipated asset resale value at the end
-----	----------------	---

of the asset's life.

909 Replacement cost The expected cost of replacing the asset.

Job Management Transaction

090 Job Management postings

Asset Disposal Transactions

101	Asset disposal cost	Asset cost at time of disposal
105	Disposal external funding	Asset value offset (capital)
109	Disposal replenishment reserve	Replacement value less asset cost (see 009)
131	Disposal previous year lease interest	Value obtained from lease record
132	Disposal year to date lease interest	Value obtained from lease record
133	Disposal previous year lease capital	Value obtained from lease record
134	Disposal year to date lease capital	Value obtained from lease record
200	Asset disposal sales value	Asset sale value

Depreciation Book Transactions

300	Book value	Calculated book value
310	Revaluation reserve	Revaluation value less asset cost
321	Depreciation this year	Depreciation journal
322	Depreciation prior year	Depreciation journal
323	Depreciation year end transfer	Year end depreciation posting from current year to prior year
325	Period depreciation	Period depreciation calculation

Asset Disposal Transactions

400	Disposal book value	Obtained from book record
410	Disposal revaluation	Revaluation value less asset cost (see 310)

reserve

421	Depreciation disposal - current	Obtained from book record
422	Depreciation disposal - prior	Obtained from book record

Depreciation Book Transfers

511	Depreciation this year transfer out	Depreciation this year - transfer out
512	Depreciation prior years transfer out	Depreciation prior year - transfer out
521	Depreciation this year transfer in	Depreciation this year transfer out - year end roll over
522	Depreciation prior years transfer in	Depreciation prior year transfer out - year end roll over
523	Transferred in depreciation year end roll	Depreciation this year transfer in - year end roll over
524	Depreciation prior year transfer in year end	Depreciation prior year transfer in - year end roll over



Select the System Reference Codes option to see the first System Reference Codes Maintenance screen.

System Reference Codes Maintenance Screen 1

This screen lists the codes, often system-defined, which exist on the system.

Sel Ref.	Description	Det. Codes
- ACTY	General Ledger Account Types	0
- ANHR	Analysis Hierarchy	1
- ANTY	Analysis Codes	1
- AUOM	Asset Unit of Measure	0
- BVAL	Valuation Method	0
- DEPM	Depreciation Method	0
- DUOM	Depreciation UOM	0
- ITYP	Item Types	0
- NPTY	Notepad Type	0
- NXTE	Next Enquiry Type	0
- NXTM	Next Maintenance Type	0

Fields:

Enter Reference

Enter an existing reference code if you wish to:

See all the related sub-codes for the code

Amend a sub-code description

Add a new sub-code. In this case you must enter 1 in the 'Maintenance Type Selected' field, then press **Enter**.

Maintenance Type Selected

1 - This, together with a reference code in the 'Enter Reference' field, displays all the related sub-codes for the code.

2 - This, together with a reference code in the 'Enter Reference' field, displays the detailed header information for that reference code.

3 - This, together with a reference code in the 'Enter Reference' field and a sub-code in the 'Code' field, displays all sub-codes for the selected sub-code. This is available only for those sub-codes which are allowed sub-codes of their own, i.e. those with 1 in the 'Det Codes' column.

Code

This can only be used in conjunction with the 'Enter Reference' field and the 'Maintenance Type Selected' fields. The system displays the sub-codes for the selected sub-code entered in this field. This is available only for those sub-codes

which are allowed sub-codes of their own, i.e. those with 1 in the 'Det Codes' column.

Sel

1 - See all the related sub-codes for the selected reference code, amend a sub-code description, or add a new sub-code.

2 - See the header details for the selected reference code.

This field is not used in conjunction with the fields at the top of the screen.



Press **Enter**. If you wanted to see the reference codes header details (i.e. you entered 2 in the 'Sel' field), the second System Reference Codes Maintenance screen is displayed.

System Reference Codes Maintenance Screen 2

If you wanted to see the reference codes header details (i.e. you entered 2 in the 'Sel' field on the first System Reference Codes Maintenance screen), the second System Reference Codes Maintenance screen is displayed.

FA008	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95 16:20:20
System Reference Codes Maintenance			
Reference.....	ACTY		
Description.....	<u>General Ledger Account Types</u>		
Display skeleton company...	1	0/1	
Usage control.....	0	0/1/2	
Code length.....	3	Maximum 3	
Code Description Length....	30	Maximum 30	
Detail Code Length.....	0	Maximum 6	
Detail Description Length..	0	Maximum 30	
Detail Entries Allowed.....	0	0/1	
Hierarchy Entries Allowed..	0	0/1	
F3=Exit F5=Refresh F12=Previous **			
07-30	SP	MW	KS IM II EDN400A PED169S1

Fields:

Description

Amend as necessary.



Tip: The code and description lengths are defined by the system and can be viewed collectively in the summary report.

Display Skeleton Company

1 - You wish codes held on the skeleton company (##) to be displayed along with user defined codes.

0 - You wish to use only user-defined codes.

Usage Control

This field determines what is displayed when you prompt on a field.

0 - All records within the reference code are displayed.

1 - The analysis codes within a reference code display only if associated valuation indices have been created.

2 - Analysis codes are defined by the system and cannot be maintained by the user.



Press **Enter**.



If, from the first screen, you wanted to see the sub-codes for a selected reference code, the third System Reference Codes Maintenance screen is displayed.

System Reference Codes Maintenance Screen 3

If, from the first screen, you wanted to see the sub-codes for a selected reference code, the third System Reference Codes Maintenance screen is displayed.

FA008		F8 - Fixed Assets V3 Company - F8		User FAF8	26/10/95 16:20:43
Reference Codes Maintenance					
Reference...	ACTY	Description...	General Ledger	Account	Types
Line	Code	Description	Appl. def'd	Comp. Code	
1	001	Historical Asset Cost	1	##	
2	002	Asset Additions	1	##	
3	003	Asset Disposal Y/E Transfer	1	##	
4	005	External Funding - Capital	1	##	
5	006	External Funding - Revenue	1	##	
6	009	Replenishment Reserve	1	##	
7	030	Leased Asset Periodic Payments	1	##	
8	031	Lease Interest Previous Year	1	##	
9	032	Lease Interest Year to Date	1	##	+
Line... 0 (to change)					
Code...		OR Enter code to start list... for company...			
F3=Exit F5=Refresh F12=Previous ***					
20-10 SF MW KS IM II EDN400A PED169S1					

Fields:

Line

Enter the line number of the code whose description you wish to amend, and press Enter.

Code

Enter the new sub-code you wish to set up, and press Enter.

Detail Code Maint

- 1 - Add new detail codes to the sub-code you have selected.
- 0 - Display the description of the analysis code for amendment.

Enter Code To Start List

Use this field to reposition the list to show the codes you want.

For Company

Use this field to reposition the list to show the codes you want.



Press **Enter** to update.

If you entered 1 in the 'Detail Code Maint' field, then when you press **Enter** you will see the fourth System Reference Codes Maintenance screen.

System Reference Codes Maintenance

Screen 4

This screen lists the detail analysis codes.

FA008

F8 - Fixed Assets V3 Company - F8

User FAF8

26/10/95
16:23:45

Reference Detail Codes Maintenance

Ref.. ANTY

Description.. Analysis Codes

Code. ATP

Description.. Asset Type

Line	Detail	Description	Comp.
1	BLDG	Buildings	F8
2	COMP	Computer Hardware	F8
3	LAND	Land	F8
4	OFFC	Office Equipment	F8
5	VEH1	Company Cars	F8
6	VEH2	Commercial Vehicles	F8

Line... 00 (to change)

Detail. _____

OR Enter detail to start list.. _____

for company.. _____

F3=Exit

F5=Refresh

F12=Previous

19-10

SF

MW

KS

IM

II

EDN400A

PED169S1

Fields:

Line

Enter the line number of the code whose description you wish to amend.

Detail

Enter the code whose description you wish to see.

Enter Detail To Start List

Use this field to reposition the list to show the codes you want.

For Company

Use this field to reposition the list to show the codes you want.



You can also display detail codes by entering maintenance type 3, but this is available only for those reference codes which hold detail codes - i.e. 'ANTY', 'VALN' and 'ANHR'.

Hierarchy

The codes to be used in any hierarchy structure must have been set up in advance using the appropriate system reference codes.

The understanding of hierarchy types depends on:

- A clear understanding of the basic structure of analysis types (analysis codes found at the first level of detail within system reference code 'ANTY') and their second level of detail, the analysis detail codes.
- A clear vision of how such detail analysis codes can be organised into alternative groupings.

An example might be to group land and building assets into an estates division, or to have all vehicles and mobile equipment grouped into a transport division.



Note: Fixed Assets hierarchies are very similar to General Ledger hierarchies, which are also alternative groupings of accounts, set up to analyse data in different ways.

Hierarchy Maintenance Screen 1

 Select Hierarchy and press **Enter** to see the first Hierarchy Maintenance screen.

FA009	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95 16:27:30
Hierarchy Maintenance			
Hierarchy Type	?	?	
Hierarchy Code	?	?	
Sub-Type	?	?	
Analysis or Hierarchy ..	-	(0=Analysis 1=Hierarchy)	
Based on Details:			
Hierarchy Type	?	?	
Hierarchy Code	?	?	
Company	-	-	
F3=Exit F4=Prompt			
07-28	SE	MW	KS IM II EDN400A PED169S1

Fields:

Hierarchy Type

Enter the hierarchy analysis code. These codes are set up under the system reference code 'ANHR'.

Hierarchy Code

Enter the analysis hierarchy detail code that is related to the hierarchy type that you have entered. These codes are set up as sub-codes of the analysis codes under the system reference code 'ANHR'.

Sub-Type

If you are creating a new hierarchy, enter a sub-type here.

Its value will depend on the status of the next field:

Analysis Or Hierarchy

If you are creating a new hierarchy:

0 - The sub-type code is derived from an analysis code set up under the system reference code 'ANTY'.

1 - You wish to build a hierarchy derived from other hierarchy groupings. (Set up under the system reference code 'ANHR'.)

Based On Details

When setting up a new hierarchy it can be based on an existing structure, which may have been created in this or another company.



Press **Enter** to see the second Hierarchy Maintenance screen.

Hierarchy Maintenance Screen 2

The screen shows the detail analysis codes originally established under the analysis type. These can also be included in an alternative grouping represented by the hierarchy type region with its hierarchy codes NW, SE and MIDlands.

FA009	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95
			16:29:00
Hierarchy Maintenance			
Hierarchy Type	REG	Region	
Hierarchy Code	MID	Midlands	
Sub-Type	LOC	Location	
Analysis or Hierarchy ..	0	(0=Analysis 1=Hierarchy)	
Codes	Description		
BHAM	Birmingham		
COVN	Coventry		
Add (0) or Remove (1) ..		0	Code .? MILT
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous			
20-27 S2 MW KS IM II EDN400A PED169S1			

Fields:

Add Or Remove

- 0 - add a code to the list.
- 1 - delete an existing code.

Code

Enter the code to be added or removed.

 Press **Enter**, then **F8** to update.

Valuation Index

If you want to revalue your assets based on an external index (for example, current cost accounting), then the index must be held within Fixed Assets.

Revaluation is not available if you are operating in base mode.



Select the Valuation Index option to display the following selection fields:

Fields:

Index

Enter a new or existing index.

Based On Index

If you wish to base a new index on an existing one, enter that existing index here.

In Company

Enter the company in which the system will find the base-on index.



*Note: The **F4** prompt will display only those indexes which hold values - those with descriptions but no values are not displayed.*



Press **Enter** to see the Valuation Index Maintenance screen.

Valuation Index Maintenance Screen

FA011 F0 - Fixed Assets V3 Company - F0 User FAF0 30/10/96
16:46:11

Valuation Index Maintenance

Index.. 001 Desc... Test Index
Default is Fixed/Extrapolate (0/1)... 0

Period	Index	Fix/Ex	Period	Index	Fix/Ex	Period	Index	Fix/Ex
0001	1.0000	0						
0002	1.5000	0						

Period... Index... Fix/Ex... Remove Period... 0 (0/1)

F3=Exit F5=Refresh F8=Update F12=Previous

21-12 SF MW KS IM II EDN400A PET179S1

Fields:

Desc

Enter or amend the index description.

Default Is Fixed / Extrapolate

0 - The index is to be fixed for intermediate periods.

1 - The index is to be extrapolated.

Example of extrapolation:

This extrapolated index - P1 111 P2 112 P7 122...

...is the same as P1 111 P2 112 P3 114 P4 116 P5 118 P6 120 P7 122.

Period

Enter the start period for the index value.

Index

Enter the index value, of up to 5 integers and 4 decimals.

Fix / Ex

0 - The index for intermediate periods between this period and the next is fixed at the previous index.

1 - The index for intermediate periods between this period and the next is extrapolated between this and the next index.

This field need be entered only if the value is to be different to that entered in the default field at the top of the screen.

Remove Period

0 - Do not remove period from index.

1 - Remove period from index.



The calculation is as follows:

$$\text{Previous index} + \frac{(\text{Next index} - \text{Prior index})}{\text{Next period} - \text{Prior period}} * (\text{Revaluation period} - \text{Prior period})$$

Functions:

F8

Update the index.

F11

Delete the index

Roll

Roll to see more details.

Structured GL Accounts

The Structured General Ledger Accounts option allows account numbers to be generated for each asset, differently for each asset if necessary, depending on which financial book is attached to the asset. The depreciation transaction that is created in this way is known as a financial transaction and is one of the General Ledger account type codes grouped together in the reference codes under 'ACTY'.

All possible types of posting to the General Ledger are included in the transaction list. In practice only a few of the financial transactions will be used by companies with relatively simple requirements. However transactions are available for companies using the advanced facilities of leasing, revaluation or external funding.

Notes on structured General Ledger accounts:

- Each book can be linked independently to the General Ledger, either to financial or to memorandum accounts.
- This procedure cannot be used for the skeleton company ##.
- When a book is linked to financial accounts in the General Ledger, both debit and credit accounts must be specified. If a book is linked to memorandum accounts, only one or the other needs to be specified.
- If accounts are not specified against an account type (financial transaction), then no General Ledger transaction will be generated.
- Book value (300) account type is unlikely to be used except if linked to a memorandum account.

If a transaction cannot be successfully corrected, it can be posted, as appropriate to the debit or credit suspense account, defined on the book profile.



Select Structured GL Accounts and **Enter** to see the first General Ledger Accounts screen.

General Ledger Accounts Screen 1

The first General Ledger Accounts screen shows the following selection fields:

Fields:

Book

Enter a book. The book profile must have already been set up and the book must be linked to the General Ledger.

Based On Book

The General Ledger links to be set up in the current book in one company can be based on structured accounts already set up in another book in another company.

If you need to copy these account links, enter the book code here.

In Company

The General Ledger links to be set up in the current book in one company can be based on structured accounts already set up in another book in another company.

If you need to copy these account links, enter the based-on company here.



Press **Enter**. You will now see the second General Ledger Accounts screen, where any existing transactions for your selected book are displayed.

General Ledger Accounts Screen 2

The system displays initially the first twelve financial transaction codes associated with the cost book. Roll up to display the remaining transactions.

The 'ACTY' analysis code that represents each transaction is listed alongside.

```

FA012          F8 - Fixed Assets V3 Company - F8      User FAF8      26/10/95
                                                16:38:53

General Ledger Accounts

Book.. D01 Deprecn. Str.line Annual %

    Acty
    - 300 Book Value
    - 310 Revaluation Reserve
    - 321 Depreciation this year
    - 322 Depreciation prior year
    - 323 Depreciation Year End Transfer
    - 325 Period Depreciation
    - 400 Disposal Book Value
    - 410 Disposal Revaluation Reserve
    - 421 Depreciation disposal - curr.
    - 422 Depreciation disposal - prior

1=Select

F3=Exit  F5=Refresh  F12=Previous

12-03  S2  MW  KS  IM  II  EDN400A  PED169S1
  
```

Fields:

Unnamed (Select)

Enter 1 against the financial transaction code for which you wish to enter a GL link.



Press **Enter**. Enter the ledger required on the next screen, then press **Enter** again to see the third General Ledger Accounts screen.

General Ledger Accounts Screen 3

This screen will display all the levels which exist for the ledger you have selected. This will not necessarily be all levels possible on the system. The system checks that:

- This is not a control account
- The accounts are financial accounts unless the book is a memorandum book.

FA012	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95
General Ledger Accounts			16:40:10
Book.. D01 Deprecn. Str.line Annual %			
<-----Debit Account----->		<-----Credit Account----->	
Acty	325 Period Depreciation	Ldg.?	
Ldg.?		Ldg.?	
Level 1.?		Level 1.?	
Level 2.?		Level 2.?	
Level 3.?		Level 3.?	
Level 4.?		Level 4.?	
Level 5.?		Level 5.?	
Level 6.?		Level 6.?	
Level 7.?		Level 7.?	
Level 8.?		Level 8.?	
Level 9.?		Level 9.?	
F3=Exit F4=Prompt F5=Refresh F11=Delete F12=Previous			
18-13	Sf	MW	KS IM II EDN400A PED169S1

Fields:

Debit Account Ldg

Enter the profit and loss sub-ledger which holds the period depreciation accounts.

Levels 1-9

Enter the codes for the different ledger levels set up in the sub-ledger entered above. Codes must be entered within quotation marks, for example "LOC", or "ATP".

Credit Account Ldg

Enter the balance sheet sub-ledger which holds the detailed depreciation this year accounts.

Levels 1-9

Enter the codes for the different ledger levels set up in the sub-ledger entered above. Codes must be entered within quotation marks, for example "LOC", or "ATP".



Press **Enter** to confirm entries and to return to the financial transaction list.

Activity codes (reference code 'ACTY'):

001	Historical asset cost
002	Asset additions
003	Asset disposal year end transfer
005	External funding - capital
006	External funding - revenue
009	Replenishment reserve
012	Asset value transfer out
013	Asset value transfer out year end roll
022	Asset value transfer in
023	Asset value transfer in year end roll
030	Leased asset periodic payments
031	Lease interest previous year
032	Lease interest year to date
033	Lease capital previous year
034	Lease capital year to date
035	Lease interest payments
036	Lease capital payments
037	Lease total interest payable
038	Lease total capital payable
039	Lease interest year end transfer
040	Lease capital year end transfer
090	Job Management postings
101	Asset disposal cost
105	Disposal external funding
109	Disposal replenishment reserve
131	Disposal previous year lease interest
132	Disposal year to date lease interest
133	Disposal previous year lease capital
134	Disposal year to date lease capital
200	Asset disposal sales value
300	Book value
310	Revaluation reserve
321	Depreciation this year
322	Depreciation prior year
323	Depreciation year end transfer

325	Period depreciation
326	Derogatoire depreciation charge
327	Derogatoire depreciation rels.
400	Disposal book value
410	Disposal revaluation reserve
421	Depreciation disposal - current
422	Depreciation disposal - prior
511	Depreciation this year transfer out
512	Depreciation prior years transfer out
513	Depreciation this year transfer out year end
514	Depreciation prior year transfer out year end
521	Depreciation this year transfer in
522	Depreciation prior years transfer in
523	Transferred in depreciation year end roll
524	Depreciation prior year transfer in year end

Reference Codes Enquiry



Select Reference Codes (Enquiries) to see a screen displaying all available codes for enquiry. Enter 1 against the code whose sub-codes you wish to see.

The structure of this enquiry mirrors that of the corresponding maintenance option.

Book Profile and GL Accounts Report



Select Book Profile and GL Accounts (Reports) to display the selection screen.

Fields:

GL Accounts Required

0 - listing of General Ledger accounts is not required.

1 - listing of GL accounts is required.

Instruction Set To Be Used

The default Report Manager instruction set (may be named BOOKPROFIL) is shown.



An example of the report, including the GL accounts that have been set up in each book.



Note that the General Ledger codes are shown together with the financial transactions to which they have been attached. If the report request omitted the GL codes, the book profile line alone would be printed.

Period Calendar Report



Select the Period Calendar option to display the selection screen.

Fields:

Select Year From

Enter the first year to print. Leave blank to start from first year.

Select Year To

Enter the last year to print

Leave both fields blank if all years are to be printed.

Reference Codes Report



Select Reference Codes (Reports) to see the System Reference File Listing screen.

FA608P	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:29:58
System Reference File Listing			
Select from the options :			
System References.....	From. ____ To... ____	Leave blank to obtain from first Leave blank to obtain to last	
List Reference Codes.....	0	{0/1}	
	From. ____ To... ____	Leave blank to obtain from first Leave blank to obtain to last	
List Detail Codes.....	0	{0/1}	
	From. ____ to... ____		
Print default company codes....	1	{0/1}	
F3=Exit			
07-36	SP	MK	KS IM II EDN400A PED169S1

Fields:

System References From / To

Enter a range of system reference codes.

Leave blank to obtain all codes.

List Reference Codes

0 - List the system reference codes (4 character codes such as ANTY, DEPM etc.).

1 - List the analysis type codes, which lie within each of the system reference codes:

E.g. ANTY contains ATP, LOC, COS.

From / To

Enter a range of analysis type codes (3 characters) or leave blank to obtain all codes. This level of printing of analysis type codes works in conjunction with the settings above to limit the number of codes and reference codes printed.

List Detail Codes

0 - List just the analysis type codes.

1 - List the analysis detail codes (such as VEH1, BHAM etc.) within their analysis type codes within the appropriate systems reference codes.

From / To

Enter a range of analysis detail codes (up to 6 characters) or leave blank to obtain all codes, within the limits set by the indicators above.

Print Default Company Codes

0 - Codes from the skeleton company '##' will not be printed.

1 - Codes from the skeleton company '##' will be printed. These can include both system-defined and user-defined codes.



The following varieties of report can be produced:

- A listing of all system reference codes.
- A listing of some system reference codes.
- A listing of all analysis type codes within all system reference codes.
- A listing of all analysis type codes within a range of system reference codes.
- A listing of a range of analysis type codes within all or some system reference codes.
- A listing of all analysis detail codes within all analysis type codes within all system reference codes.
- A listing of a range of analysis detail codes within some analysis type codes within some system reference codes.



Tip: The above reports can be doubled in number if the distinction is made between listings containing just your company codes and listings containing yours and the skeleton or default company codes.

Hierarchy Report



Select the Hierarchy option to see the Hierarchy listing screen.

FA609P F8 - Fixed Assets V3 Company - F8 User FAF8 27/10/95
11:30:22

Hierarchy Listing

Select :

Hierarchy Types.....From. ☐ _____

To... _____

Leave blank to obtain from first

Leave blank to obtain to last

Hierarchy Codes.....From. _____

To... _____

Leave blank to obtain from first

Leave blank to obtain to last

F3=Exit

07-39 **Sf** **Mk** KS IM II EDN400A PED169S1

Fields:

Hierarchy Types From / To

Enter the range of hierarchy types you require or leave blank to obtain all types.

Hierarchy Codes From / To

Enter the range of hierarchy codes you require or leave blank to obtain all codes.



Press **Enter** to submit a job to produce the report.

System Reference Audit History Report

This report prints a list of changes made to either a book profile or a General Ledger link profile.



Select System Reference Audit History to see the System Reference Audit History Reports screen.

```
FA700P          F8 - Fixed Assets V3 Company - F8          User FAF8          27/10/95
                                                         11:31:59

System Reference Audit History Reports

1. Book Profile
2. General Ledger Link

Select Option..... 1

List change fields only.... 1 (0=No/1=Yes)

F3=Exit

15-30  SF  MK  KS  IM  II  EDN400A  PED169S1
```

Fields:

Select Option

- 1 - Book profile audit report is requested.
- 2 - The General Ledger link audit report is required.

List Change Fields Only

- 0 - All fields are required.
- 1 - Only fields that have changed are required.



Whichever option is taken in either of the above fields, when you press **Enter** the Book Profile Audit Trail Report screen is displayed.

Book Profile Audit Trail Report Screen

This screen is displayed when you have entered your report options on the first screen.

FA701P	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:32:21
Book Profile Audit Trail Report			
1. Print all unprinted records 2. Print all records for a Book 3. Print all records from a date			
Select Option..... 2			
For option 2 enter Book or Book and From date For option 3 enter From date or Book and From date			
Book.....? 001			
From Date..... 0/00/00			
F3=Exit F4=Prompt			
10-23   KS IM II EDN400A PED169S1			

Fields:

Select Option

- 1 - All unprinted records are to be selected.
- 2 - All records for a given Book are to be selected.
- 3 - All records from a given date are to be selected.

Book

If option 2 was entered above, you must enter a book code.

If option 3 was entered, a book code is optional.

From Date

If option 2 was entered above, a date can be entered.

If option 3 was entered, you must enter a date.

The field can be blank.



This report produces a page per financial transaction / General Ledger code line.