

-
-
-
-
-

Chapter 8

Utilities



Financial Manager Utilities

Five utility options are provided by Financial Manager to enable you to copy reports, output formats and data field definitions in the data dictionary to a different company.

The three options grouped under the heading 'Ad Hoc Copy Utilities' enable you to:

- Copy all or a selection of data dictionary fields from a selected company to the current company.
- Copy all or a selection of output formats from a selected company to the current company.
- Copy all or a selection of reports from a selected company to the current company.

The two 'Company Copy Utilities' options enable you to:

- Copy data from any existing company, including template companies, to a new company. You can copy any combination of data dictionary, output formats and reports, but you cannot select. All the data within a particular type must be copied.
- Copy data from any existing company to any other, including template companies. You can copy any combination of data dictionary, output formats and reports, but you cannot select. All the data within a particular type must be copied.

Data Dictionary Copy

This procedure allows you to selected user-defined fields from another company into the current company.



Select the option Data Dictionary Copy and the following fields are displayed:

Copy From Company

Enter the company code of the company from which you want to copy details. It must be a valid company set up on the General Ledger.

All Dictionary Fields?

Leave as 0 to display a list of all user-defined fields in the source company's data dictionary. You can then make a selection from this list and the selected fields will be copied across.

Enter a 1 to copy all the user-defined fields.

The To Company field is displayed but cannot be accessed. It shows the company code of the current company to which you want to copy details.



Press **Enter** to accept.

Whether selected fields or all fields are to be copied, all fields which do not already exist in this company are copied across.

Any fields which are duplicated are displayed in sequence. For each duplicated field press either **F8** to overwrite the original field with the copied field, or **Enter** to retain the original field.

Output Format Copy

This procedure allows you to copy selected output formats across from another company into this company.



Select the option to copy Output Formats and enter the company from which you want to copy output formats. It must be a valid company set up on the General Ledger.

The To Company field is display only and shows the current company to which you are performing the copy.



Press **Enter** to accept the details and to display the next screen.

RW110	E1 - Demonstration Company	USER ED3	6/01/94 14:39:28
Copy Output Formats		From:	E2 - Demonstration Company 2
1	Format Name	Description	
—	HFORMAT	Header demonstration format	
—	DFORMAT	Detail demonstration format	
—	TFORMAT	Total demonstration format	
1=Select F3=Exit F12=Previous			



A list of all the formats in the source company is displayed on the screen. Enter a 1 against all those formats you want to copy across and press **Enter** to confirm your selection.



Note: If the format already exists in the current company it cannot be selected.



The selected formats are displayed on the screen and you can confirm your choice again by pressing **F8**. The copy will then take place.



Note: If the new format contains fields which are not defined in the data dictionary and error message is displayed. The format will be copied but without the missing fields. You should correct the data dictionary and/or the format before using the format in a report specification.

Report Copy

This procedure allows you to copy across report specifications from another company into the current company.

-  Select the option Report Copy and enter the company from which you want to copy across report specifications. It must be a valid company set up on the General Ledger.

The Copy to Company field is display only and shows the current company to which you are performing the copy.

-  Press **Enter** to accept the details and the next screen is displayed.

RW110	E1 - Demonstration Company	USER ED3	6/01/94 14:39:28
Copy Reports	From: E2 - Demonstration Company 2		
1	Report Name	Description	
—	JANREP	January Demonstration Report	
—	FEBREP	February Demonstration Report	
—	MARREP	March Demonstration Report	
1=Select F3=Exit F12=Previous			

All the report specifications in the source company are displayed on the screen. Enter a 1 against the specifications you want to copy across and press **Enter** to confirm your selection.

-  *Note: If the specification already exists in the current company it cannot be copied across.*

-  Press **F8** to confirm the copy and the copy is then processed.

-  *Note: If the new specification contains formats which either contain errors or do not exist at all, an error message is displayed. The specification will still have to be copied. Before this report can be used you must correct the data dictionary, format and/or specification.*

Create

This procedure enables you to create a new company by copying the contents of an existing company, which may be a template company. Only the static data in a company can be copied; the copied data will not include items or balances, for example.



Select the *Create* option and enter the company which is to provide the data for the 'To' company. This may be a template company. Then enter the company to which data is to be copied, and press **Enter**.

RM881	E1 - Demonstration Company	User ED3	11/10/94 14:43:11
-------	----------------------------	----------	----------------------

Maintain Company

From company . : E1 To company . : E2

Reports	:	—	(Enter '1' to select)
Output formats.	:	—	
Data dictionary	:	—	

F3=Exit	F8=Confirm	F12=Previous
---------	------------	--------------

Fields:

Reports

Enter 1 if you want all the reports currently existing for the 'From' company to be copied to the 'To' company.

Output Formats

Enter 1 if you want all the output formats currently existing for the 'From' company to be copied to the 'To' company.

Data Dictionary

Enter 1 if you wish to copy the data dictionary from the 'From' company to the 'To' company.



When you have entered the data you want to copy, press **F8** to update.

Maintain

This procedure enables you to copy data between existing companies. Template companies may be used.



Select the Maintain option and enter the company which is to provide the data for the 'To' company. This may be a template company. Then enter the company to which data is to be copied, and press **Enter**.

```
RW881                      E1 - Demonstration Company  User ED3      11/10/94
                               14:48:35

Maintain Company

From company . : E1      To company . : E2

Reports . . . . . : _      (Enter '1' to select)
Output formats. . . . . : _
Data dictionary . . . . . : _

F3=Exit      F8=Confirm      F12=Previous
```

Fields:

Reports

Enter 1 if you want all the reports currently existing for the 'From' company to be copied to the 'To' company.

Output Formats

Enter 1 if you want all the output formats currently existing for the 'From' company to be copied to the 'To' company.

Data Dictionary

Enter 1 if you wish to copy the data dictionary from the 'From' company to the 'To' company.



When you have entered the data you want to copy, press **F8** to update.