

-
-
-
-
-

Chapter 5

Budgets Maintenance



Introduction To GL Budgets Maintenance

There are many different ways of entering budgets and forecasts to suit a wide diversity of business requirements. Review these various methods to see which best suits your organisation. It is unlikely that you will use all the available options, since just one or two will probably be sufficient to meet your requirements.



To set up or maintain budget and forecast details, select the GL Budget Maintenance or Budget Processing options.

Budgets Processing Options

The purpose of the budgeting options is to enable you to:

- Specify period budgets for General Ledger accounts.
- Roll budget values up from a lower-level, detailed view to a higher-level, less detailed view.
- Use rules to create new budgets based on existing budgets and previous period balances.
- Download data from a PC and create budgets from it, via Viewfinder.
- Produce reports of the budgeting figures.

Budget Rule Types

Generation

This method copies a budget, actuals, or a combination of the two - the source - to a range of accounts defined as the targets. You can specify a factor, so that each source value increases or decreases by a percentage before it is received into the target budget.

For example, you can create a set of budgets for pension contributions to be 10% of the salary budgets.

Apportionment

This method takes a source budget for a single account, and applies factors to it, apportioning it across target accounts. You might choose, for example, to apportion the total electricity budget across departments depending on the departmental head count.

Spreading

This method takes the budgets already existing over the target accounts, and spreads them across the year according to defined factors.

For example, this facility could be used to reflect seasonal business trends.

Basic Concepts

The source account and source budget provide the initial values used. These values are operated on by a factor or a ratio. A factor will multiply or divide each value before it goes into the target account. A ratio will divide the total source value into certain proportions. The result is put into the target accounts.

Familiarity with the concept of user-defined views (if your company uses them) and the structure of your company's chart of accounts is assumed in all budgeting sections. This familiarity is essential both in setting up budgets and in interpreting results.



Note: For the use of user-defined views, refer to the section User-Defined Links Maintenance.

Each of the three budget rules involves two stages:

- Firstly, define the rule - this means specifying the source, the targets and any calculations to be done.
- Secondly, once the rule exists, go to the relevant Rule Processing option, select the rule, and submit a job to produce the budgets.

Points To Remember

Using source account values in calculation does not clear the values down in the source account, so it is possible to have the same value appearing in both source and target budgets.

All budgeting operations work within a specified ledger and view. You cannot create a budget from source in another ledger, nor can cross-ledger views be used in

creating budgets. (You can, however, roll up to a cross-ledger view.) Budgets can be defined for the same ledger code in different companies.

Throughout these sections, the references to budget will apply equally to forecast. Processing is the same for both.

Rolling Up

Using the user-defined links option, you can link detailed, low-level views to higher level views. Any update to budgets in the low-level view will automatically update the budgets higher up. This is called rolling up.

For example, assume that budgets are entered for accounts in a view with levels 1, 2, 3, and 5. You set up links between this view, one using levels 1, 2, and 3, and another using levels 3 and 2 only. Budgets generated automatically for the lower-level view will update budgets in the other two.

The updating of views at a higher level with views of a lower level is not mandatory. Updating will only take place if links have been set up for these views.

Understanding The Budgeting Diagrams

Several diagrams are used in the budgeting sections to clarify the workings of the budgeting module. These diagrams use the following standards:

Accounts and budgets are represented by a row of six joined boxes, each box representing one period. Six are used rather than twelve (which would be a more usual number of periods for a company) in order to simplify the diagrams.

Each set of boxes is labelled. Account numbers are ACn, budget codes BUDn, where n is a number.

Elements of the label in bold type are specified when defining the rule. Elements not in bold type are specified when running the job.

Spread Profiles Maintenance

1...
2...

1/GLG

Set up profiles to enable you to spread annual budget and forecast values over accounting periods. Set pre-determined ratios for the spread.



Select the Budget option to maintain Spread Profiles. This displays any profiles that have already been set up. Amend a profile by entering its code and pressing **Enter**.



Add a new profile by entering a three-character code and pressing **Enter**. The Maintain Spread Profiles screen is shown.

GL075		Y6 - Education Company - Y6		USER FFV6		31/07/95	
						14:07:09	
Maintain Spread Profiles.							
Profile Code	NEW	Period	Value				
		01	_____				
		02	_____				
		03	_____				
		04	_____				
		05	_____				
		06	_____				
		07	_____				
		08	_____				
		09	_____				
		10	_____				
		11	_____				
		12	_____				
Profile Description		_____		Total		_____	
F12=Previous							
06-40		SF	MM	KS	IM	II	KENB20A PCET02S1

To delete an existing code, enter the code number, press **Enter** and then press **F11=Delete** to delete.

Fields:

Period Value

The spread proportion value for each period. The sum of all period values must equal the total. A period need not have a value. Decimal places are not allowed.

Profile Description

You must enter a description of up to twenty characters.

Total

This must be the sum of all the period values.



Press **Enter** to check your entry and return to the menu with **F3=Exit** or **F12=Previous**.

Budget Codes Maintenance



2/GLG

Use this procedure to set up codes for budgets and forecasts.

Maintain budget values for any account. Budget codes distinguish the values.

- A budget or forecast is identified by its code and type. You may use the same code for a budget and a forecast.
- You can define budgets and forecasts for quantities as well as values.
- You can enter budgets in prime currency where the company is a multi-currency company.



Select the option to maintain Budget Codes. The Maintain Budget And Forecast Codes screen displays.

Maintain Budget And Forecast Codes Screen

At this screen select a budget for amendment or deletion, or, add a new budget code.



Note: Two codes, budget or forecast, are available as defaults on enquiry screens. The defaults are pre-defined on the company profile, but can be overridden at enquiry time. For example, change the default on a long-term basis (6 months original budget, then 6 months revised budget). Change this on the company profile.



Select the Budget Codes maintenance option. The first Maintain Budget And Forecast Codes screen displays.

GL470 Y6 - Education Company - Y6 USER FFY6 31/07/95 14:04:33			
Maintain Budget & Forecast Codes			
Opt	Budget Code	Budget Type	Description
-	B01	1	Default budget
-	F01	0	Default forecast
Position to . ? ____ (0=Forecast, 1=Budget, 2=Quantity forecast, 3=Quantity budget, 4=Currency forecast, 5=Currency budget)			
1=Amend, 4=Delete			
F3=Exit F4=Prompt F10=Add a budget or forecast			
20-18 SF MK KS IM II KENB20A PCET02S1			

Fields:

Opt

- 1 - Select a budget or forecast for amending.
- 4 - Delete a budget or forecast.

Position To (Unnamed First Field)

Enter the budget code from which you wish the list to start.

Position To (Unnamed Second Field)

Enter the budget type from which you wish the list to start. Valid types are:

- 0 - Base forecast - a forecast to be held in the base currency of the company.
- 1 - Base budget - a budget to be held in the base currency of the company.

2 - Quantity forecast - a forecast of quantities.

3 - Quantity budget - a budget of quantities.

4 - Currency forecast - a forecast to be entered in a prime currency, but to be converted and stored with prime and base values. This type is not valid if you are working in a single currency General Ledger.

5 - Currency budget - a budget to be entered in a prime currency, but to be converted and stored with prime and base values. This type is not valid if you are working in a single currency General Ledger.

Functions:

F10

Add a new code.



When you add or amend a budget code the Change A Budget Code window will be displayed for you to enter the details.

Change A Budget Code Window (Option 1)

Use this window to change the description of a budget code.



Display this window by selecting a budget code line with 1 at the first Maintain Budget And Forecast Codes screen.

```

GL470          Y6 - Education Company - Y6          USER FFY6          31/07/95
                                           14:04:33

Maintain Budget & Forecast Codes

  Opt   Budget   Budget
   1     Code    Type   Description
   _     B01     1     Default budget
   -     F01     0     Default forecast

Change a Budget Code
Budget Code . . . B01
Budget Type . . . 1 (Budget)
Description . . . Default budget
F12=Previous

Position to . ? _ _ (0=Forecast, 1=Budget, 2=Quantity forecast, 3=Quantity
                    budget, 4=Currency forecast, 5=Currency budget)

1=Amend, 4=Delete
F3=Exit      F4=Prompt      F10=Add a budget or forecast
   15-36      SF           MK           KS           IM           II KENB20A PCET02S1
  
```

The budget code and type display for your information.

Fields:

Description

Enter a new description or amend the current description of this budget/forecast code.



Press **Enter**, then **F8=Update** to accept the new or amended code. You are returned to the previous screen. Amendments display.

Add A Budget Or Forecast Code Window (F10)

Use this window to add a new budget or forecast code. Select one of 6 types of budget or forecast code and add a description.



Note: Two budget/forecast codes are available as defaults on enquiry screens; the defaults are pre-defined on the company profile, but can be overridden at enquiry time. Should you need to change the default on a long-term basis (for example, first 6 months original budget, next 6 months revised budget) this can be changed on the company profile.



Display this window by pressing **F10=Add a Budget or Forecast** at the Maintain Budget And Forecast Codes screen.

GL470 Z1 - GB Demonstration Company USER GBJBA1MS 17/12/97 13:00:26

Maint Add a Budget or Forecast Code

Budget Code . . : C05

Budget Type . . : 1 (0=Forecast, 1=Budget, 2=Quantity Forecast, 3=Quantity Budget, 4=Currency forecast, 5=Currency budget)

Description . . : Sales Cost Budget

F12=Previous

CUR	5	Currency Budget
FBD	0	Forecast Budget
FOR	5	Foreign currency budget
KMB	1	km budget

Position to . ? _ _ (0=Forecast, 1=Budget, 2=Quantity forecast, 3=Quantity budget, 4=Currency forecast, 5=Currency budget)

1=Amend, 4=Delete

F3=Exit F4=Prompt F10=Add a budget or forecast

13-45 SA MW KS CL IM DM II STUD140 KB PKH312S1

Fields:

Budget Code

Enter a three-character code to create a new budget or forecast code.

Budget Type

Enter the budget type. This will be one of the following:

- 0 - Forecast.
- 1 - Budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.

4 - Currency forecast.

5 - Currency budget.

Description

Enter a new description or amend the current description of this budget/forecast code.



Press **F8=Update** to accept the new code. You are returned to the previous screen which includes the new code.

User-Defined Links Maintenance



3/GLG

Using the user-defined links option, link detailed low-level views to higher level views. Any update to budgets in the low-level view will automatically update the budgets higher up. This is known as rolling up.

Before using the User-Defined Links option, you must set up some user-defined views.



Note: For details see the chart of accounts section User-Defined Views Maintenance.


You can define more than one entry level view for a ledger, but in most situations there will be a one ledger to one entry level view relationship.

A cross-ledger view may not be an entry level view, but may be a higher level view. If you wish to maintain a budget for a cross-ledger view, you will need to specify it as a higher level view in all ledgers that contribute to it.

You can enter budgets directly into views specified as higher level views. However, this may result in the budget for that view not reconciling to the budget for the entry-level view.

Sequence Of Screens Diagram

This option is a complex one. The following diagram illustrates the sequence of screens, and will make the next section easier to understand.



Select User-Defined View Window



Select the budgets maintenance option User-Defined Links, enter the ledger on the first Maintain Links For Rolling Up Budgets screen and press **Enter**.

The next screen to display depends on whether the ledger you have selected has any entry (low) level views set up for it:

- If none has yet been set up, the Select User-Defined View window displays for you to set one up.
- If an entry level view has been set up, you will go straight to the third Maintain Links For Rolling Up Budgets screen, to link that view to a high level view.

If several entry level views exist, you will see the second Maintain Links For Rolling Up Budgets screen, to enable you to choose which entry level view you wish to link.

If no entry level view has yet been set up for the ledger you select, you will see the Select User-Defined View window, which enables you to select an existing view to become an entry level view.

Once you have selected one, you will be taken to the third Maintain Links For Rolling Up Budgets screen, in order to link it to a higher level view.

Maintain Links For Rolling Up Budgets Screen 1



Display this screen by entering a ledger on the Maintain Links For Rolling Up Budgets screen.

If more than one entry level view has been set up for the ledger, you will see the second Maintain Links For Rolling Up Budgets screen.



Note: Keys are views against which budgets may be entered.

fields:

Opt

1 - Select the view to be set up as an entry level view. You will be taken to the screen on which you link higher-level views to this entry level view.

4 - Remove the view.



Press **F3=Exit** or **F12=Previous** to return to the ledger selection screen.

Maintain Links For Rolling Up Budgets Screen 2



Whatever the route you take through the screens, you will end up at the Maintain Links For Rolling Up Budgets screen.

At this screen assign higher level views to your entry level view.



Note: This screen looks like the previous screen, but the list of views is called Keys (that is, views) to which budgets may be rolled up.

If the ledger you select on the first screen already has one and only one entry level view set up, you will be taken directly to this screen.

```

GL520          Y6 - Education Company - Y6          User FFY6          31/07/95
                                           14:09:36

Maintain Links for Rolling Up Budgets

Ledger . . P/L PROFIT & LOSS LEDGER
Entry key. 1 2 3 4 5 6 7 8 9 Division/Cost Centre
           - - - 1 2 - -

Keys to which Budgets may be Rolled Up

Opt  Lgr Key Description                                <-----Key----->
1    Cost Centre                                         <-Account level->
█    P/L Division                                         1 2 3 4 5 6 7 8 9
                                           - - - - -
                                           - - - 1 - -

1=Select  4=Remove
F3=Exit   F5=Refresh  F10=Add a budget entry key  F11=Delete  F12=Previous
13-03    SP          MM          KS          IM          II KENB20A PCET02S1
  
```

Fields:

Opt

1 - Against a view shown on the third Maintain Links For Rolling Up Budgets screen will link it to the entry level view towards the top of the screen. This means that the entry level budget values will from now on be automatically rolled up to the linked view.

4 - Beside a view to remove the link.

Functions:

F10

Add a Budget Entry Key. Define a new entry level view. You could use this if you do not want to select higher level views - for this entry level.



Press **F8=Update** to accept the new code. You

are returned to the previous screen which includes the new code.

Budget Locking Maintenance



4/GLG

This option enables you to select any budget for any specific year and lock it so that it cannot be maintained. Alternatively unlock a budget to enable maintenance.



Take the Budget Locking Maintenance option to see the following fields:

Fields:

Budget Code

Enter the budget you wish to lock or unlock.

Type

Enter the budget type.

Year

Enter the particular year for the budget you are maintaining.



Press **Enter** to display a new field.

Locked?

The current status of the budget lock displays here

0 - The budget is unlocked.

1 - The budget is locked.

You can maintain this field as required.



When the lock field is set, press **Enter**.

Rule Maintenance

Once budget types are created, four options are available for creating your budget rules:

- Budget Generation.
- Budget Apportionment.
- Budget Spreading.
- Warehouse Upload.

Full explanation and examples are given for each option. The option to select individual rules/users or all rules/users is available.

Budget Generation Rule Maintenance

11/GLG

This option enables you to set up definitions which will use existing budgets and actuals to create a new budget for a set of accounts.

The new budget can be a simple copy of the source data, or you can use factors to modify the values.

This option does not create the budgets itself, it simply stores the rule definitions. Once the rule is set up, the budget will be run using the Budget Generation option (Rule Processing).



Note: It is possible to submit a job to create budgets for a large number of accounts. For this reason a warning message displays when you create the rule, giving the upper limit to the number of target accounts involved.

```

GL606                Z1 - GB Demonstration Company    User GBJBA1MS    20/01/98
                                                           7:39:15

Generation - Define

Type option, Press enter
2=Change, 3=Copy, 4=Delete

Position to rule: _____
More:    -

Sel Rule      Description      User
- REP-GEN001 Repairs - Generate From Target TRENAMNJ
- REP-GEN002 Repairs - Generate With D-Fact TRENAMNJ
- REP-GEN003 Repairs - Generate App. Budget TRENAMNJ
- RULEABC    ktdkdfyfvjuyfyul GBJBANTX
- S21-1ST    S/21 Testing - Rule 1 GBJBARUL
- Y1BGF01    Copy utilities budget 95 to 96 GBJBAMLP
- 363        Problem 363 GBJBAJS1
- 606100     test for acc. LOAN

F3=Exit F10=Add

9-3  SA MW KS CL IM DM II STUD140 KB PKH312S1
  
```

Fields:

Sel

Enter one of the following values:

2 - To amend an existing rule.

3 - To copy a rule.

4 - To delete a rule.



Press **F10=Add Rule** to create a new rule.

Add Rule Window (F10)



To display this window press **F10=Add Rule** at the Budget Generation Rule Maintenance screen.

To enter a new rule, press **F10=Add Rule**. A window displays with the following fields:

Fields:

Unnamed (Rule Code)

Enter the rule code for your new rule.

Unnamed (Rule Description)

Enter the rule description for your new rule.



Press **Enter** to confirm the new rule and to display the Generation Define Screen.

Change Rule Window (Option 2)

-  Select an existing rule to maintain and to display a window with the following fields:

Use this window to change the rule description.

Fields:

Unnamed (Rule Code)

The rule code displays.

Unnamed (Rule Description)

The rule description displays for amendment.

-  Press **Enter** to continue to the second Generation Define screen.

Generation Define Screen 2



Press **Enter** from the Add Or Change Rule windows to see the second Generation - Define screen.

This screen specifies the accounts for which a budget will be created using the rule.

If you are creating a new rule, this screen first displays the default view of the profit and loss ledger. If you are maintaining a rule, the screen displays the ledger and user-defined view which were set up for this rule. You can change the ledger or view by pressing **F16=Change Ledger/View**.

Each budget generation rule works within a single ledger and view. You cannot create budgets for accounts in many ledgers with a single rule. Normally, you will select your view to be an entry-level view for the ledger.

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95 14:17:29
Generation - Define (Defn company Y6 Ledger P/L Rule FIRST)			
Target accounts	From	To	
Company. ?	Y6	Y6	
EXPENSE CODE ?			
Base on values or qty. . . (1/2)			
Source budget. ?	Type . . .	Currency. ?	
F3=Exit F4=Prompt F8=Update F12=Previous F13=Source Accounts			
F14=Dynamic Factor Accounts F16=Change Ledger/View			
06-30	SF	MM	KS IM II KENB20A PCET02S1

Fields:

From - To

These columns display the levels of the selected view, in view sequence. The rule will create a budget for accounts that are within the specified range. The company level is mandatory entry, while for the other fields four types of entry are valid:

- a - Entry in From and To - a straightforward range.
- b - Entry in From only - a single value.
- c - Both From and To blank - pick up all values.
- d - Used in conjunction with 1 and 2 above, the * character can be used as a wildcard. The selection A* to C*, for example, will pick up all values starting with A, B or C. The * must be in the same positions in the From and the To fields.



Note: If you specify more than one target company, the select ledger and view must exist

in all the target companies, with the same structure. If, for a particular company, this is not the case, that company will be excluded when the rule is run.

Base On Values Or Qty

When you submit the job to create the budgets you can choose to create the values from existing budget figures, from actuals, or from a mixture of the two. This field is relevant only if you choose to include actuals in the source of the new budgets.

If you decide to use the actuals, this field enables you to specify whether actual values (enter 1 here) or actual quantities (enter 2) should be used. By default, the actual figures will come from the target accounts.

Source Budget

An existing budget code must be entered here.

This budget will be the source for any budget figures required. By default, the budget figures will come from the target accounts.

Type

Enter the source budget type. This will be one of the following:

- 0 - Base forecast.
- 1 - Base budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.
- 4 - Currency forecast.
- 5 - Currency budget.

Currency

If the budget type is 4 or 5, enter the budget currency code.

Functions:

F13

Source Accounts. Specify accounts to be used instead of the target accounts as the source of information by the rule.

F14

Dynamic Factor Account. Specify accounts to be used as factors for the budget.

F16

Change Ledger/View. Change the ledger or view to be used.



Press **F8=Update** to save the changes.


Simple Budget Generation Example




Note: Please refer to the Introduction for details of the notation standards used in the diagrams which follow.

The following diagram shows the result of the simplest type of budget generation. The target accounts are TG1 and TG2, and the Base on values or qty field is set to 1 for values.

When the job was run, it was decided that actuals would be used, not budget values, so the source budget in this case can be any existing budget, as its figures are not used:



The target accounts are again TG1 and TG2, and the Base On Values Or Qty field again 1, but this time use of all-budget values is specified at runtime. The picture is as follows:



Generation Define Screen 3 (F13)

When no source account is specified, the target accounts are used to provide any actuals and budgets required. For example, create a new budget (for a set of accounts) that is 10% more than the old budget.

Specify a source account (**F13=Source Accounts**) to become the source for the actuals. It is then the account associated with the defined source budget.



Press **F13=Source Accounts** on the target accounts screen to display the Generation Define Screen.

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95
			14:20:30
Generation - Define (Defn company Y6 Ledger P/L Rule FIRST)			
Source account level overrides			
Company.	?		
EXPENSE CODE	?		
F3=Exit F4=Prompt F12=Previous			
06-30	SP	MM	KS IM II KENB20A PCET02S1

The target details display at the top of the screen as a reminder.

Fields:

(Fields as titled)

Descriptions display as previously defined.

The level values entered are used to override those found on each target account to form the corresponding source account.

If you leave a level blank, the original target level will be used. See Source Account Budget Generation Example for more information.




Press **Enter** to return to the target account screen.

Source Account Budget Generation Example



Note: Please refer to the Introduction for details of the notation standards used in the diagrams which follow.

The following diagram shows how defining a source account affects budget generation. The target accounts defined are TG1 and TG2, and the source budget is BUD1. The source account defined as the override means that AC1 and AC2 are picked up to provide the source values. Actuals are being used to provide the first two periods' values, BUD1 is used for the rest:



Generation Define Screen 4 (F14)



Press **F14=Dynamic Factor Account** for the Generation Define screen.

Use this option when the source and target accounts have been defined for your rule. The **F14=Dynamic Factor Account** function enables you to specify a separate set of accounts.

Actual or budget values for these accounts can be used in a mathematical operation with the corresponding source account values to produce a modified set of target values.

For example: Form a sales value budget:

Price information (memo set) * quantity information (other accounts)

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95
			14:21:02
Generation - Define (Defn company Y6 Ledger P/L Rule FIRST)			
Dynamic factor level overrides			
Company.	?		
EXPENSE CODE	?		
Arithmetic operation . . . *			
Ratio on val, qty or bud . _ (1/2/3)			
F3=Exit F4=Prompt F12=Previous			
06-30	SP	ML	KS IM II KENB20A PCET02S1

Enter the account or level code overrides to define the factoring accounts . As with defining source account overrides, any level left blank will cause the target level to be used in defining the factor accounts.

Fields:

Arithmetic Operation

Enter * if you wish each source value to be multiplied by the factor, / if you wish it to be divided, + to add, or - to subtract.

Ratio On Value, Qty Or Budget

This entry determines which value is to be used as the factor.

- 1 - To use actual value as the factor.
- 2 - To use actual quantity.
- 3 - To use a budget value.



Select 3, press **Enter** to display fields asking you to enter the budget details.

Budget Details Screen (Option 3)

Enter the budget code, select a type and where appropriate, the currency.



Select 3 on the Generation Define Screen. Press **Enter** to display fields enabling you to enter the budget details.

Fields:

Budget Code

Enter the code of the budget to be used for the factor values.

Type

Enter the budget type of the budget code. This will be one of the following:

- 0 - Base forecast.
- 1 - Base budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.
- 4 - Currency forecast.
- 5 - Currency budget.

Currency


If the type is 4 or 5, enter the budget currency. This field will default to the base currency if left blank.

Factor Account Example



Note: Please refer to the Introduction for details of the notation standards used in the diagrams which follow.

The following diagram illustrates the use of a factor account. The target account is TG1, the source account AC1, the source budget BUD1, the factor account override AC2 with BUD7. Actuals are used as the source for periods 1 and 2; budgets for periods 3 to 6. This is specified at runtime.



This rule can be used only by selecting the Budget Generation option from the menu.

Budget Apportionment Rule Maintenance

12/GLG

This option enables you to create a budget in target accounts by applying a ratio to a source budget in a single account. The ratio can be derived from posting values, from quantities, or from an existing budget.

One example of the use of this feature is to apportion an overhead expense between departments according to department head count.

This section explains in detail how budget apportionment works. There are two ways of defining an apportionment rule. The first uses data from the target accounts as its ratio figures, while the second specifies separate source accounts for the ratio. Each is examined in turn.

This option does not create the budgets itself, it simply stores the rule definitions. Once the rule is set up, the budget will be run using the Budget Apportionment option (Rule Processing).



Note: It is possible to submit a job to create budgets for a large number of accounts. For this reason a warning message displays when you create the rule, giving the upper limit to the number of target accounts involved.

Budget Apportionment Rule Maintenance Screen 1

-  Select the Budget Apportionment option to display a list of existing rules.

A list of existing rules display. Select a rule to amend, copy or delete.

Fields:

Sel

Enter one of the following values:

2 - To amend an existing rule.

3 - To copy a rule.

4 - To delete a rule.

-  Press **F10** to create a new rule. Enter a description at the window. Press **Enter**, and the first screen of the apportionment rule definition displays.

Apportionment Define Screen 2



To display this screen press **Enter** at the first Apportionment Define screen.

If you are creating a new rule, this screen first displays the default view of the profit and loss ledger, which can be changed using **F16=Change Ledger/View**. If you are maintaining a rule, the screen displays the ledger and user-defined view which were selected for this rule.

Each budget apportionment rule works in a single ledger and view. You cannot create budgets for many accounts with a single rule. Normally, you will select your view to be an entry level view for the ledger (see the section on User-Defined Links Maintenance).

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95
			14:26:12
Apportionment - Define (Defn company Y6 Ledger P/L Rule RULE)			
Source apportion account			
Company. ?	E		
EXPENSE CODE ?	_____		
F3=Exit F4=Prompt F12=Previous F16=Change Ledger/View			
06-30	SP	ML	KS IM II KENB20A PCET02S1

Enter the account which is to provide the source value to be ratioed into the target accounts' budgets. The budget codes are specified when submitting the job, using the processing option Budget Apportionment.

The level codes entered here must combine to form a valid account, as follows:

- Each individual code must be valid.
- If, for the ledger being processed, each active level in the range 1 to 4 is in the selected view, those levels must combine to form an entry on the chart of accounts.
- If, for the ledger being processed, links are active and each level in the link is in the selected view, those levels must combine to form an entry on the links table.



Note: The values in the account entered here will not be cleared down after the new budgets are created, so if you do not want the budget left in the source account, enter a zero budget for it after you have run the rule.



Enter this account and press **Enter** to see the third Apportionment Define screen:

Apportionment Define Screen 3



Press **Enter** at the second Apportionment Define screen.

This screen specifies the accounts for which a budget will be created using the rule.

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95
Apportionment - Define (Defn company Y6 Ledger P/L Rule RULE)			14:27:06
Target accounts	From	To	
Company ?	<u>Y6</u>	<u>Y6</u>	
EXPENSE CODE ?			
Ratio on val, qty or bud . _ (1/2/3)			
F3=Exit F4=Prompt F8=Update F12=Previous F13=Ratio on Accounts			
06-30	SF	ML	KS IM II KENB20A PCET02S1

Fields:

From - To

These columns display the levels of the selected view, in view sequence. The rule will create a budget for accounts that are within the specified range. The Company level is mandatory entry, while for the other fields four types of entry are valid:

- 1 - Entry in From and To - a straightforward range.
- 2 - Entry in From only - a single value.
- 3 - Both From and To blank - pick up all values.
- 4 - Used in conjunction with 1 and 2 above, the * character can be used as a wildcard. The selection A* to C*, for example, will pick up all values starting with A, B or C. The * must be in the same positions in the From and the To fields.

If you specify more than one target company, the selected ledger and view must exist in all the target companies, with the same structure. If, for a particular company, this is not the case, that company will be excluded when the rule is run.

Ratio On Val, Qty Or Budget

- 1 - Take the actual values in the ratio source accounts, and use them to apportion the value in the source account.
- 2 - Take the actual quantities in the ratio source accounts, and use them to apportion the value in the source account.
- 3 - Display fields enabling you to specify the budget to use for the ratio figures.



*Note: The ratio source accounts will be the target accounts unless **F13=Ratio on Accounts** is used to define a different ratio source.*



We will assume that you have selected option 3.
Pressing **Enter** shows:

Ratio On Source Budget

Enter the code of the budget to be used for ratioing. This will relate to the target accounts defined on this screen unless you use **F13=Ratio on Accounts** to define override accounts, in which case it will relate to those accounts. This field appears as a default on the screen which submits the job, but it can be changed.

Type

Enter the source budget type. This will be one of the following:

- 0 - Base forecast.
- 1 - Base budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.
- 4 - Currency forecast.
- 5 - Currency budget.

Currency

If the budget type is 4 or 5, enter the budget currency code.

Example




Note: Please refer to the Introduction for details of the notation standards used in the diagrams which follow.

Example of Budget Apportionment

The target budget (BUD2) is specified at runtime. The following diagram shows budget apportionment using a budget as the source of the ratio figures.

The source account is AC3. The target accounts are TG1 - TG2, with BUD7 entered as the ratio source.

The **F13=Ratio on Accounts** key is not used, so the target accounts themselves provide the ratio information.



An example of the calculation method follows, using the figures in the previous shaded boxes:

$$750 + 250 = 1000$$

$$(750 / 1000) \times 900 = 675$$

Apportionment Define Screen 4 (F13)



To display this screen press **F13=Ratio On Accounts** at the 3rd Apportionment Define Screen.

This method of apportionment follows the same route as the previous one until **F13=Ratio on Accounts** is pressed on the targets screen, when the Apportionment Define screen appears, enabling you to specify different accounts to supply the ratio.

Example Target Budget




Note: Please refer to the Introduction for details of the notation standards used in the diagrams which follow.

As in the previous example, the following diagram shows budget apportionment using a budget as the source of the ratio figures.

The source account is again AC3, and the target accounts are TG1 - TG2, with the ratio source budget BUD7.

This time, **F13=Ratio on Accounts** is used to specify accounts AC1 - AC2 as the ratio source accounts.

The target budget (BUD2) is specified at runtime:



The level values entered are used to override those found on each target account to determine the corresponding ratio account.

If you leave a level blank, the original level will be used.



Note: The ratios are determined separately for each period in the year.

Budget Spreading Rule Maintenance



13/GLG

A budget spread rule takes the existing budget for a range of accounts and redistributes it across a range of periods. The total budget for the accounts is unchanged.

There are two steps in creating the rule:

- 1 - Specify target accounts (no source account is specified, because the accounts used as the source are the target accounts themselves).
- 2 - Specify the spread over the target period range.

This option does not modify the budgets itself, it simply stores the rule definitions. Once the rule is set up, the job can be run using the Budget Spreading (Rule Processing) option.



Note: It is possible to submit a job to create budgets for a large number of accounts. For this reason a warning message displays when you create the rule, giving the upper limit to the number of target accounts involved.

Budget Spreading Rule Maintenance Screen

1



Take the Budget Spreading option (Rule Maintenance) to see a list of existing rules.

Select a rule to amend, copy or delete from the list of existing rules.

Fields:

Sel(ect)

Enter one of the following values:

2 - To amend an existing rule.

3 - To copy a rule.

4 - To delete a rule.



Press **F10** to create a new rule. Enter a description at the window. Press **Enter**, and the first screen of the spreading rule definition displays.

Budget Spread Define Screen 2



Press **Enter** at the first Budget Spread Define screen.

This screen specifies the accounts for which budgets will be modified using the rule.

If you are creating a new rule, this screen first displays the default view of the Profit and Loss ledger. If you are maintaining a rule, the screen displays the ledger and user-defined views which were set up for this rule.

You can change the ledger or view by pressing **F16=Change Ledger/View**.



Note: Each budget spread rule works within a single ledger and view. You cannot create budgets for accounts in many ledgers with a single rule. Normally you will select your view to be an entry level view for the ledger. See the earlier section on User-Defined Links Maintenance.

Fields:

From - To

These columns display the levels of the selected view, in view sequence. The rule will modify budgets for accounts within the specified range. The Company level is mandatory entry, while for the other fields four types of entry are valid:

- 1 - Entry in From and To - a straightforward range.
- 2 - Entry in From only - a single value.
- 3 - Both From and To blank - pick up all values.
- 4 - Used in conjunction with 1 and 2 above, the * character can be used as a wildcard. The selection A* to C*, for example, will pick up all values starting with A, B or C. The * must be in the same positions in the From and the To fields.



Note: For the spreading rule, the target accounts and budgets are also the source accounts and budgets.



Press **Enter** when you have entered the target accounts, and you will be taken to a screen which requires you to specify the ratio to be used for spreading the budgets.

Mass Budget Spread Define Screen



To display this screen enter a target and press **Enter** at the second Budget Spread Define Screen.


At this screen specify the ratio to be used for spreading the budgets.

Example Spread Definition



Note: Please refer to the Introduction for details of the notation standards used in the diagram which follows:

Define TG1 TG2 as the target accounts, and AC1 AC2 for the override, using BUD6 for the spread:



The target budget and the budget to supply the figures to be spread are defined at runtime.

GL607	Y6 - Education Company - Y6	User FFY6	31/07/95 14:31:36
Mass Budget Spread - Define (Defn company Y6 Ledger P/L Rule RULE)			
Ratio on spread profile. ? ☐			
OR			
Spread on account level overrides			
Company. ?			
EXPENSE CODE ?			
Spread on val, qty or bud. _ (1/2/3)			
F3=Exit F4=Prompt F8=Update F12=Previous			
05-30	SP	MM	KS IM II KENB20A PCET02S1

Fields:

Ratio On Spread Profile

If you wish to use an existing spread profile as the ratio for the spread, enter the code here.

Alternatively, you can spread based on actual or budget information held about the target, or a related set of accounts. To do this, enter a value in the Spread on field at the bottom of the screen.

Spread On Account Level Overrides

For each target account, the spread information will be found by using the override levels entered here.

Spread On Val, Qty Or Bud

- 1 - To use actual values for the ratio.
- 2 - To use actual quantities for the ratio.
- 3 - To bring up fields enabling you to specify the budget to be used for the ratio figures.

Source Budget

An existing budget code must be entered here.

Type

Enter one of the following source budget types:

- 0 - Base forecast.
- 1 - Base budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.
- 4 - Currency forecast.
- 5 - Currency budget.

Currency

If the budget type is 4 or 5, enter the budget currency code.



When you have entered the ratio to be used,
press **F8=Update** to update the rule.


PC Uplift Budgets Rule Maintenance

1... 21/GLG **2...**

If you use a PC option to create budgets you can transfer these budgets to a General Ledger company on your main system using the PC uplift feature. PC uplift transfers spreadsheet data to a location on your main system known as worksheets. To use the data for budgets, your transfer must follow the rules specified below.

Once the data is in the information base, the rules you set up in this option enable the system to add the essential information (company code, budget, budget type) to the raw data and to create the General Ledger records.

The following diagram illustrates the procedure:



As mentioned earlier, the PC spreadsheet data must conform to certain rules if a successful upload is to take place.

These rules are explained in reference to the following example spreadsheet.

Spreadsheet Data Rules - Example

	A	B	C	D	E	
1	Example Budget Upload					
2						
3		Final	Final	Final	Final	
4		Budget	Budget	Budget	Budget	
5		9401	9402	9403	9404	
6	001AA					
7	002AA					
8	001BB					
9	001BB					

- There must be at least some data in column A, for example the spreadsheet title in cell A1.
- The column containing the account numbers must be defined as the row descriptor. This need not be column A, but can be any column.
- The area holding the budgets must be defined as the details area. There can be up to 13 columns of budgets. The columns need not be columns B-N. Note that if your General Ledger is defined with more than 13 periods, you do not need to set up separate spreadsheets. Simply define a new set of parameters stored in a separate export file over the same spreadsheet to reference the remaining columns.
- The account code format depends on the rules defined on the host:

Where the user-defined view in the rule is an asterisk (*), the account entered is the 12 character fiscal account code.

Where you have used a specific view in the rule, the account you enter is in the format of this view (for example, 6512).

Do not use separators.

Once the data is set up in accordance with these rules, you can run PC Uplift Budgets to transfer the data to the information base.

It is then that you use this option, PC Uplift Budgets Rule Maintenance, to define the rules which will govern the transfer of the data from the information base.

Add Rule Window (F10)



Press **F10=Add** on the PC Uplift Budgets Define Screen to see the Add Rule Window.

The Add Rule Window is displayed whether you choose to amend or create a rule.

GL606	Y6 - Education Company - Y6	User FFY6	31/07/95 14:32:59
Data Warehouse to Budgets Upload - Define			
Type option, Press enter 2=Change, 3=Copy, 4=Delete		Position to rule: _____ More: _____	
Sel Rule	Description	User	
Add Rule RULE _____ Rule _____ F12=Previous			
F3=Exit F10=Add 16-40 SF MW KS IM II KENB20A PCET02S1			

Fields:

Code

If you have selected an existing code, this field is not maintainable. If you are creating a new rule, enter its code here.

Description

If you have selected an existing code, this field displays the current description, which may be changed. If you are creating a rule, enter its description here.



Press **Enter** to see the PC Budget Uplift Rules Definition Screen.

PC Budget Uplift Rules Definition Screen



To display this screen press **Enter** on the Add Rule Window.

If you are creating a new rule, this screen first displays the default view of the Profit and Loss ledger, which can be changed using **F16=Change Ledger/View**.

GL608	Y6 - Education Company - Y6	User FFY6	31/07/95 14:36:29
-------	-----------------------------	-----------	----------------------

PC Budget Uplift - Rules Definition

Rule.	RULE	Rule
Company	Y6	
Budget.	? B01	
Type.	(0/1/2/3/4/5)	
Ledger.	P/L	
User defined key.	1	
Currency.	?	
Roll to base.	— (0/1)	
Rate code	?	
Currency rate	— .00000	
Multiply/Divide	—	
Year.	—	
Period range.	01 to 12	

F3=Exit F4=Prompt F8=Update F12=Previous F16=Change Ledger/View

07-25 SP MW KS IM II KENB20A PCET02S1

Fields:

Company

Enter the target company code for the spreadsheet data which is to be uploaded.

Budget

Enter the target budget code for the spreadsheet data to be uploaded.

Type

Enter the type of target budget which is to be uploaded from the spreadsheet data. This will be one of the following values:

- 0 - Base forecast.
- 1 - Base budget.
- 2 - Quantity forecast.
- 3 - Quantity budget.
- 4 - Currency forecast.
- 5 - Currency budget.

Currency

If the budget type is 4 or 5, enter the currency code of the budget.

Roll To Base

Enter 1 if you want base values to be calculated from the prime values in the budget. This is used only with budget types 4 or 5.

This field is not relevant if your budget is in base currency.

Rate Code

Enter the rate to be used for prime to base conversion. This is used only with budget types 4 or 5.

Currency Rate

Enter a currency rate for prime to base conversion. This will override the rate code value.

This is used only with budget types 4 or 5.

Multiply/Divide

Enter the operation to be applied to the currency rate entered above.

* - Multiply

/ - Divide

This field is only used with budget type 4 or 5.

Year

Enter the year to which the budget applies.

Period Range

Enter the range of periods covered by the budget being uploaded.

Column B on your spreadsheet corresponds to the first period in this range, and so on.



When you have completed the entries, press **F8=Update** and the rule you have defined will be saved. The actual data transfer will not take place until you select the PC Uplift Budgets processing option.

Spread Profiles Report



31/GLG



Select the Spread Profiles Report (GL Budgets). You are not required to fill in any parameters; a batch job will be submitted when you have confirmed by pressing **F8**, and will generate the report of all spread profiles for the company.

Budget Codes Report



32/GLG



Select the option to print Budget Codes. The Print Report On Budget And Forecast Codes parameter screen displays.

Select a range of budgets and options of base, quantity or prime budgets and forecasts for the report.

GL471	Y6 - Education Company - Y6	USER FFV6	31/07/95 14:30:30
Print Report on Budget & Forecast Codes			
Print Base Forecasts?	1	(0/1)	
Print Base Budgets?	1	(0/1)	
Print Quantity Forecasts?	1	(0/1)	
Print Quantity Budgets?	1	(0/1)	
Print Prime Forecasts?	1	(0/1)	
Print Prime Budgets?	1	(0/1)	
From Budget	?	---	(Leave blank for first)
To Budget	?	---	(Leave blank for last)
Print accounts to which a budget has been applied?	0	(0=No, 1=Yes)	
F3=Exit F4=Prompt 05-41 SF MK KS IM II KENB20A PCET02S1			

Fields:

Print Base Forecasts

0 - Do not print forecasts.

1 - Print forecasts.

Print Base Budgets

0 - Do not print budgets.

1 - Print budgets.

Print Quantity Forecasts

0 - Do not print quantity forecasts.

1 - Print quantity forecasts.

Print Quantity Budgets

0 - Do not print quantity budgets.

1 - Print quantity budgets.

Print Prime Forecasts

0 - Do not print prime forecasts.

1 - Print prime forecasts.

Print Prime Budgets

0 - Do not print prime budgets.

1 - Print prime budgets.

From Budget

Enter the code name of the first budget in the range of budgets you wish to see on the report.

Leave blank to accept all budgets.

To Budget

Enter the code name of the last budget in the range of budgets you wish to see on the report.

Leave blank to accept all budgets.

Print Accounts To Which Budget Applies

0 - Do not print the accounts which have a budget specified.

1 - Print the accounts which have a budget specified.



Press **Enter** to submit a batch job to print the report.

User-Defined Links Report



33/GLG



Select the option to print User-defined Links.

This procedure allows you to run a report of the specified paths for rolling up budgets, either based on the views that are rolled to from an entry-level view or the views that roll to a target view. It does not provide an audit trail of rolled up budgets.

Print Entry Level Views And Views To Which They Are Rolled

0 - Do not print entry level views.

1 - Print entry level views.

Print Calculated Views And Views From Which They Are Rolled

0 - Do not print calculated views.

1- Print calculated views.



Press **Enter** to submit a batch job to produce the report.

Rule Reporting

Once your budget rules are created, four options are available to report details:

- Budget Generation Rule Report.
- Budget Apportionment.
- Budget Spreading.
- Warehouse Upload.

The option to select individual rules/users or all rules/users is available.

Budget Generation Rule Report



41/GLG



Select the Budget Generation option (Rule Reporting). The screen displayed requires you to enter the rule code of the rule you want to print, and a prompt of existing generation rules is available.

When you have entered the code, press **Enter**. A message will be displayed at the bottom of the screen to tell you that the print is being generated, and you can then exit by pressing **F3=Exit**.



Produce a report of all generation rules by leaving the field blank and pressing **Enter**. A message will warn you that the report may be a long one, and you must confirm by pressing **Enter** again.

Budget Apportionment Rule Report



42/GLG



Select the Budget Apportionment option (Rule Reporting). The screen displayed requires you to enter the rule code of the rule you want to print, and a prompt of existing apportionment rules is available.

When you have entered the code, press **Enter**. A message displays at the bottom of the screen to tell you that the print is being generated.



You can produce a report of all apportionment rules by leaving the field blank and pressing **Enter**. A message will warn you that the report may be a long one, and you must confirm by pressing **Enter** again. Exit with **F3=Exit**.

Budget Spreading Rule Report



43/GLG



Select the Budget Spreading option (Rule Reporting). Enter the rule code to be printed. Select from existing spread rules is available.

When you have entered the code, press **Enter**. A message will be displayed at the bottom of the screen to tell you that the print is being generated, and you can then exit by pressing **F3=Exit**.



Produce a report of all spreading rules by leaving the field blank and pressing **Enter**. A message will warn you that the report may be a long one, and you must confirm by pressing **Enter** again.

PC Uplift Budgets Rule Report



51/GLG



Select the PC Uplift Budgets option. The screen displayed requires you to enter the rule code of the rule you want to print, and a prompt of existing rules is available.

When you have entered the code, press **Enter**. A message is displayed at the bottom of the screen to tell you that the print is being generated, and you can then exit by pressing **F3=Exit**.



Produce a report of all rules by leaving the field blank and pressing **Enter**. A message will warn you that the report may be a long one, and you must confirm by pressing **Enter** again.