

-
-
-
-
-

Chapter 1

Maintenance



Maintenance Introduction

Before invoices can be posted or payments made in Accounts Payable it is first necessary to set up the basic information about suppliers. This can be done, after the company profile has been set up, using maintenance options.

First of all, one record is created for each supplier, using the Names and Addresses option from the menu. Each record is identified by a unique, user-defined supplier account number, and holds such information as the supplier address, details of payment terms and methods, VAT codes, discounts and General Ledger accounts.

The system also enables you to define despatch addresses for each supplier. These are used if you have the Purchase Management application installed, and are particularly flexible with regard to the entry of text at supplier or item level.

Reason codes and location codes may also need defining - see the relevant sections for more details.

The final three options on the Maintenance section enable you to set up profiles for recurring payments to be made within Accounts Payable.

Reports are available on most of the maintenance options.

Company Profile Maintenance



3/ASCO

Each application requires the configuration of control parameters and master files in order for you to operate it. The most important control information that any application requires is the company profile. Accounts Payable supports multiple companies. For every company that you want to use you must create a company profile that holds the rules that govern the operation of Accounts Payable for that company.



Warning: In order to configure the Accounts Payable module you must ensure that the General Ledger company which you wish to link AP to is installed with a complete chart of accounts. Also set up the Cash Management company to be linked to Accounts Payable.

This section describes how you create and maintain a company profile in Accounts Payable. The system also provides you with the facility to produce a printout of configured company profiles.



Warning: You should avoid changing existing company profiles once the application is in use, as this may corrupt your data. If a change is essential it must be strictly controlled.



Note: You cannot maintain a company profile when other users are using the application.

This section describes how to create or maintain a company profile. The maintenance of company profiles is performed using the same procedure and screens as those used in creating a company.

Creating a Control Account

When you specify a General Ledger account as an Accounts Payable control account, the system displays a message saying that if you want to make this account a General Ledger control account, press **F8**.

Printing the Company Profile

You can print a report of company profile details. A report is generated of all the company profile data for this company.

Country Specific Parameterisation

GL Country Specific Parameters controls such features as the accounting period to which an invoice is posted, the goods and VAT amounts which are required for each line dissection and the dates when an invoice can be due.

Below are some of the parameters that affect Accounts Payable.

Default VAT Calculation Method A/R

This determines the values required on the invoice dissection line:

0 - Enter the goods and VAT values.

1 - Enter the goods value and the VAT value is calculated.

2 - Enter the gross amount and the VAT value is calculated from this.

Check that date and period correspond causes the system to validate the invoice date to see if this falls within the application posting period. This requires the accounting calendar to be active:

Accounting Calendar Active

This switches on the calendar in the General Ledger. Non working days and holidays can be specified in this calendar. It is possible to prevent future posting by using this calendar. There is a field that allows or disallows this.

AP Due Date Exclude Weekends? /AP Due Date Exclude Holidays?

If set to yes and the calculated due date falls on a weekend or holiday, the next valid working day will become the due date. For the two due date options to be effective:

- 'Accounting Calendar Active' must be set to 1.
- Holiday and weekend dates are set up as a calendar code in the Parameter CLND in the General Ledger.

'Calendar' code must be entered for the supplier at Names and Address Maintenance



To access the company profile, select the Accounts Payable option, enter the code of the company you wish to set up or maintain, and press **Enter**.

Maintain Company Profile Screen 1

This screen is the first screen of information about the company you are creating or maintaining. It contains basic company details and defines defaults that are used throughout the application. If you are creating a new profile then you must complete the fields displayed. If you are maintaining an existing company profile then you can amend any of the fields displayed.

PL005		User LOAN	13/11/96
			13:02:26
Maintain company profile		Company number Z1	
Company name Z1 Sample Test Company			
Multi currency?	0 (0/1)	Default currency rate code? PERD	
Periods per year	12	Currency code	GBP
Posting period	9601	Overdue analysis period 1	)
Next invoice number	1212	2	60)
Next payment number	1	3	90) Days
Next transfer ref	T 000000	4	120)
Revaluation?	1 (0/1)	5	150)
Default payment terms	0 30	Immediate/Delayed updates	I (I/D)
Post inhibit flag	0	Allow due date overrides?	1 (0/1)
Purge: No. of months	2	Purge: No of transactions	
Payment print queue	QPRINT	In library	*LIBL
Take all discounts	0 (0/1)	ELSE, days margin	14
Use batch controls?	1 (0/1)	Country code	GB
Invoice log active?	1 (0/1)	Default payment method	CHQ
Auto generate inv ref?	1 (0/1)	Extended terms	
General Ledger active?	1 (0/1)	General Ledger company	Z1
Cash Management active?	1 (0/1)	Cash Management company	Z1
F3=Exit F4=Prompt F12=Previous 06-26 SF ML KS IM II KENB20A PET16SS2			

Fields:

Company Name

If this is the first time this company has been set up in any application, enter the name of the company. (This name will then be given to all other applications for this company.)

If the company has already been named, the name displays and cannot be changed.

Multi Currency

1 - Currency transactions may be posted.

0 - Postings may be made in base currency only.

Default Currency Rate Code

For a multi-currency ledger, enter the rate code most often used to convert prime currency values into base currency values. If the code is not yet set up, a window displays to enable you to define it.

Periods Per Year

The number of periods in the financial year, from 1 to 99. This must be the same as for the General Ledger if the two applications are linked.

Currency Code

The default currency code for suppliers in the company. This must be a valid currency code.



Warning: Once you have used Accounts Payable, this field cannot be amended.

Posting Period

When adding a new company, enter the opening period for the ledger using the format YYPP. This is subsequently maintained by the normal period close and open functions. Once set up it should not be updated. The period entered should be the period into which you wish to enter the opening balances.

Overdue Analysis Periods

The accounts payable overdue analysis allows for analysis across five periods. The number of day's indebtedness for each period is established here. These values provide a default that can be changed at report request time.

Next Invoice Number

To ask the system to generate your invoice numbers sequentially, enter 1 in the 'Auto Generate Invoice References' field on this screen.

Enter the first number from which the system should begin to number items. This may be 1, or the number after the last value used on the system, if applicable. Most users write this number on the actual document for reference purposes after entering the invoice on the system.

You may also, if using two separate Accounts Payable systems, set them off on separate number sequences. This is essential if two or more Accounts Payable companies are linked to the same General Ledger company.

The system will automatically number invoices from the value given, and will update this field.

Next Payment Number

The number sequence for payment runs processed through the GL Bank menu. This is not used if Cash Management is linked.

Next Transfer Reference Number

Each transfer may be assigned an automatic transfer reference - See 'Item Transfer' procedure. This reference number is assigned during the transaction to transfer an invoice from one supplier account to another.

If several Accounts Payable companies are linked to one General ledger, the ranges of references used need to be different for each Accounts Payable company.

Revaluation

0 - Currency revaluation is not required, or you run a single currency environment.

1 - To revalue creditor balances in this company by the General Ledger revaluation procedure.

Default Payment Terms

Enter the codes that enable the system to calculate a default payment date for each item posted. The value can be overridden at supplier level.

There are three parts to the definition of payment terms:

1. A single character code that defines the type of terms to be used. Select from the following codes:

D - Number of days from invoice date.

M - Number of months before payment.

P - Periodic range.

T - Extended (spread) payment terms.

2. This field is used with the above code P, to indicate the period range in number form. For example, a code of P 2019 106 would generate for all invoices with a document date between 20th of this month and the 19th of next month a payment date of 6th of next month.

3. This field holds the number of days in the format DDD for the above code D, or holds the month and the date in the format MDD for the above codes P and M.

For example, a code of D ____ 030 means that the payment date is 30 days from the invoice date. A code of M ____ 210 means a payment will be made on the 10th of the second month after the month in which the invoice was sent.

Immediate/Delayed Updates

You can opt either for an immediate or for a delayed update of Accounts Payable. If immediate update is chosen, an update job is submitted at the end of each session.

Enter:

I - Immediate update of the ledger.

D - Deferred update.

(General Ledger update is always submitted as a batch job).

Post Inhibit Flag

1 - No processing is allowed in this Accounts Payable company. It is used by the application during period close to prevent processing until the next period is opened. The flag can also be set manually if you wish to prevent processing.

0 - Allow processing to restart. This can be useful as set up time to prevent users from entering test data into a live company in error. Please note that whilst this flag is set, should you attempt to process any data you will receive a message saying the period has been closed.

Allow Due Date Overrides?

1 - To enable payment due dates (calculated by the application from the given payment terms) to be changed at invoice posting.

Leave this field blank to inhibit changes

Purge: Number Of Months

When completed, transactions are eligible to be deleted or 'purged' from the computer system. The value entered into this field indicates the minimum number of periods for which transactions are to be retained for each customer.

At set up time it is worth entering a value here. For example, enter 12 even though this could be changed later. This will prevent accidental purge of transactions in recent periods if running the purge to remove names and addresses.

Purge: Number Of Transactions

The value entered into this field indicates the minimum number of transactions that are to be retained for each customer, regardless of the value in the 'Purge: Number of Months' field. Zero transactions may be stated. Extreme caution should be exercised when deleting transactions. Refer to your consultant. Transactions are purged (archived using options in the utilities menu) and can be enquired/reported upon using the historical data menu.

Payment Print Queue And Library

These fields establish the print queue and library associated with the production of remittance advices and cheques that are produced on special stationery. The values override those set up in System Manager. You may need to discuss these values with your systems administrator.

Take All Discounts And Days Margin

These two parameters establish company policy with regard to discounts. If you want discounts to be taken in the payment routines regardless of age, enter a 1 in 'Take all discounts'. If you want discounts to be taken only under controlled circumstances, enter a 0 in 'Take all discounts' and specify in 'Days margin' the number of days overdue beyond which discount will not be taken. Days Overdue is based on the date the 'Final Report' is confirmed.

Use Batch Controls?

Enter a 1 here if you wish to use batch controls, otherwise leave this field blank.

As well as the mandatory session control, which ensures the audit trail of transactions on the system, Accounts Payable offers you an optional batch control facility.

This, if switched on here, requires anyone about to enter a batch of transactions to enter a total beforehand. This is reconciled with the actual batch total on leaving the session. Any discrepancy displays, but may be ignored.

Country Code

This is a three character field that holds the code of the country in which the system is operating. The code will ensure that the financial system operates in accordance with local practice. The code is not related to language or currency codes. See the section on Country Specific Parameters.

Invoice Log Active?

Determines whether you may enter invoices to the invoice registration log (pending authorisation), before they are posted to the ledger.

1 - You may enter invoices to the log. If you intend to use the invoice matching features of the Purchase Management application, you need to set this flag to 1.

0 - The invoice log features will not be used.

Default Payment Method

If the Cash Management application is not installed then the payment methods available to you are predefined as:

CHQ - Cheque

TRF - Transfer

BAC - BACS

When Cash Management is installed then payment methods are defined there. This is done using the payment methods option on the Maintenance menu. Any number of methods may be defined, although each will be of one of the following types:

- Cheque
- Transfer
- Electronic
- Collection documents
- Cash
- Credit Card
- EDI

Auto Generate Invoice References?

Accounts Payable invoices, credit notes and journals require a unique reference for access, enquiry and audit purposes.

1 - You wish these references to be generated by the application.

0 - You wish to enter the references for directly posted transactions.

Extended Terms

The Cash Management application enables you to set up extended terms codes that govern the payment by instalment of any Accounts Payable item. The code selected will spread the payment of the item according to the rules set up in the code itself.

General Ledger Active?

The General Ledger application is a prerequisite of the full Accounts Payable application.

1 - The link is active

0 - The link is not active

If this is set to 0 no General Ledger analysis will be available.

General Ledger Company

If the link from Accounts Payable to the General Ledger is active, you must also enter the company of the General Ledger company to which you are linked. General Ledger details are entered on a subsequent screen.

Cash Management Active?

The Cash Management application is mandatory. Enter 1.

Cash Management Company

Enter the company code of the Cash Management company from which payments are to be made. This need not be the same as the General Ledger company to which you are linked. However, the Cash Management company and the Accounts Payable company must be linked to the same General Ledger.

Add a Rate Window



If the rate code you select on the maintenance screen has not yet been set up, a window will be displayed to tell you to press **F4** for a list of available rate codes, or to press **Enter** to add a rate code. If you press **Enter** these are the fields you will see:

Fields:

Rate Code Description

Up to 35 characters defining the rate code (e.g. 'Standard Trading Rate').

Effectivity Type

An effectivity date may be applied to each rate code. This may be entered as a calendar date or accounting period.

P - accounting period

D - calendar date

Effectivity dates are entered when you set up the exchange rates themselves.

Add a Currency Window



If the currency code you select on the maintenance screen has not yet been set up, a window displays to tell you to press **F4** for a list of available currency codes, or to press **Enter** to add a currency code. If you press **Enter** these are the fields you will see:

Fields:

Description

Enter the currency description.

Short Description

The description entered here will appear on many screens and reports.

Smallest Unit

This field contains the value of the smallest unit of the specified currency (e.g. in US dollars the smallest unit is one cent, shown as 0.01, whereas the smallest unit of the Japanese yen is one yen 1.00).

Movement Tolerance

Some currency exchange rates fluctuate wildly whereas others vary within a much smaller band. The movement tolerance field enables you to specify a single plus/minus percentage for the exchange rate variation. Movements outside this range will cause a warning to be issued when exchange rate information is entered.

Further maintenance of currency rates is available from the GL currency menu.

Maintain Company Profile Invoice Log Details Screen



If on the previous screen you entered 1 against Invoice Log Active, the Maintain Company Profile Invoice Log Details screen will be displayed when you press **Enter**:

PL005	ALL COMPANIES.	User PRODSUPP	18/07/96
			14:20:36
Maintain company profiles...Invoice log details			
Company number . . . : Z2			
Please answer 1 or 0/blank (1=yes, 0/blank=no) to the following:			
Auto. references? . . . 1	Generate log references.	(0/1)	
Validate accounts? . . . 1	Validate General Ledger accounts	(0/1)	
Validate VAT? 1	Valid VAT codes and values.	(0/1)	
Ignore VAT tolerance . _	Ignore bulk transfer VAT tolerance	(0/1)	
GL postings from receipts . . . _			
Post unmatched to ledger . . . _			
F3=Exit without update		F12=Previous	
11-25	SP	KS	IM II KENB20A PET165S2

Fields:

Automatic Log References

All log transactions require a unique reference for access, enquiry and audit purposes.

1 - if you wish these references to be generated by the application.

0 - if you wish to enter the references manually.

Validate General Ledger Accounts

When analysing log items it is possible to specify dissection to actual General Ledger accounts. It may be that such analysis is not required at this stage. In this case you may analyse items to general headings rather than real codes.

Specify 1 here if you want codes to be validated on the General Ledger chart of accounts.

Validate VAT Values

1 - You wish VAT codes and values for posted items to be validated when they are posted to the log. This is particularly useful if you use the log reports to accrue for VAT.

0 - You do not want the items validated until they are transferred to the ledger.

GL Postings From Receipts

This field is available when you have the Purchase Management system installed.

1 - If you are using AFI to post stock receipts as a result of goods receipts in Purchase Management, ledger postings will:

- Debit stock account
- Credit Receipts Suspense (stock accruals account) when stock receipt posted.

In Invoice Matching on posting the invoice, ledger postings will:

- Debit Receipts Suspense (Stock accrual account)
- Credit Creditors account.



Note: On the third company profile screen you will be prompted to enter a GL balance sheet stock accruals account.

0 - You are not using AFI to post stock receipts - no GL postings will be generated.



Warning: A problem could occur if you change this field after processing. A manual adjustment journal for the existing receipts would be required.

Post Unmatched To Ledger

This field is an Italian accounting requirement to enable VAT reclaim at an earlier stage.

1 - Unmatched invoices posted at the Invoice Matching option will be posted to the ledger rather than the log. The default ledger balance accounts will be updated to:

- debit unmatched suspense and VAT accounts and credit the creditors accounts.

Once matched, goods received will be posted from the suspense account to either

- the accrual account or
- purchase accounts(for non-stock orders).



Note: On the third company profile screen you will be prompted to enter a GL balance sheet 'Unmatched Suspense Account' code.

Only when matched may payments be made at the automatic payment cycle. Manual or ad hoc payments may be made.

0 - if your unmatched invoices are to be posted to the unmatched invoice log and only later (when matched) posted to general ledger accounts.



If you are creating a new company or amending an existing company profile for which the General Ledger interface is active, then the following fields are displayed:

Fields:

Control Account

This is the default creditors control account in the attached General Ledger for this Accounts Payable company, and it may not be changed once postings have been made to it. (The account may be changed at supplier level as long as no postings have been made to the supplier).

The account entered must not have had postings made to it, and, once defined, the system prevents user postings being made.

General Ledger Bank Account

This is the default bank account in the General Ledger for Accounts Payable payments. It must be user-defined as a bank account. This account can be changed at supplier level.

General Ledger Discount Account

This is the General Ledger account for the posting of discount taken when items are settled.

Stock Accruals Account

This field will display if GL Postings From Receipts (previous screen) is set to 1.

This is the General Ledger credit account for posting stock accruals via AFI.

Post Unmatched Suspense Account

This field will display if Post Unmatched To Ledger (previous screen) is set to 1.

If you are using the three way match option this is the debit account for posting unmatched invoices.

Creditor Suspense Account

This field is for future development.

Default VAT Code

A VAT code is set up in the General Ledger to carry not only a percentage rate (in Britain, for example, the code STD might carry a rate of 17.5%), but also to specify the General Ledger accounts for VAT postings for sales and purchases.

The effect of settlement discounts on VAT calculations is controlled by options from the GL VAT menu.

When posting transactions, the system calculates a VAT rate from the VAT and goods values entered, and compares it to the rate attached to this VAT code. If these are not the same (or are outside the tolerance levels defined in the General Ledger), then an error message is given.

Enter here the VAT code to be used as the default for this company, this may be overridden at supplier and transaction level.

VAT On Cash Date

The entry in this field decides whether VAT is accounted for an item on the transaction date or when payment is made.

0 - VAT based on transaction 'tax date'.

1 - VAT based on cash payment.

This is a default flag that may be changed for individual suppliers.

VAT Address Code

If VAT communications are to be sent to an address other than the normal supplier address, enter the despatch address code that will be used for each such supplier.

Names and Addresses



1/APM

This option enables you to set up and subsequently maintain basic details for each of your suppliers.

VAT Registers

This facility to produce VAT analysis reports based on tax area is used in Italy, where VAT registers are a feature of VAT reporting. The two-character codes, known as registers, are set up in the General Ledger, and each code relates to a particular VAT office.

If the VAT to be paid is cash-based, in which case VAT cannot be claimed until the supplier has been paid, then, in addition to the standard purchase register already set up for the tax office, a suspense VAT register would be defined to it. This register would hold the VAT on the paid invoice until it was claimed, when it would be transferred to the purchase VAT register.

Contra Accounts

A trading partner may often be both a supplier and a customer. Where this is the case, the contra accounts facility establishes a link between the supplier and customer accounts. This link causes an Accounts Payable payment to be reduced by the amount in the contra account in Accounts Receivable.

It is possible to include Accounts Receivable items to net off against the amount due. It is then necessary to enter the contra account function within Accounts Receivable to match the payment to the Accounts Receivable items.



Select the Names and Addresses Maintenance option from the Maintenance menu, and the supplier selection screen will be displayed.

You can now:

- Enter a new supplier code to add a new supplier. The maintenance screen will be displayed with blank fields
- Enter a new supplier code to add a new supplier, then press **F6** to base the supplier on an existing supplier. Instead of showing blank fields, the maintenance screen will be displayed showing the details of the supplier on which the new supplier is to be based
- Enter an existing code to view or change the details of a supplier already on the system

If you enter a new supplier and wish to base it on an existing supplier, enter the new supplier code and press **F6** to see the following fields:

Fields:

Supplier Code

Enter here the code of the supplier whose details you wish to be copied to form the basis of the new supplier.

Company

Enter the company to which the base supplier is defined. This field defaults to the current company.

Copy Despatch Addresses

1 - The despatch addresses defined to the base supplier to be copied to the new supplier.



Now press **Enter** to see the first Supplier Maintenance screen.

Supplier Maintenance Screen 1

PL015		Y9 - Education Company - Y9		USER FFV9	27/07/95
					8:37:15
Supplier Maintenance					
Account : K100		NEW		Alpha Seq _____	
Name		_____			
Address		_____			
_____		_____			
_____		_____			
Phone 1		Post code		_____	
Phone 2		Fax 1		_____	
Country ? GB		Fax 2		_____	
Contact 1		Language ?		_____	
Contact 2		_____			
Remarks		_____			
Currency 1		Currency code . ?		GBP	
Payment terms 0 30		Payment method . ?		_____	
Disc % & override . . 0		Discount code . ?		_____	
F3=Exit F4=Prompt F12=Previous					
06-12		SP		ML	
KS		IM		II EDN400A PCET02S3	

Fields:

Account Code

This is a display-only field with the caption 'addition' or 'amendment' as appropriate displayed alongside.

Supplier Name

Up to 35 characters are allowed for the display or printing of the supplier's name.

Alpha Sequence

The information entered here is used to sequence the supplier in alphabetical order in reports. It can be used to search for a supplier using ? and F4 prompt. If you do not wish to use Alpha Sequence for report sequencing you can use this field to specify particular supplier types e.g. stationery.

Address Line 1

Up to 35 characters may be entered for the first three lines of the supplier's address.

Address Line 2

Free format entry of up to 35 characters.

Address Line 3

Free format entry of up to 35 characters.

Address Line 4

Free format entry of up to 25 characters.

Address Line 5

Free format entry of up to 25 characters.

Post Code

Enter the supplier's post code.

Phone 1

Up to 20 characters for the supplier telephone number.

Fax 1

Up to 20 characters for the supplier facsimile number.

Phone 2

Enter here a second supplier telephone number.

Fax 2

Enter here a second supplier facsimile number.

Country

Some payment methods require the supplier's bank details. If the default payment method you select for this supplier is one of these methods, a bank details window will be displayed.

The country code entered here decides the format of this window for entry of the supplier's banking details.

Language

This field is for future development.

Contact 1

Enter here the name of your usual contact at this supplier. The name will appear on enquiries and reports.

Contact 2

Enter here the name of a second contact at this supplier. The name will appear on enquiries and reports.

Remarks

Up to 60 characters are available to hold any remarks or notes.

Calendar

Enter or select a calendar code (as set up in the GL Parameters option). This code will be used to calculate the payment due date.

If no code is entered 0001 will display as a default calendar code.

Currency

0 - If this supplier trades only in base currency.

1 - If the supplier trades in various currencies and may have currency invoices posted to the account. This is seen if the ledger is multi-currency.

Currency Code

If the multi-currency field is 0 then either leave this field blank (the base currency will then be the default), or enter the base currency. This is seen if the ledger is multi-currency. Currencies must be defined in the GL Currency Menu.

If the multi-currency field is 1, enter the three-character currency code that is to be the default trading currency of the supplier. Leave the field blank if no default code is required (the supplier may trade in several currencies).

Payment Terms

Payment terms will default to those which are established in the company profile if these fields are left blank, but enter different terms here to define rules for this particular supplier.

There are four parts to the definition of payment terms.

1. A single character code that defines the type of terms to be used. Select from the following codes:

D - Number of days from invoice date.

M - Number of months before payment.

P - Periodic range.

T - Extended (spread) payment terms.

2. This field is used with the above code P, to indicate the period range in number form. For example, a code of P 2019 106 would generate for all invoices with a document date between 20th of this month and the 19th of next month a payment date of 6th of next month.

3. This field holds the number of days in the format DDD for the above code D, or holds the month and the date in the format MDD for the above codes P and M.

For example, a code of D ____ 030 means that the payment date is 30 days from the invoice date. A code of M ____ 210 means a payment will be made on the 10th of the second month after the month in which the invoice was sent.

4. If the above code T was specified, then this field must hold the extended terms code. This is a code set up in the Cash Management application that defines a schedule of payments. If the invoice meets the financial value it will be paid in specified instalments.

Payment Method

Enter the default payment method to be used for payments to this supplier. This defaults in from the company profile or can be input for each supplier record. The payment methods are set up in Cash management maintenance. The choice of payment method includes the following types:

- Cheque
- Transfer
- Electronic
- Collection docs (bills of exchange)
- Cash
- Credit Card
- EDI



Note: Bank details will be requested for EDI payment methods (unless excluded). EDI payment methods with bank details excluded are

created by selecting a type 7 (EDI) but one that was set up as a sub-code on CS Parameter EBDP.

Discount Percentage

Enter the percentage settlement discount that can be claimed from invoices submitted by this supplier.

This field cannot be used if a discount code is defined for this supplier.

Override

0 - Do not allow discount percentage to be changed at item entry time.

1 - To allow the discount percentage to be changed at item entry time.

Discount Code

Enter here the Cash Management extended settlement discount code that holds the discount structure used by this supplier.

This field cannot be used if a discount percentage has been entered for this supplier.



Press **Enter** to validate the screen and go to the second Supplier Maintenance screen.

Supplier Maintenance Screen 2



Press **Enter** on the first Supplier Maintenance screen to see the second Supplier Maintenance screen. This enables you to enter more details, including the General Ledger accounts to be used in processing payments to a supplier.

PL015	Z1 - GB Demonstration Company	USER LOAN	13/11/96 13:54:16
Supplier Maintenance			
Account : GOV		NEW	
Name . : Government Suppliers		Alpha Seq	GOV
Factor code . ?		Group code 1/2/3/4 ?	FF1
Payment group ? M		A/C status ?	-
Deletion flag . _		Credit limit	0
VAT code . . ? 001		Cash basis VAT	0
VAT ID		Fiscal code	
Withholding tax 1		Tax classification .	0
GL company . : Z1		GL dist code ?	
Control A/C . ?		Bank A/C ?	
Purchase A/C ?		Contra Co/Account ?	
Pricing UoM . . _		Value date type . .	1
F3=Exit F4=Prompt F12=Previous			
17-61 SF ML KS IM II KENB20A PET165S2			

Factor Code

If the supplier wishes all payments to be made to a factoring company, enter the factor's supplier code here. This is created in the same manner as an ordinary supplier account.

The factor company must itself be set up as a supplier in Accounts Payable.

Group Code 1/2/3/4 ?

These four three-character group codes enable suppliers to be sequenced in many different ways, for user-defined analysis.

These codes must be predefined GL parameters SGP1 to SGP4.

These codes may also be used to sequence reports within this application, for example the aged creditors analysis, and the name and address report.

Payment Group

You can categorise your suppliers, for example, as steel suppliers, miscellaneous suppliers, etc.; the category can be used to select suppliers for an automatic payments run.

This must also be pre defined in the GL parameters.

The character * must not be used as it has a reserved meaning within the application.

Account Type

1 - Purchase order matching is required for invoices posted to the log for this supplier.

Status

This single-character field indicates the current status of the supplier in terms of postings and payments. It may have the following values:

Blank - Normal operation.

H - Hold.

N - None.

P - Prompt pay.

L - Log only.

X - Exclusion.

Blank - Items entered to the supplier's account are processed by the automatic payment procedure.

H (Hold) - All invoices and journals entered for this supplier are held, and will not be eligible for payment through the automatic payments due cycle.

H has no effect on credit notes, which are always treated as prompt pay items.

H has no effect on items already posted to the invoice log or ledger. If you need to hold these items, this may be done through payment status maintenance.

N (None) - Payments to the supplier will not be made under any circumstances.

P (Prompt pay) - All items will appear on the next automatic payment due report. The payment due date will be set to the document date automatically when the item is entered.

L (Log only) - Postings to this supplier may only be made to the invoice log.

X (Exclusion) - Invoices and credit notes may not be posted against this supplier. Payments may still be made.

If the status is changed there is no retrospective effect on outstanding invoices.

Deletion Flag

This field indicates whether the supplier is still active. It is normally left blank to denote an active supplier. If you wish a supplier to be removed from the application, enter D. This will have two effects:

No further postings will be allowed.

The application will attempt to remove the supplier when the supplier purge and archive routines are next run. If there are still unpurged transactions against the supplier at this time, the application will be unable to remove the supplier.

Credit Limit

This field is for future development.

VAT Register Required

1 - You wish to analyse the supplier's VAT using registers.

VAT Register

This is a two-character field that holds a VAT register code defined in the General Ledger. Enter the appropriate VAT register for the supplier.

VAT Code

Enter here a default VAT code to be used for this supplier. If this field is left blank, the system will default instead to the VAT code on the company profile. The code can be redefined at transaction level.

A VAT code is set up in the General Ledger to carry not only a percentage rate, but also to specify the General Ledger accounts for VAT postings for sales and purchases.

When posting transactions, the system calculates a VAT rate from the VAT and goods values entered, and compares it to the rate attached to this VAT code. If these are not the same (or are outside the tolerance levels defined in the General Ledger), then an error message is given.

Cash Basis VAT

This field decides whether VAT is accounted for on the item tax date or when payment is made. The field defaults to the value on the company profile.

0 - VAT based on transaction date.

1 - VAT based on payment.

VAT ID

Enter the VAT identity code assigned by the government to this supplier.

Fiscal Code

Enter the classification code assigned by the government to this supplier.

This is a reference field that displays on some reports.

Withholding Tax

1 - If this supplier is subject to withholding tax, to be paid directly to the government.

See the Maintaining Withholding Tax section for more details.

Tax Classification

Enter the appropriate code from the following:

0 - Legal entity

1 - Male

2 - Female

The last two codes are used for withholding tax suppliers.

GL Company

This field displays the General Ledger company to which this Accounts Payable company is attached.

GL Dist Code

If a pre defined distribution code is used when invoices are posted to AP the General Ledger dissections will be generated automatically. More accounts are available here than the Purchase Account. Standard distributions are defined on the AP Maintenance menu.

Control Account

This field enables you to specify that this supplier's transactions are to be posted to a different control account to the one set up in the company profile.

If left blank, the default control account on the company profile will be used. If an account is entered, it must already have been defined to the chart of accounts in General Ledger.

This account cannot be changed once postings have been made for this supplier.

Bank Account

Separate bank accounts may be set up to cater for specific suppliers. If entered, it must have been defined to the chart of accounts and as a bank account. If left blank, the company profile bank account is used.

Purchase Account

This field enables you to specify that purchases made from this supplier are normally to be posted to the General Ledger account code entered here.

The account must already be set up on the chart of accounts. This code is offered for dissection of invoices and credit notes, but you may change it if you wish.

Contra Account Company

This is a two character field that holds the company code of the related contra account in Accounts Receivable. Contra accounting is carried out from the AR processing menu.

Contra Account

This is an eight character field that holds the Accounts Receivable customer account number that is automatically set up as a contra account.

Pricing UoM

Enter a pricing unit of measure for this supplier. You may enter any text as this is a free text field.

Value Date Type

- 1 - In place. The supplier's bank and your bank are close to each other - normally in the same town.
- 2 - The banks are in different towns.
- 3 - The banks are in different countries.

This field displays only if value dates are required in the country-specific parameters in the General Ledger.

The value is used with the value date table in Cash Management to calculate the date on which the bank account is updated with a payment. It is an estimate of the number of days a payment takes to clear.

Withholding Tax Maintenance Window

This function is essentially a form of advance income tax. For example, any sub-contractors and professional employees are set up as suppliers in Accounts Payable. When they submit invoices, part of the invoice value is retained by the paying company and paid directly to the government.

In order to do this, details required by the government are entered on the Withholding Tax Maintenance window.



Enter '1' in the Withholding Tax field on the second Supplier Maintenance screen to see the Withholding Tax Maintenance window.

Fields:

Tax Company

For withholding tax to be paid, the government must be defined as a supplier on the system. Enter here the company to which the government supplier is defined, normally the same company.

Tax Supplier Code

For withholding tax to be paid, the government must be defined as a supplier on the system. Enter here the government's supplier code.

Type

This is a government-provided code identifying the supplier's type of business. This is always attached to a supplier defined as a withholding tax supplier.

National Code

Enter the code indicating the country from which the supplier is operating.

Address Code

Enter the government-provided code indicating the region of the tax authority for the purposes of withholding tax.

Area

Enter the government-provided code indicating the area of the tax authority for the purposes of withholding tax. The area code lies within the address code.

Birthplace

Enter the birthplace of the supplier.

Date Of Birth

Enter the birth date of the supplier.

Calculation Percentage

Enter the percentage of the goods or service value that is subject to withholding tax.

Tax Percentage

Enter the withholding tax percentage that is to be charged against the amount subject to withholding tax.

Payment Analysis Maintenance Window

The payment analysis facility is governed by a flag setting in the environment in which the company is running. It is not a setting on the company profile itself.

Payment analysis enables you to analyse payments you make by attaching each one to an analysis group. These groups are set up in the General Ledger, and can have a series of analysis enquiries and reports run over them.

This facility has a particular application in the USA, where it is referred to as 1099, and is a type of tax reporting. Companies employing contractors are required to inform the government of any payments made, and the payment analysis facilities provided throughout the application enable accurate reporting of this.



If the company you are working with is defined as using payment analysis or 1099, then when you press **Enter** on the second Supplier Maintenance screen the Payment Analysis Maintenance Window displays.

Fields:

Analysis Reporting ID

Enter the government-provided analysis reporting ID (TIN number) for this supplier.

Default 1099 Anl Group

Enter the analysis group that you wish to appear as a default group when postings are made.

Reporting ID Type

Enter the type of ID for this supplier:

0 - Payment analysis supplier.

1 - 1099 supplier.

If you enter 1, the 1099 Reporting Address Maintenance window displays to enable you to specify the address to which the supplier's copy of the 1099 details will be sent. (This may not be the same as the supplier master address.)

1099 Reporting Address Maintenance Window



Enter 1 in the Reporting ID Type field on the Payment Analysis Maintenance window to see the 1099 Reporting Address Maintenance window.

Use this window to specify the address to which the supplier's copy of the 1099 details will be sent. This may not be the same as the supplier master address. When you produce a 1099 return for the US government, you will send a copy to the supplier. As the supplier address you have on the system could be a branch address, for example, you need to enter the head office address for the tax return.

The government assigns one 'Analysis Reporting ID' (also known as 'TIN' number) to each business entity. As several of your suppliers may belong to a single entity, they will have the same reporting ID. Once the reporting address has been entered for one of them, the details will be displayed automatically in the window for each of the others. Otherwise, the fields will be blank.

Fields:

Name

Enter the name of the supplier entity to which a copy of the 1099 return is to be sent.

Line 1

Enter the first line of the reporting address.

Line 2

Enter the second line of the address.

Line 3

Enter the third line of the address.

City

Enter the city name. This field is mandatory entry. The city name must be entered here to ensure that the address is formatted correctly when printed.

State

Enter the two-character state code.

The following is a list of standard USA state codes:

Code	Description	Code	Description
AL	Alabama	MT	Montana
AK	Alaska	NE	Nebraska
AZ	Arizona	NV	Nevada
AR	Arkansas	NH	New Hampshire
CA	California	NJ	New Jersey
CZ	Canal Zone	NM	New Mexico
CO	Colorado	NY	New York
CT	Connecticut	NC	North Carolina
DE	Delaware	ND	North Dakota
DC	District of Colombia	OH	Ohio
FA	Florida	OK	Oklahoma
GA	Georgia	OR	Oregon
GU	Guam	PA	Pennsylvania
HI	Hawaii	PR	Puerto Rico
ID	Idaho	RI	Rhode Island
IL	Illinois	SC	South Carolina
IA	Iowa	SK	South Dakota
KS	Kansas	TN	Tennessee
KY	Kentucky	TX	Texas
LA	Louisiana	UT	Utah
ME	Maine	VT	Vermont
MD	Maryland	VA	Virginia
MA	Massachusetts	VI	Virgin Islands
MI	Michigan	WA	Washington
MN	Minnesota	WV	Wisconsin
MS	Mississippi	WI	Wyoming
MO	Missouri	GU	Guam

Zip Code

Enter the zip code.

Country

Enter the country code.

Edit Code

The 1099 reporting requirements specify that the tax identification number (TIN) of a supplier be formatted correctly. There are two formats:

- 1 - The supplier is a company and TIN is a federal identification number.
- 2 - The supplier is an individual and the TIN is a social security number.

Bank Details Maintenance Window



When you have completed the second Supplier Maintenance screen, plus any payment analysis and 1099 information, press **Enter**. If the payment method you have specified for your supplier requires bank details to be entered, the Bank Details Maintenance window displays. The format of this window varies depending on the country entered in the Country Code field on the first Supplier Maintenance screen.



*Note: If you are maintaining a supplier defined as a withholding tax supplier, the Bank Details Maintenance window appears after you press **F8** to update the Withholding Tax Maintenance window.*

Despatch Addresses

2/APM

This facility is used only by the Purchase Management package, and should be disregarded if Purchase Management is not available.

If Purchase Management is installed, then this maintenance option enables you to assign up to 999 despatch addresses to any one supplier.



Note: The supplier must be set up as a code in the Names and Addresses option before despatch addresses can be attached to it.

If a VAT address code is specified on the company profile, you need to set up a VAT address with this code for each supplier requiring separate VAT communications.



Select the Despatch Addresses option, and on the selection screen enter the code of the supplier you wish to maintain, and press **Enter**. The supplier address will be displayed beneath the supplier code you have entered.



Press **Enter** again, and you can then either enter the code of the despatch address you wish to maintain, or leave the code blank. If left blank you can select from a complete list of addresses for the supplier.

Whichever path you choose, you will then see the maintenance screen.

PL025	Z1 - GB Demonstration Company	User LOAN	13/11/96
			15:20:45
Enter/Update Supplier Despatch Addresses			
Supplier Code.....: MCB1		McBrook	
		Mundella Works	
Shipping Address code.....: STH		ADDITION	
Shipping Name...: _____			
Address Line 1...: _____			
Address Line 2...: _____			
Address Line 3...: _____			
Address Line 4...: _____			
Address Line 5...: _____			
Post Code.....: _____			
Contact Name.....: _____			
Telephone Number: _____			
Group.....?.. 1: _____ Group 2: _____ Group 3: _____ Group 4: _____			
Special Remarks.: _____			
F4=Prompt F12=Previous			
09-21 SF MW KS IM II KENB20A PET16SS2			

Fields:

Shipping Name

Enter the name of the despatch recipient. Use up to 35 characters.

Address Line 1

Enter the first line of the despatch address. Up to 35 characters may be entered.

Address Line 2

Free format entry of up to 35 characters.

Address Line 3

Free format entry of up to 35 characters.

Address Line 4

Free format entry of up to 25 characters.

Address Line 5

Free format entry of up to 25 characters.

Post Code

Optional entry. Enter the post code of the despatch address.

Contact Name

Enter the contact name at this address. Up to 35 characters.

Telephone Number

Enter the telephone number of this address, up to 20 numeric characters.

Supplier Groups 1 - 4

These three character group codes enable the coding of suppliers for user defined analysis. These codes may also be used to sequence reports within this application such as the aged debt analysis and name and address report. These codes are predefined using the GL Parameters maintenance option.

Special Remarks

This is a free format entry field of up to 60 characters. It provides a brief narrative for the despatch address if required.

Activity Code

Optional entry defining the status of this despatch record. A blank in this field signifies that the address is active. If the despatch address is to be suspended enter D in this field. The despatch address details will be removed from the system when the next purge or archive routine is performed.

Reason Codes



3/APM

When creating a journal adjustment or a credit note, an explanation of the reason for the transaction may be attached to the journal or credit. This is done by creating a code for each reason, and entering the appropriate code when creating the transaction. The codes are set up here.



Select the Reason Codes Maintenance option, and the following fields will be displayed. To create a new code, enter a reason code and a description.



Note that these codes are not maintainable - to alter a code simply delete it with a 4, then enter it as a new code.

Fields:

Delete

To delete an existing reason code, enter a 4 in this field and press enter.

Reason Code

Enter the new reason code.

Description

Enter a brief reason code description.

Location Codes



4/APM

This facility is used only by the invoice log procedure. If you do not use an invoice log, do not set up location codes.

If you are using the log but do not wish to trace log items, it is advisable to set up a blank location code so that the validation may be bypassed. A blank code should ONLY be used in this circumstance. To create a blank location leave the location code blank but enter a description.

A location code represents an individual or a department within a company to whom authority is given for the acceptance of invoices, credit notes or journals. Its use, mandatory if logs are used, enables the tracking of documents sent for authorisation.



Select the Location Codes Maintenance option, and the following fields will be displayed. To create a new code, enter a location code and a description.



Note that these codes are not maintainable - to alter a code simply delete it with a 4, then enter it as a new code.

Fields:

Delete

To delete an existing location code, enter a 4 in this field and press **Enter**.

Location Code

Enter the location code.

Description

Enter a brief description of the location being defined.

Supplier and Item Text



5/APM

In addition to the normal financial details held for each supplier, you may also maintain free-format text. The text may be used for keeping records of accounts in query, payment promises, telephone conversations, and so on. You may also add or change text associated with a specific transaction on this supplier's account. This text can be accessed and maintained in many areas of the system. e.g. Enquiries.



Select the Supplier and Item Text maintenance option, enter your selected supplier and press **Enter**. The following fields will be displayed:

Fields:

Item Type

If text is to be entered for the supplier only then this field must be left blank. If text is to be entered for a specific document, enter the type code of that document in this field. The valid type codes are as follows:

CR - Credit Note

JL - Nominal Journal

CA - Cash on Account

FJ - Prime Currency Journal

PX - Cancelled Payment

PY - Payment

DL - Log Deletion

AL - Allocation

JT - Journal Transfer

Item Reference

Enter the reference number of the item to which text is to be attached. This is a mandatory entry field if the item type is entered.



Note: You cannot prompt on this field alone. If you wish to prompt, enter ? in both fields and press F4.



Whether you have decided to enter supplier or item text, press **Enter** and a screen of blank lines will appear, enabling you to enter text as you wish. Once you have finished entering, press **F8** to update the text.

Recurring Profile



6/APM

The recurring payments facility enables you to make regular payments automatically, for example, lease payments or payments for public utilities. Once a recurring profile has been defined it should be processed via the recurring payments option on the processing menu.

The running order for setting up recurring profiles is as follows.

The Parameters option from the GL Audit menu to set up parameter RPAC.

Schedule from the AP Maintenance menu to set up the schedule.

Recurring Profile from the AP Maintenance menu to set up the recurring profile.

There are three types of recurring payment:

Constant Recurring Payment

When you know the value of each payment to be made as well as the value of each General Ledger dissection, this can all be defined and payments made with a minimum of maintenance.

Standing Recurring Payment

If the payment value varies but the General Ledger accounts used remain the same, this type of payment enables you to specify the accounts here, but to enter the values when the payment is due.

Spread Recurring Payment

If the payment value varies but the General Ledger accounts used and the proportion of the payment value to go to each account remain the same, this type of payment enables you to specify the accounts and ratios here, but to enter the value when the payment is due.

Recurring Profile Maintenance Screen 1



Select the Recurring Profile option to see the first Recurring Profile Maintenance screen.

PL260	Z1 - GB Demonstration Company	USER LOAN	13/11/96 15:28:48
Recurring Profile Maintenance			
Supplier ? █			
Profile ? ____			
Based on profile . ? ____			
Based on company . ? <u>Z1</u>			
F3=Exit F4=Prompt			
05-23 SP MM KS IM II KENB20A PET165S2			

Fields:

Supplier

Enter the code of the supplier to which you want to make recurring payments.

Profile

Enter a code to which you are to define the pattern of recurring payments.

Based On Profile

If you wish to copy the details of a profile which has already been defined, enter that profile code here.

Based On Company

If you wish to copy the details of a profile that has already been defined, enter the company of that profile code here.

This field defaults to the current Accounts Payable company.



When you have completed these fields, press **Enter** to proceed to the second Recurring Profile Maintenance screen.

Recurring Profile Maintenance Screen 2



Press **Enter** on the first Recurring Profile Maintenance screen to see the second.

PL260	Z1 - GB Demonstration Company	USER LOAN	13/11/96 15:34:10
Recurring Profile Maintenance			
Supplier MCB1	McBrook	Profile 02	INCOMPLETE
Description . . .	plc rp2		
Timing			
Number to post	12		
Terms	0	30	
Next date	201295		
End date	999999		
Lead time	30		
Schedule	?		
Last date / Number processed : 000000 / 0			
Rules & Values			
Type	3		
Autopay	4		
Standard value		1175.00	
Discount rate			
Discount value			
F3=Exit F4=Prompt F11=Delete F12=Previous			
Date may not be less than current date.			

Fields:

Description

Enter here the code description.

Number To Post

Enter the number of postings to be made for this profile. Enter 0 if an end date is to be specified.

Terms

You can define here your pattern of recurring payments, using the following three fields:

1 - A single character code that defines the type of terms to be used. Select from the following codes:

D - Number of days from invoice date.

M - Number of months before payment.

P - Periodic range.

W - Weekly terms.

2 - This field is used with the above code P, to indicate the period range in number form. For example, a code of P 2019 106 would generate for all invoices with a document date between 20th of this month and 19th of next month a payment date of 6th of the month following the 19th.

3a - If the first code is D:

This field holds the number of days in the format DDD.

3b - f the first code is P or M:

This field holds the no. of months and the date (format MDD).

3c - If the first code is W:

Position 1 holds a value from 1-7 (1=Monday, 2=Tuesday etc.). Positions 2-3 hold a multiple of 7 to indicate frequency of payment.

For example, a code of D ____ 030 means that the payment date is 30 days from the invoice date.

A code of M ____ 210 means a payment will be made on the 10th of the second month after the month in which the invoice was sent.

A code of W ____ 414 means that payments will be made every other Thursday.

Next Date

This field holds the date on which the supplier next expects payment to be made.

This field is system-maintained, so as to display the next payment date as payments are made.

End Date

Enter here the date of the final payment to be made.

Lead Time

The 'next date' field represents the date on which payment must be received by the supplier.

Enter here the number of days before this date that the payment procedure must be started (taking account of the mail, the clearing system, your own procedures, etc.).

This entry has a direct effect on the date that the payment will be recommended to be paid. Note that when calculating the lead time, weekends must be included. Thus if it is Friday 15th, and you want payment to reach the supplier on Tuesday 19th, the lead time is five days, not three.

Schedule

A schedule is a code set up in Accounts Payable Maintenance that holds user-defined posting dates.

If you wish to define your posting dates using a schedule, (if, for example, the payments are irregular), enter an existing schedule code here.

Schedules cannot be used if the 'terms' field is being used.

Type

You must enter one of the following codes in this field:

1 - Constant

The value of each payment is unchanging, and the distribution to the General Ledger accounts and values is also constant.

2 - Standing

The payment value may vary, but the General Ledger accounts used do not change. The account values are entered when posting.

3 - Spread

The payment value may vary, but the General Ledger accounts used and the ratio of the spread values are predefined. The values may be amended when posting.



Note that this field can not be maintained once a posting has been made.

Autopay

This entry decides to what extent automatic processing is to be used when a recurring payments run is made.

Enter one of the following:

- 1 - creates a log item only.
- 2 - creates a ledger item only.
- 3 - creates a ledger item and a payment record for subsequent release from Cash Management.
- 4 - creates the ledger item and automatically processes a manual payment through Cash Management. This is the recommended entry for standing order payments, for example.

If 1 or 2 is entered, the supplier's default payment terms must not be for spread payments.

Standard Value

The entry here depends on the code entered in the 'type' field.

- If the profile type is constant (1), enter here the gross posting amount in prime currency. The value must be greater than '0.00'.
- If the type is standing (2), this field is not used and must equal '0.00'.
- If the type is spread (3), enter the spread control value. The value must be greater than '0.00'.

Discount Rate

This field defaults to the discount percentage set up for this supplier. The field may be maintained only if the discount override flag for the supplier is set to 1.

Discount Value

This field can be used only if the profile type is constant (1), and the discount override for the supplier is set to 1.

Enter the value of the discount in prime currency.



Press **Enter** to continue to the third Recurring Profile Maintenance screen.

Recurring Profile Maintenance Screen 3



Press **Enter** on the first Recurring Profile Maintenance screen to see the second.

PL260	Y9 - Education Company - Y9	USER FFV9	28/07/95 15:20:40
Recurring Profile Maintenance			
Supplier M100	ADINGTON MANUFACTURING SUPPLIERS	Profile TEST ACTIVE	
Description . . : Test Recurring Profile			
Defaults			
Payment method	? HQ		
External reference	RPAC 001		
Analysis code ? TS			
Inter co	0		
VAT 1 17.50			
Currency ? GBP			
Rate code	*DFT		
Rate	1.00000 M		
F3=Exit F4=Prompt F11=Delete F12=Previous F17=Override rate			
09-33 SR MK KS IM II EDN400A PE0079S1			

Fields:

Payment Method

Enter a valid payment method.

External Reference

Enter here any contract or agreement number. If this field is not used, it will default to the profile code.

Location Code

Enter a location code if the 'Autopay' field is set to 1.

Analysis Code

This is a user classification code that is not used by the system.

Valid codes are set up on the General Ledger parameter file. Use the parameter RPAC. At least one code must be set up because it is a mandatory entry field.

Inter Co

1 - Inter company postings are to be made.

Withholding Tax/Payment Analysis

1 - If either payment analysis (including 1099) details or withholding tax details are to be entered.

VAT

1 - VAT is to be entered as part of the General Ledger distribution.

VAT Value

Enter a VAT value only if the profile type is constant (1), and the VAT field is 1.

VAT Register

This field will default to the register set up for the supplier, but may be amended.

Currency

If this is a multi-currency supplier, this field will default to the supplier's currency, and may be amended.

Rate Code

This code will supply the currency conversion rate if any currency other than base is being used.

Rate

An actual currency conversion rate may be entered here instead of a rate code.



When you press **Enter** again, the dissection screen will be displayed to enable you to enter the correct distribution for the profile you have selected. This will depend on whether you selected a constant, standard or spread profile in the Type field on the second Recurring Profile Maintenance screen.

Maintain Constant Distribution Screen



Press **Enter** on the third Recurring Profile Maintenance screen to see the dissection screen relevant to the profile you selected in the Type field on the second Recurring Profile Maintenance screen. If you asked for a constant profile, you will see the Maintain Constant Distribution screen.

PL270	Y9 - Education Company - Y9	User FFY9	28/07/95 15:21:11
-------	-----------------------------	-----------	----------------------

Maintain Constant Distribution			
Description . Test Recurring Profile			
Control value	:	117.50	
Vat value	:	17.50	
X	Account code	Description	Value
-	606130	Electricity	100.00
	Extn 00004/000/000	VAT	17.50 STD

Account code ?		Value .	
Vat ?	STD	Desc	

X 1=Select, 4=Delete			
F4=Prompt	F8=Accept	F11=Delete whole distribution	F12=Previous
20-19	SP	MK KS IM II	EDN400A PE0079S1

Fields:

X

- 1 - To select a line for amendment.
- 4 - Delete a line.

I/C

If posting is required to a General Ledger company other than the current one, enter that company here.

Account Code

Enter the General Ledger account.

Value

Enter the value to be posted to this account.

VAT

The VAT code in this field will default to the supplier's VAT code for the first line, and thereafter will default to the last code entered.

VAT Value

Enter the VAT value for the account.

Description

Enter a description as required. If left blank, this field will default to the short description on the Chart of accounts.



Press **Enter** to see the line you have entered appear at the top of the screen. If you are using General Ledger extension codes, an extension code window will appear first, and you must amend the codes if necessary, then press **Enter** to accept them.

Maintain Standing/Spread Distribution Screen

Select a distribution line for amendment or deletion.



Press **Enter** on the third Recurring Profile Maintenance screen to see the dissection screen relevant to the profile you selected in the Type field on the second Recurring Profile Maintenance screen. If you asked for a standing or a spread profile, you will see the Maintain Standing/Spread Distribution screen.

PL270	Y9 - Education Company - Y9	User FFV9	28/07/95 15:25:06
Maintain Standing Distribution Description . Test Recurring Profile			
X	Account code	Description	
-	606130	Electricity	
Account code ? _____			
Desc _____			
X 1=Select, 4=Delete			
F4=Prompt F8=Accept F11=Delete whole distribution F12=Previous			
F22=More detail			
20-19	SR	MK	KS IM II EDN400A PE0079S1

Fields:

X

1 - Select a line for amendment.

4 - To delete a line.

I/C

If posting is required to a General Ledger company other than the current one, enter that company here.

Account Code

Enter the General Ledger account.

Desc

Enter a description as required. If left blank, this field will default to the short description on the chart of accounts.



Press **Enter** to see the line you have entered appear at the top of the screen. If you are using General Ledger extension codes, an extension

code window will appear first, and you must amend the codes if necessary, then press **Enter** to accept them.

Withholding Tax Window

This screen displays If your supplier is a withholding tax supplier (see the Names and Addresses section for further details).



Enter 1 in the Withholding Tax field on the third Recurring Profile Maintenance screen and press **F8=Accept** to update to display the following fields.

Fields:

Type

This field will default to the tax code set up for the supplier, but may be amended.

Calculation %

Enter the percentage of the goods or service value which is subject to withholding tax.

This field defaults to the value set for the supplier, but may be amended.

Tax %

Enter the withholding tax percentage to be charged against the amount subject to withholding tax. This field defaults to the value set up for the supplier, but may be amended.

Excluded Goods Value

Enter the value of goods not taxed.

This field will default to zero.



Press **Enter** to accept these details. A window will be displayed showing the calculated values.



Press **F8** to complete all updates.

Payment Analysis (1099) Window

This screen displays if you are using payment analysis, or your supplier is a 1099 supplier (see the Names and Addresses section for further details).



Enter 1 in the Payment Analysis field on the third Recurring Profile Maintenance screen and press **F8** to update.

Fields:

Code

Enter the analysis group code for the entered value.

Amount

Enter the value for the corresponding analysis group code.



Press **F8** to update.

Standard Distributions



7/APM

This option enables the system to enter General Ledger dissections automatically when making a posting.

First, you must define any commonly used pattern of dissections as a code. This code is then specified as a supplier default or entered for an individual posting. This provides the dissections automatically during posting, but you can still make any necessary amendments before the posting is sent.



Select the Standard Distribution option from the Maintenance menu to see the Maintain Distribution Templates screen.

Maintain Distribution Templates Screen

This screen enables you to:

- Select a template to maintain by entering 1 beside it. Its details will be transferred to the fields at the bottom of the screen, where they can be amended
- Enter a new template using the fields at the bottom of the screen

PL271		Y9 - Education Company - Y9		USER FFV9	28/07/95
Maintain Distribution Templates					
X	Dist.ref	Description	Type	Control value	I/C
-	COS1	Cost of Sales 1 (Standing)	2	.00	0
-	COS2	Cost of Sales (Spread)	3	100.00	0
-	UTIL	Utilities	3	100.00	0
Distribution ref . . .		Description . . .			
Distribution type . . .		Inter Co . . . @			
Control value . . .					
X 1=Select 4=Delete					
F3=Exit F4=Prompt					
19-25	SF	ML	KS	IM	II EDN400A PE0079S1

Fields:

X

- 1 - Select a line for amendment.
- 4 - To delete a line.

Distribution Ref

Enter a standard General Ledger distribution.

Description

Enter a template description.

Distribution Type

- 2 - For a standing type.
- 3 - For a spread type.

Control Value

This field will be used only for a template with a distribution type of 3 (spread). Enter the value.

Inter Co

- 1 - If distribution postings are to be made across General Ledger companies.



When the template has been maintained or entered, press **Enter** and you will see the Maintain Spread Distribution screen, where you can maintain existing details or enter new ones.

Maintain Spread Distribution Screen

Select a distribution line for amendment or deletion.



Press **Enter** at the Maintain Distribution
Templates Screen.

PL270	Y9 - Education Company - Y9	User FFV9	28/07/95 15:28:18
Maintain Spread Distribution			
Description . Cost of Sales (Spread)			
Control value :		100.00	
X	Account code Description	Value	
-	601100 Raw Mat Purch.UK	50.00	
-	601200 Raw Mat.Purch.USA	20.00	
-	601300 Raw Mat.Purch.Europe	15.00	
-	601400 R.Mat Purch.Other	15.00	
Account code ? _____		Value . _____	
Desc _____			
X 1=Select, 4=Delete			
F4=Prompt F8=Accept F11=Delete whole distribution F12=Previous			
F22=More detail			
20-19 SF MW KS IM II EDN400A PE8079S1			

Fields:

X(Select)

- 1 - To select a line for amendment.
- 4 - To delete a line.

I/C

If posting is required to a General Ledger company other than the current one, enter that company here.

Account Code

Enter the General Ledger account.

Value

Enter a value. Note that if you are defining a spread profile, the values entered here are taken to be a ratio, not an actual value.

Desc

Enter a description as required. If left blank, this field will default to the short description on the chart of accounts.

Functions:

F22

More Detail. This displays more detail of each entry.



When you are satisfied with the updates, press
F8=Accept.

Schedules



8/APM

This facility enables you to set up a schedule of payment dates to use with the recurring payments facility.

This facility will be used when the pattern of payments is irregular.



Select the Schedules option to see the schedule selection screen.

If you wish to maintain an existing schedule, enter the code in the field and press **Enter**. The dates defined to that schedule will be displayed first, unless you wish to maintain the description, in which case you must press **F19** to see the header.

If you are entering a new code, enter the code in the field and press **Enter**, and the header screen will be displayed automatically to enable you to enter the description.

Fields:

Group Description

Enter a description for the schedule code.



When you have entered or maintained the description, press **Enter** to see the first Maintain Schedules screen.

Maintain Schedules Screen 1



When you have entered or maintained the description, press **Enter** to see the first Maintain Schedules screen.

PL265		Y9 - Education Company - Y9		USER FFY9		28/07/95 15:58:10	
Maintain Schedules							
Schedule		Description				Action	
TEST		Test Schedule Group				Change	
Type changes, press Enter							
Seq.No.	Date	Seq.No.	Date	Seq.No.	Date		
10	280795	110	_____	210	_____		
20	40895	120	_____	220	_____		
30	110895	130	_____	230	_____		
40	180895	140	_____	240	_____		
50	250895	150	_____	250	_____		
60	_____	160	_____	260	_____		
70	_____	170	_____	270	_____		
80	_____	180	_____	280	_____		
90	_____	190	_____	290	_____		
100	_____	200	_____	300	_____		
More...							
F3=Exit		F8=Update		F9=Generate dates		F12=Previous	
11-16	SP	ML	KS	IM	II	EDN400A	PE0079S1

Fields:

Date

Enter the series of dates on which you wish payments to be made.

Functions:

F9


Generate Dates. This brings up the Generate Dates window.



Enter each date individually in the fields provided. There is no need to enter them in order, as they will be sorted automatically.



Press **F9=Generate Dates** to bring up the Generate Dates Window to generate the dates automatically.



Start Date For The Sequence

Number Of Dates To Generate

Last Day In Each Month

A Day In Each Month

Number Of Days Interval

When you have entered the generation rules you wish to use, press **Enter** to see the result on the first Maintain Schedules screen. If it is correct, select **F8=Update**.

Names and Addresses Report



31/APM

You can produce a list of all or a range of your suppliers, in alphabetical order or sequenced by supplier group, and with addresses only or including all details, by running this option.

List Supplier Names and Addresses Screen 1

Select accounts for the report, the sequence and detail level.



Select the report Names and Addresses option to display the first List Supplier Names and Addresses screen.

```
PL021          Y9 - Education Company - Y9      User FFY9      28/07/95
                                           16:00:03

List Supplier Names & Addresses

ALL Addresses in ACCOUNT CODE sequence ..... █ Please Enter '1' Against ONE
Select a RANGE of ACCOUNT CODES ..... - Report Type Only.
Sequenced by content of SUPPLIER GROUP 1..... -
Sequenced by content of SUPPLIER GROUP 2..... -
Sequenced by content of SUPPLIER GROUP 3..... -
Sequenced by content of SUPPLIER GROUP 4..... -
Sequenced by content of ALPHA SEQUENCE CODE.. -

Enter a '1' here to obtain ALL details on the Report _
Otherwise a summary report will be printed (one line per supplier).

F3=Exit (no print).

05-49  SF  MW  KS  IM  II  EDN400A  PE0079S1
```

Fields:

Account Code Seq.

To produce a report in ascending account number sequence, enter a 1 in this entry field.

Account Number Range Select

1 - To enable the selection of a range of accounts for which the report is to be produced.

Supplier Group 1

1 - To sequence the report by the contents of the supplier group 1 code.

Supplier Group 2

1 - To sequence the report by the contents of the supplier group 2 code.

Supplier Group 3

1 - To sequence the report by the contents of the supplier group 3 code.

Supplier Group 4

1 - To sequence the report by the contents of the supplier group 4 code.

Alpha Sequence Select

1 - Sequence the report by the contents of the supplier alpha search entry, as found on the supplier maintenance screen.

Summary Or Detailed Report Select

Either a detailed report may be produced showing the full name and address details of the supplier, or a summary report showing only the supplier name and first line of the address. To obtain a detailed report, enter a 1 in this field.

List Supplier Names and Addresses Screen 2

Specify the range of accounts to be included in the report.



If on the previous screen you entered 1 in the Select A Range Of Account Codes field, the second List Supplier Names and Addresses screen displays. This enables you to specify the range required.

Fields:

Starting Account Number

Enter the starting account code from which the report is to commence. Leave this field blank to commence the report at the lowest defined account code.

Ending Account Number

Enter the ending account code at which the report is to end. Leave this field blank to end the report at the highest defined account code.



Press Enter to submit the report.

Despatch Addresses Report



32/APM

You can produce a list of despatch addresses for your suppliers by entering details in the same way as for the Names and Addresses report.

List Supplier Shipping Addresses Screen 1

Select accounts for the report, the sequence and detail level.



Select the report Despatch Addresses option to see the first List Supplier Shipping Addresses screen.

```
PL021          Y9 - Education Company - Y9      User FFY9      28/07/95
                                           16:01:05

List Supplier Shipping Addresses

ALL Addresses in ACCOUNT CODE sequence .....: _ Please Enter '1' Against ONE
Select a RANGE of ACCOUNT CODES .....: _ Report Type Only.
Sequenced by content of SUPPLIER GROUP 1.....: _
Sequenced by content of SUPPLIER GROUP 2.....: _
Sequenced by content of SUPPLIER GROUP 3.....: _
Sequenced by content of SUPPLIER GROUP 4.....: _
Sequenced by content of ALPHA SEQUENCE CODE.: _

Enter a '1' here to obtain ALL details on the Report _
Otherwise a summary report will be printed (one line per supplier).

F3=Exit (no print).

05-49      SF      MW      KS      IM      II      EDN400A      PE0079S1
```

Fields:

Account Code Seq.

1 - To produce a report in ascending account number sequence.

Account Number Range Select

1 - To enable the selection of a range of accounts for which the report is to be produced.

Supplier Group 1

1 - To sequence the report by the contents of the supplier group 1 code.

Supplier Group 2

1 - To sequence the report by the contents of the supplier group 2 code.

Supplier Group 3

1 - To sequence the report by the contents of the supplier group 3 code.

Supplier Group 4

1 - To sequence the report by the contents of the supplier group 4 code.

Alpha Sequence Select

1 - To sequence the report by the contents of the supplier alpha search entry, as found on the supplier maintenance screen.

Summary Or Detailed Report Select

Either a detailed report may be produced showing the full name and address details of the supplier, or a summary report showing only the supplier name and first line of the address.

1 - To obtain a detailed report.



If on the previous screen you entered 1 in the Select A Range Of Account Codes field, the second List Supplier Shipping Addresses screen displays to enable you to specify the range required.

List Supplier Shipping Addresses Screen 2

Specify the range of accounts to be included in the report.



Enter 1 in the Select A Range Of Account Codes field to display this second List Supplier Shipping Addresses screen.

Fields:

Starting Account Number

Enter the starting account code from which the report is to commence. Leave this field blank to commence the report at the lowest defined account code.

Ending Account Number

Enter the ending account code at which the report is to end. Leave this field blank to end the report at the highest defined account code.

Reason Codes Report



33/APM

This option produces a full list of reason code details. No parameters need to be entered.



Select the report Reason Codes option. Press **F8** to produce a list of all the reason codes set up in Accounts Payable.

Location Codes Report



34/APM

This option produces a full list of location code details. No parameters need to be entered.



Select the report Location Codes option. Press **F8** to produce a list of all the location codes set up in Accounts Payable.

Supplier Audit Report



35/APM

The supplier audit report is a list of all additions and alterations made to your supplier details, either since the report was last run, or since a specified date. In the case of additions, the report prints all the new details. For amendments, the report prints the affected details as they appeared before the change as well as in their amended state. Suppliers flagged for deletion also appear on the report.

This report should be scheduled to run on a regular basis and checked to ensure any new or changed supplier have been maintained correctly. This also clears down the work file.



Select the Supplier Audit report option.

Fields:

Supplier Code

Enter the supplier code to produce an audit list for a specific supplier. Alternatively, leave the code blank to print the audit report for all accounts.

Date

Enter a start date from which changes are to be printed including any previously printed changes. Alternatively, leave the date blank to print all changes which have not previously been printed.



Press **Enter** to submit the report.