

-
-
-
-
-

Chapter 2

Processing



Advanced Shipping Processing

Advanced Shipping manages your shipping from building consignments through to invoicing, and encompasses the following:

- Consignment notes
- Allocation/pricing/pick note initiation/despatching
- Automated pack creation and weight calculation
- Production of advanced shipment notification (ASN) records.
- Bar-coded packing label production
- Dual level packaging
- Self billing

Build and Maintain Consignments



1/ADP

This option allows you to create new consignments and maintain existing consignments.

Consignment Maintenance Screen



Select Build and Maintain Consignments from the menu to display the Consignment Maintenance Screen.

AS200	Z1 - GB Demonstration Company	User GJBANB1	29/05/98 11:36:41
Advanced Shipping Consignment Maintenance			
Customer.....?..	_____		
Despatch date.....	0/00/00		
Consignment Stockroom.?..	__		
Item.....?..	_____		
OR			
Consignment no...?..	_____		
O/S allocation/build reqs only.. 1 (0/1)			
F3=Exit F4=Prompt F6=Add New Consignment			
MA	a	06/024	

Fields:

Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a customer. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Despatch Date

Enter the despatch date.

This prompt is designed to ensure you are aware of all New/Open consignments for the Customer, thus avoiding a situation where you set a new consignment up for a future date, unaware for instance that there is an existing consignment for the day prior to that date which could be used.

Consignment Stockroom

Enter the consignment stockroom code. This must be set up for the Customer/Delivery sequence of this consignment. This will restrict the items for inclusion on the consignment to those matching the consignment stockroom.

Item

Enter an item code or ? to display an Item Scan Window. An incomplete item name or number can be entered to search for an item. This window will only present items that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

OR



Completion of Customer and Despatch Date plus **F6=Add New Consignment** will create a new consignment and display the Consignment Header Screen in Add Mode.

Consignment Number

When this is entered, any entry in the other fields is ignored. This option will take the user in to the Consignment Header Maintenance Screen.

O/S Allocation/Build Reqs Only

This field applies to the whole of the session. Its effect is to display only customer/item requirements for the given date on the Reserve Requirements/Build Consignments Screen which are not yet fully allocated and/or built. Paging through is always allowed but if the item is entered on the selection screen, it will function as a position to.

This flag will default to 1 (yes). If the flag is set to 0 (no), all item requirements for the customer/date will be displayed, regardless of the quantities left to allocate/build.



Press **Enter** to go to the Consignment Header, or Requirements Reservation/Assign to consignment, depending upon what you have entered.

Functions:

F6

Add New Consignment. This displays the Consignment Header Screen in Add Mode.



Note: You cannot maintain a Despatched Consignment.

Reserve Requirements and Build Consignments Screen

This function is complex and involves manipulating data from a number of files simultaneously. However, you may just accept all default suggested values via **F8=Update**.

In summary, making allocations via Screen 2 Action Quantities will create/update general reservation records for the customer/item/RAN/stockroom. These records are integrated into Inventory reconciliation.

Press **Enter** from the Consignment Maintenance Screen if the O/S Allocation/Build Reqs Only field is set to 1, or select **F14=Customer Reqs** from the Consignment Header Screen.

AS210		Distribution V3 -> V3 Financials		User GJBAPH2	16/02/96
					15:01:33
Advanced Shipping Reserve Requirements & Build Consignments					
Customer	ZSJ1	000	Steve Johns		
Item	STEVE001	steve's first item			
Pallet type	B01	Pack type A01	Items per pack .. 1		
Despatch date ..	5/12/95	Item units..... EA Single of.			
Call off ref. ..					
Quantity to Ship	Shortage	Allocated unbuilt	Allocated & built	Quantity to allocate	Quantity to build
30.000	.000	.000	15.000	15.000	15.000
Stockroom		Allocated unbuilt	Allocated & built	Available	Action Quantity
01 Main stockroom		.000	15.000	999951.000	<u>15.000</u>
B1 Bens Main Stockroom		.000	.000	20.000	<u> </u>
Sel	Consignment	Status	Built Quantity	Packed Quantity	Action Quantity
-	00000011	OPEN	15.000	.000	<u>15.000</u>
-	00000012	OPEN	.000	.000	<u> </u>
1=Header 2=Simulate load 3=Confirmation parameters					
F3=Exit F8=Update F12=Cancel					
F14=Previous item F15=Next item F16=Requirement breakdown					
15-66	SP	MW	KS	IM	II KENB20A PET007S1

Fields:

Part 1 - Requirement Summary

Quantity To Ship

Total requirement quantity less despatches already made, (Inventory Issue Units of Measure).

Each requirement will accumulate for an individual item unless RAN processing or unique reference numbers applies, in which case each call off is displayed as an individual requirement. The RAN reference in the display information portion of the screen will only display where applicable.

A breakdown of this requirement is displayed upon pressing **F16=Requirement Breakdown**.

Shortage

If Quantity to ship less total allocated (built + unbuilt) is greater than the total available quantity, the shortage difference will be displayed in red!

Allocated Unbuilt

Total allocated quantity for that customer requirement.

Allocated & Built

Total quantity assigned to consignments.

Quantity To Allocate

Quantity to ship less allocated & built plus allocated unbuilt.

Quantity To Build

Quantity to ship less allocated & built.

Part 2 - Allocation Details

Stockroom

Listed in sequence from the stockroom OR delivery profile(s) attached to the relevant contract(s).

Allocated Unbuilt

Total allocated quantity for this customer/item/RAN/stockroom.

Allocated Built

Total pick quantity for this customer/item/stockroom up to and including the specified despatch date.

Available

Total available stock at that stockroom for that item.

Action Qty

Amount to allocate/de-allocate for the requirement in Part 1 against the selected stockroom. The system will allocate against stock.

Defaults to Quantity to Allocate (Part 1) or total available - whichever is lower - against each stockroom in sequence.



Note: This quantity must be reduced to nearest complete pack where the Pack Rounding field is set to 1 on the AS Contract Header.

Part 3 - Consignment Details

Select

The following options are available:

- 1 - Moves to Consignment Header Maintenance - Amend Mode.
- 2 - Moves to Simulate Load.
- 3 - Moves to Confirmation Parameters.

Consignment

All non-confirmed consignments for that customer/despatch date are listed.

Status

Consignment Status codes are as follows :

NEW - New Consignment.

OPEN - Contains Requirements.

CONF - Confirmed.

Built Quantity

Quantity planned to be despatched in this consignment for the customer/item/despatch date.

Packed Quantity

This field is reserved for future use.

Action Quantity

Quantity of allocations to be assigned/de-assigned to that particular consignment. If Lot Allocation Policy is 01 on the Advanced Shipping Company Profile, you will be forced to allocate lot number.

This field will default to Allocated Unbuilt and Screen 2 Action Quantity and suggest against the most recent consignment.



Press **F8=Update** to update the files.

Functions:



*Note: Upon using the F3/F12/F14/F15/ function keys or Option 3, if you have not already done so, you will be reminded to press **F8** and update any screen changes to allocations/ assignments prior to moving on to other screens.*

F6

Displays the Consignment Header Screen in Add Mode.

F14

Displays details for previous item with outstanding requirements for same customer/despatch date.

F15

Displays details for next item with outstanding requirements for same customer/despatch date.

F16

Displays Breakdown of Requirements. The individual requirement date(s) and quantity(s) will be displayed.



Note: If the Create Pack Details field is set to 1 on the Customer Master File, the program will check that a customer/item/pack/pallet record exists upon entering this screen. If not an appropriate message will be displayed and the Action Quantity fields will be input inhibited.

Consignment Header Screen (F6)



Select **F6=Add New Consignment** on the Consignment Maintenance Selection Screen, or press **Enter** from Consignment Maintenance Screen.

AS205	Z1 - GB Demonstration Company	User GBJBA1MS	15/10/97
Advanced Shipping Consignment Header		*** AMEND MODE ***	
Consignment number.. 00000072			
Customer..... RCMC	001	Costello Motor Supplies North	
		10 Bolton Road	
Mode of transport.....?	5	Post	
Despatch date.....	6/01/96	Despatch time..... 0:00	
Est. arrival date...	8/01/96	Est. arrival time.. 0:00	
Consignment Stockroom.?	—		
Supplier code.....			
Plant number.....?			
Final delivery point.?			
Additional dest. code.?			
Freight forwarder.....?			
Carrier code.....?	BL1	Blakes of Loxley PLC	
Vehicle registration....			
Trailer reference.....			
F3=Exit F4=Prompt F8=Update F10=Confirm parameters F11=Cancel consignment F12=Previous F14=Customer requirements F15=Item summary			
5-46	SR	MW	KS CL IM DM II STUD140 KB PET178S1
Ready	R:05 C:046	ID:a	LU: NUM

Fields:

Customer

Customer details will display from those previously entered.



*Note: In ADD Mode Consignment Number & Status will assigned upon screen update via **F8=Update**.*

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Despatch Date

The system defaults to the value previously entered and can be amended.

Despatch Time

The system defaults to the customer default (optional), and can be amended.

Est. Arrival Date

Enter the estimated arrival date for this consignment.

Est. Arrival Time

Enter the estimated arrival time for this consignment.

Consignment Stockroom

Enter the consignment stockroom code when the customer receives consignment stock. The code entered must exist for the customer number and delivery sequence.

When a value is entered here, then only those items that exist on contracts with a matching consignment stockroom code will be accessible to be shipped against.

Supplier Code

The system displays the value from Customer Defaults.

Plant Number

Enter a valid plant number. This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Enter a valid final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Destination

Enter a valid additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

Enter a valid freight forwarder code. This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Carrier Code

Enter a valid carrier code. This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Vehicle Registration

Enter the vehicle registration number transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.

ASN Map Sequence & 856 Hierarchical Level

Enter the hierarchical level sequence code.

This field is displayed when the customer has been set up to send 856 ASNs. The default code defined on the Customer Defaults ASN And Pack Details Screen in the maintenance section is displayed. It can be overridden to the allowed values for this customer.



Press **Enter** to validate & redisplay the screen.

Functions:



*Note: In ADD Mode the Function Keys are restricted to **F3**, **F4**, **F8**, **F12** and **F14**.*



*Note: Function keys other than **F8**, **F11** and **F4** will warn the user if they have made amendments to the screen but not saved them via **F8=Update**.*

F8

Creates/Maintains Consignment Header record

F10

Displays Confirmation Parameters Screen.

F11

Deletes the consignment. This function will only be possible for consignments set to a status 'new' i.e. those which have no requirements attached.

F14

Displays Reserve Requirements/Build Consignments Screen with the first relevant Quantity to Ship for that customer/date. This key is only enabled where this screen has not been accessed from Reserve Requirements/Build Consignments Screen to avoid recursive calls.

F15

Displays the Item Summary Screen.

Breakdown of Requirements Window (F16)

This window displays the underlying requirement records which make up the total quantity to ship. The records will be displayed in date/time sequence and are display only.



Select **F16=Requirement Breakdown** from the Reserve Requirements/Build Consignments Screen to display the Breakdown of Requirements Window.

```
AS210          Distribution V3 -> V3 Financials    User GJBAPH2    16/02/96
                                                    15:01:33

Advanced Shipping Reserve Requirements & Build Consignments
Customer ..... ZSJ1          000          Steve Johns

Breakdown of Requirements

Shipment Shipmt Contract RAN/Call Off Reference      Outstanding
Date      Time                                     Requirement
30/11/95                                     TAG1          10.000
30/11/95                                     TAG2          5.000
  2/12/95                                     TAG2          5.000
                                     SJ1-1
                                     SJ1-2

F12=Previous

Sel  Consignment      Status      Built      Packed      Action
      Quantity      Quantity      Quantity
-      00000011      OPEN      15.000      .000      15.000
-      00000012      OPEN      .000      .000
1=Header 2=Simulate load 3=Confirmation parameters
F3=Exit  F8=Update  F12=Cancel
F14=Previous item F15=Next item F16=Requirement breakdown
15-66  SP      MW      KS      IM      II  KENB20A  PET087S1
```

Consignment Item Summary Screen (F15)

It is accessible for outstanding consignments only. It displays previously entered header information plus details from the item records which have this consignment reference.



Select **F15=Item Summary** from the Consignment Header Screen to display the Consignment Item Summary Screen.

Advanced Shipping Consignment Item Summary						
Consignment Number .. 00000011 Status .. 04 OPEN						
Customer ZSJ1 000 Steve Johns						
Supplier Code						
Despatch Date 5/12/95 Despatch Time ..						
Item	Contract	Order	Line	Stock Room	Quantity Built	Quantity Packed
STEVE001	TAG1	0012424	1	01	10	0
STEVE001	TAG2	0012424	2	01	5	0
F3=Exit F12=Previous F15=Expand/Summary						
01-02 SF MW KS IM II KENB20A PET007S1						

Functions:

F15

Toggles between displaying reference line or summary details only.

Lot Allocation Window

This screen is accessed either via the Allocate/Build Screen where Lot Allocation Policy '01' is in force.

This is the standard SOP Lot Allocation Window and is described fully in the SOP Product Information.



Note: Lot Allocation Policy is defined on the Advanced Shipping company profile and has the following values:

'01' - Allocated during consignment maintenance

'02' - Automatically allocated by warehousing where appropriate or during consignment maintenance where not

'03' - Allocated at confirm despatch.

Consignment Confirmation Parameters Screen (F10)

The function of this screen is to check the status of a consignment to ascertain what, if any, actions are outstanding; and to allow certain other actions to be triggered. When all outstanding actions have been completed, 'Confirmation of Despatch' of the consignment will be allowed. Record locking will be used to ensure the consignment can not be updated elsewhere.



Select **F10=Confirm Params** from the Consignment Header Screen to display the Consignment Confirmation Parameters Screen.

```
AS230          Distribution V3 -> V3 Financials    User GJBAPH2    16/02/96
                                                    15:06:37

Advanced Shipping Consignment Confirmation Parameters

Consignment number... 00000011      Status... 04 OPEN
Customer..... ZSJ1      000      Turnpick House

Despatch date..... 5/12/95      Despatch time.. 0:00

-----
Actions required for this consignment:

Pick note print..... 2

Consignment confirm despatch... 1

-----
0=Some outstanding 1=Process outstanding 2=None outstanding
F3=Exit F5=Refresh F8=Update F12=Previous

17-35  SF  MW  KS  IM  II  KENB20A  PET087S1
```

Only 'Actions' relevant to this consignment will be displayed, see the text below. The indicator against each action type will denote :

0 - Some actions are outstanding for the consignment.

1 - Some actions are outstanding for the consignment & will be triggered via **F8=Update** from this screen.

2 - All of this type of action for this consignment has been completed.

Actions involving Warehousing cannot be set to 1; they must be processed elsewhere. The indicator field is input inhibited in these cases. Those which can be triggered from this screen default to 1, (except Confirm Consignment where other actions are outstanding), but you can change this before pressing **F8**. The final Consignment Confirm Despatch field defaults to 0 until all outstanding actions are complete (and display 2). If the field is set to 1 whilst other actions are outstanding, you will only be able to confirm individual pick notes and not the entire consignment.

Consignment Action Types:

- Pick Note Print.

- Warehousing Pick Documentation.
- Warehousing Confirm Pick/Despatch.
- Consignment Confirm Despatch.



Press **F8=Update**.

Functions:

F5

Re-validates screen, re-assesses the outstanding actions and re-displays screen.

F8

Processes those actions set to 1.

Simulate Consignment Load Screen (Option 2)

Access to this screen is prohibited if the flag Create Pack Details is set to 'No' on the Customer defaults.



Enter option 2 against a consignment on the Reserve Requirements/Build Consignments Screen to display the Simulate Consignment Load Screen.

```

AS214          Distribution V3 -> V3 Financials    User GJBAPH2    16/02/96
                                                    15:19:11

Advanced Shipping Simulate Consignment Load

Consignment Number... 000000011          Status .. 04 OPEN
Customer..... ZSJ1          000          Steve Johns
Supplier Code.....
Item..... STEVE001          Despatch Date... 5/12/95
                               Despatch Time...

Suggested Action Quantity to build : 15.000 EA
Pallet  Pack  Packs/  Layers/  Units/  Number  Number  Dummy
Type    Type  Layer   Pallet   Pack    Pallets  Packs   Packs
B01     A01    1       1        1       15      15      0

Consignment      Pallet  Number      Gross UoM      Volume UoM
Totals           Type                    Weight
Exclusive        B01      15      168.000      900.000

Inclusive        B01      15      168.000      900.000
Simulated Totals      30      336.000      1800.000

F3=Exit  F8=Accept Action Quantity  F12=Previous

10-39  SF  MW  KS  IM  II  KENB20A  PET007S1
  
```

Fields:

Suggested Action Quantity To Build

Default to the action quantity against the consignment on Reserve Requirements/Build Consignments Screen. This may be overridden to show the result of including this quantity on the consignment.



The following fields are displayed/calculated from the fields on the relevant customer/item/pack/pallet record:

Pallet Type

This is the defined pallet type for this customer/item relationship.

Pack Type

This is the defined pack type for this customer/item relationship.

Packs/Layer

The number of packs on each layer of the pallet.

Layers/Pallet

The number of layers on the pallet.

Units/Pack

The number of items in each pack.

Number Pallets

The number of pallets calculated for this consignment. (Inclusive pallets only).

Number Packs

The number of packs calculated for this consignment. (Inclusive pallets only).

Dummy Packs

The number of empty packs generated from the calculation of this consignment. This will only show a value if the system has been asked to produce complete layers only, and dummy packs are to be created to complete a pallet layer. (Inclusive pallets only).

Odd Packs

Odd packs will only be displayed if odd packs are required and complete layers are not.



Warning: This simulation routine will NOT attempt to combine part pallets, or pallets with dummy packs on, or odd packs which can now go on to part pallets. It will just add what is required for the new quantity onto new pallets

Consignment Totals

This section of the display shows the exclusive and inclusive values calculated for the suggested action quantity to build.

The exclusive details show the pallets required for items currently built into the consignment.

The inclusive details identify the additional pallet/pack requirements if the action quantity for the item was built onto the consignment.



When you press **Enter** it validates and calculates the result of load simulation and then redisplay the screen showing the newly calculated values.

Functions:

F8

Updates the relevant action Quantity from the simulation, updating the Reserve Requirements/Build Consignments Screen accordingly.

Consignment Decreases Screen

This screen is displayed during the update process of the Reserve Requirements/Build Consignments Screen for each negative Consignment Action Quantity in Screen 3. If the system can determine where to decrease (i.e. in the normal situation where there is only one stockroom to consider), this will be actioned automatically.

Input fields will be protected for warehouse controlled picking lines, and cannot be cancelled using this process.

For non-warehouse pick lines, suggested reductions will work up from the bottom of the list, using up all or part of the built quantities until either the entire negative quantity has been satisfied or the list has been exhausted. (As the validation on the Reserve Requirements/Build Consignments Screen prevents a total quantity which would deplete warehouse picking lines, the total negative quantity will be satisfied).



Note: Where the Pack Rounding flag is set to on, round down suggested quantities to exact multiples of Items per Pack.

You will then be able to amend the suggested quantities/flags.

Functions:

F8

Updates underlying files for this consignment reduction.

Consignment Confirm Despatch



2/ADP

Use this option to confirm despatch of all non-warehousing items attached to a consignment. Warehousing Confirm Pick/Confirm Despatch must take place for any warehouse controlled items attached to the consignment before the total consignment can be confirmed.

Confirming the consignment as complete prompts for pack and pallet details where required; and lets you override calculated weight/volume totals, create consignment note details, and update the status on the consignment header.

Confirmation of Despatch Screen



Select the Consignment Confirm Despatch option from the menu to display the Confirmation Of Despatch Screen.

```
AS305          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    15:47:50
Advanced Shipping Confirmation of Despatch

Customer.....?..  _____
Despatch date.....  0/00/00  _____

OR

Consignment no...?..  _____

F3=Exit  F4=Prompt

06-24    SP    MW    KS    IM    II    KENB20A    PET087S1
```

Fields:

Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a customer. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Despatch Date

Enter the despatch date.



Note: Using both Customer and Despatch Date will return any consignments for that customer on that date.

OR

Consignment No

Enter the consignment number. If you make an entry in this field, the other fields are ignored.



Press **Enter** to display the next screen.

Consignment Confirmation Of Despatch Screen



You can access this screen by selecting the Build and Maintain Consignments function (from the Confirmation Parameters Screen) or by selecting the Confirm Consignment Despatch function, after completing the selection screen with a valid consignment number.



*Note: If accessed via the separate Consignment Confirm Despatch menu option, this function will prohibit **F21=Confirm Consignment** if either there are outstanding actions or some picking instructions have not been confirmed.*

This screen lists the stockrooms associated with a consignment. You can amend the despatch date, time and method, and confirm non-warehouse pick notes.

When all pick notes on a consignment have been completed, the consignment itself may be confirmed via **F21=Confirm Consignment**.

AS300		Distribution V3 -> V3 Financials		User	GBJBAPH2	16/02/96
						15:49:48
Advanced Shipping Consignment Confirmation of Despatch						
Customer.....	ZSJ1	000	Steve Johns			
			Turnpick House			
Consignment Number..	00000011		Status..... OPEN			
Despatch Date	5/12/95		Despatch Time....			
Despatch Method..?	1		Sea			
Sel	Stock	Stockroom	W'house	Status		
	Room	Description	Control			
-	01	Main stockroom	N	Outstanding		
1=Confirm in Full 2=Confirm and Amend						
F3=Exit F4=Prompt F5=Refresh F8=Process Selections F12=Previous						
F15=Select all '1' F16=Select all '2'						
07-23 SF MW KS IM II KENB20A PET007S1						

Fields:

Despatch Date

This field defaults from the original consignment values but may be overridden.

Despatch Time

This field defaults from the original consignment values but may be overridden.

Despatch Method

This field defaults from the original consignment values but may be overridden.

Sel

Selection field. Enter one of the following options:

- 1 - Confirm in full. this method of confirming does not display amend screens, so you cannot amend values. Where lot details are required the Confirmation Screen is displayed as if you had entered 2 against the pick note.
- 2 - Confirm and amend. This method of confirming displays amend screens, so you can amend values.

This field is not available for:

- Warehouses
- Stockrooms which have already had all their picking instructions confirmed
- Stockrooms whose underlying picking details are cancelled
- Pick notes which have not yet been printed or require reprinting.

Add Charges

This is only be displayed if Invoice Consolidation Policy is set to one per consignment/contract or one per consignment/contract/RAN.

Charges may be added at consignment level via the option on this screen - **F21=Confirm Consignment** will call the Confirm Consignment Charges Screen, before moving on to Confirm Consignment. The Add Charges flag can only be set when **F21=Confirm Consignment** is enabled.



Press **F8=Process Selections** to continue.

Functions:

F5

Refreshes the display : changes the text against the stockroom, i.e. from outstanding to confirmed where applicable.

F8

Processes selection options 1 & 2 : Confirms pick notes with and without amendment interactively. As much of the processing may be occurring here with minimal intervention, a message will remain on this screen to the effect of 'Despatch Confirmation in Progress', until all selections have been processed.

Those pick notes selected with a 2 will link in to the detailed confirmation screen. Those selected with a 1 will be fully confirmed without displaying the other screen unless lot details are outstanding.

F15

This automatically puts 1 in the selection field of each pick note which can be confirmed from here.

F16

This automatically puts 2 in the selection field of each pick note which can be confirmed from here.

F21

Confirm Consignment. This confirms the despatch. If the pack and pallet details already exist, you will see the Consignment Totals Screen, otherwise this function will create pack and pallet details. If there are unprinted shipping labels still on the system for this customer and consignment, a window asks you whether you wish to print them or not. If you do, you are taken to the relevant screen, otherwise the despatch is confirmed.

Confirm Lot Details Screen

-  If lot details are outstanding when you select **F8=Process Selection** on the Consignment Confirmation of Despatch Screen, the Confirm Lot Details Screen is displayed.

```

AS350          Distribution V3 -> V3 Financials      User GBJBAPH2  16/02/96
                                                    15:54:35
Advanced Shipping Consignment Confirmation of Despatch

Customer..... ZSJ1      000      Steve Johns
                                           Turnpick House
Consignment Number . 00000011      Revision.....
Despatch Date ..... 5/12/95      Despatch Time ..... 0:00
Stockroom ..... 01

Line  Item/Description/  UOM  Quantity to  Quantity
     Call Off Ref.      Ship  Despatched
001  STEVE001           EA    5.000      .000
     steve's first item
     SJ1-1

F3=Exit  F4=Prompt  F12=Previous  F13=Confirm despatch

13-49    SF      MW      KS      IM      II  KENB20A  PET007S1
  
```

-  *Note: The line numbers on this screen may not correspond to pick note line numbers as this screen is displaying picking instructions for a particular Consignment/Stockroom/Revision sequence which may refer to more than one file.*

-  Press **Enter** to validate the screen and return multiple lot details.

Functions:

F13

Confirms the quantities despatched and lot details. Where lot details are required but not entered, this function key will highlight the line in error and force entry.

Confirm Consignment Charges Screen

This screen will function as the corresponding screen within Advanced Order Entry functions.

A brief explanation of the charges function is provided here, if you require a full explanation, please refer to the Advanced Order Entry Product Information.

Despatch date, time and method are not maintained using this screen.

A charge code from the SUNC miscellaneous charge codes on the description file will be entered by the system. The amount and VAT code from the file will be presented but may be overridden. Up to three charges can be added to the consignment.



Enter a code, press the **Enter** key again to retrieve the amount and VAT details for the selected charge.



Note: If the charge code is incorrect or wrongly selected it can be removed by blanking the code value.



Warning: It is assumed that contract pricing is set in the currency of the customer and that it will be converted to base using the default currency rate code on the customer sales details profile.

Functions:

F13

This will update changes before moving on to Confirm Consignment - Load Totals or Confirm Consignment Confirmation Window, as appropriate (as if **F21=Confirm Consignment** were selected without the charges flag being set to Yes).

Consignment Totals Screen

If pack/pallet details are not necessary for this consignment you will bypass this screen and go straight to the Confirm Consignment Confirmation Window. The confirm consignment function needs to perform the following tasks :

- If required create pallet/pack details for the consignment and allow the user to verify and optionally amend them.
- Allow you to override total weight and volume calculations for the consignment.
- Generate a consignment note.
- Update the status of the consignment to 'confirmed'.

Upon entering this screen, the system calculates and creates all pack and pallet records (into a work file) for the consignment. It then summarises consignment pack and pallet totals and allows user overrides of total figures. All calculated values are held in temporary work files - no commitment takes place until the consignment is finally confirmed.

Fields:

Pallet Type

The pallet type for this contract is taken from the customer/item/pack/pallet details file.

No. Of Pallets

The calculated number is based on the contract and customer/item/pack/pallet details file.

No Of Packs

The calculated number is based on the contract and customer/item/pack/pallet details file.

Net Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Gross Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Volume

The calculated number is based on the contract and customer/item/pack/pallet details file.

Calc Totals

The system calculated totals for this consignment.

Actual Totals

Defaulted to the system calculated values but may be overridden.

Functions:

F15

Displays consignment pack and pallets.

F21

Carries out final confirmation process on the consignment.



Warning: The F21=Confirm Consignment key is not available until the Confirm Despatch Updates sleeper program is run. See Sleeper Processes.

Consignment Packs and Pallets Screen (F15)



This screen is accessed by selecting **F15=Consignment Pack and Pallets** from the Consignment Totals Screen.

You can only access this screen where pack details have been calculated. This screen displays the system calculated pack/pallet details and allows you to amend them. It will allow you to review all the pallet/pack details for a particular RAN or item/contract.

The system will display the consignment values and settings used for the calculations for this item/contract/RAN.

Fields:

Item/Contract/RAN Section

This section provides mainly memo information for aiding you when amending details.



Note: These are the only input-capable fields in this portion of the screen. This is to allow you to go straight to a known Item on the consignment and review pack/pallet details. If any details have been changed for the current item/contract/RAN it will warn you to update before moving on to the chosen item/contract/RAN.

Select

Deletes a suggested pack range. Delete a range will display a warning message.



The calculated pack range details will be displayed. The details may be amended and a unique pack mark may be added.

Pallet Ref.

This is a display only field and is the internal reference for the pallet.

Pack Range From/To

This is the internal reference(s) of the packs associated with the pallet.

Volume/Qty Per Pack

This is the volume of the pallet and the number of items each pack contains.

Pack Marks

Optionally enter a value that identifies these particular packs within the consignment.



If the entered/displayed details are correct press **F10=Confirm Item/Contract/RAN** to confirm the values for this item/contract/RAN.

Functions:

F5

Recalculates packed qty -

Sum (No. Packs in Range * Quantity Per Pack) for all ranges.

Number of Packs in Range=1 + 'To Pack' - 'From Pack'

Packed Quantity highlighted if not equal to Ship Quantity.

Redisplays if range sequence has altered.

Redisplays the last Pallet & Pack Number for this consignment.

Validates changes to date and issues any messages.

F6

Inserts an input range to set up a new record.

F10

Validates pack/pallet details for the item/contract/RAN, if validated commits the changes to the work files and displays the next item/contract/RAN on the consignment. Recalculate any weights/volumes left blank on a range, using the formulae for weights & volumes.

F13

Displays hides the Call off reference & pack marks for the pack details.

F14

Displays the previous item/contract/RAN details.



Note: Issues warning if amendments to current Item/Contract/RAN are about to be lost.

F15

Displays screen for the next item/contract/RAN.

Confirm Consignment Confirmation Window

The final Confirmation Window can be displayed over Consignment Confirmation of Despatch or Confirm Consignment - Load Totals, depending upon whether pack & pallet details are required.

A further **F21=Confirm Consignment** from here will finalise the consignment.

The following updates will take place :

- Set the consignment status on confirmed.
- Recheck all underlying records which are for RANs and set to complete regardless of whether or not the RAN requirement quantity has been fully satisfied.
- Pack and pallet details generated to the work files will be committed to the database and the weight, volume, totals information written to the database.
- Generate a consignment note.

Functions:

F21

Actions the above updates.



Warning: The F21=Confirm Consignment key is not available until the Confirm Despatch Updates sleeper program is run. See Sleeper Processes.

Fastpath Shipping



3/ADP

This option allows you to create and confirm consignments in one step and allocate requirements to existing non-confirmed consignments.

To create and confirm a consignment in two steps, use this option to create the consignment and when confirmation of the despatch is required, select the consignment from the Fastpath Confirmation option from the menu.



Select Fastpath Shipping on the menu to display the Advanced Shipping Fastpath Screen.

Advanced Shipping Fastpath Screen

This screen allows you to create new consignments and select existing non-confirmed consignments.



Select Fastpath Shipping on the menu to display the Advanced Shipping Fastpath Screen.

AS100	Z1 - GB Demonstration Company	User GBJBANB1	29/05/98 12:10:12
Advanced Shipping Fastpath			
Customer.....?..	_____		
Item.....?..	_____		
OR			
Consignment no...?..	_____		
Despatch date.....	<u>29/05/98</u>		
Despatch time.....	<u>12:10</u>		
Display individual or summarised requirements ? <u>1</u> (0/1)			
F3=Exit F4=Prompt F6=Add New Consignment			
a			07/031

Fields:

Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a customer. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Item

Enter an item code or ? to display an Item Scan Window. An incomplete item name or number can be entered to search for an item. This window will only present items that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Consignment No

If this is entered, any entry in the other fields is ignored. This option will take you in to the Create Shipment Details Screen.

Despatch Date

Enter the despatch cut-off date and time. Any outstanding items to be despatched up to this date will be displayed on the Create Shipment Details Screen.

Despatch Time

Enter the despatch cut-off time.

Display Individual Or Summarised Requirements

Item requirements make up the total quantity to be shipped and are displayed in the Create Shipment Details Screen.

0 - Displays a breakdown of item requirements.

1 - Displays a summary of item requirements.



Press **Enter** to display the Create Shipment Details Screen.

Functions:

F6=Add New Consignments

Add New Consignment. This function displays the Consignment Header Screen which allows you to create a new consignment.

Consignment Header Screen (F6, F10)

This option allows you to create a new consignment when it is in Add Mode and allows you to make changes to existing non-confirmed consignment details when it is in Amend Mode.

-  Select **F6=Add New Consignment** on the Advanced Shipping Fastpath Screen to display the Consignment Header Screen in Add mode.
-  Select **F10=Head Maint** on the Create Shipment Details Screen to display the Consignment Header Screen in Amend mode.
-  Select **F10=Header Maintenance** on the Confirm Shipment Details Screen to display the Consignment Header Screen in Amend mode.

AS205		Version 3 Demonstration Company		User QAUT02	25/06/97
					9:16:11
Advanced Shipping Consignment Header				**** ADD MODE ****	
Consignment number.. *****					
Customer.....	CG02	000	Automotive customer number 2 !!!		
			31 Lenton Boulevard		
			Road		
Mode of transport.....?	3				
Despatch date.....	25/06/97	Despatch time..... 9:15			
Est. arrival date...	27/06/97	Est. arrival time.. 9:15			
Supplier code.....					
Plant number.....?					
Final delivery point..?	FDEL01	Final Delivery Point			
Additional dest. code..?	ADES01	ADDITIONAL ADDRS de			
Freight forwarder.....?	FFWD01	Freight Forwarder 01			
Carrier code.....?	CARR01	Transport carrier co			
Vehicle registration.....					
Trailer reference.....					
F3=Exit F4=Prompt F8=Update F12=Previous					
05-46 SF MK KS IM II EDN400A PE9106S2					

Fields:

Consignment Number

In Add Mode, the consignment number and status are assigned when the screen is updated using **F8=Update**.

Customer

Previously entered customer details are displayed.

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Despatch Date

This is displayed from previously entered information. It can be amended.

Despatch Time

This is displayed from previously entered information. It can be amended.

Est Arrival Date

Enter the estimated arrival date for this consignment.

Est Arrival Time

Enter the estimated arrival time for this consignment.

Supplier Code

The system displays the value from Customer Defaults.

Plant Number

Enter a valid plant number. This field is optional and defaults to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Enter a valid final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Dest Code

Enter a valid additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

Enter a valid freight forwarder code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Carrier Code

Enter a valid carrier code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Vehicle Registration

Enter an identifier for the vehicle that is transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.



Press **Enter** to validate the data you have entered.



Select **F8=Update** to update the data you have entered and display the Create Shipment Details Screen.

Create Shipment Details Screen

This screen displays a list of items with outstanding quantities to be supplied to the customer against a consignment stockroom prior to the despatch date entered in the Advanced Shipping Fastpath Screen. Select the required item/s and specify the quantity to be shipped.



Press **Enter** on the Advanced Shipping Fastpath Screen to display the Create Shipment Details Screen.



Select **F8=Update** on the Consignment Header Screen to update the data and display the Create Shipment Details Screen.

AS110	Z1 - GB Demonstration Company	User GBJBA1MS	15/10/97 14:16:54
Advanced Shipping Create Shipment Details NEW			
Customer	: ABC01 000	ABC Holiday Shop Ltd 24, Carrington St,	
Despatch date	: 20/06/97	Consignment	: 00000290 Stockroom:
Despatch time	: 14:17	K	
Sel Item	Contract	Required Qty	Available Qty
■ CARBODY	0000110	10	1603
111111789012345678901234567890123456			
1=Confirm Details 2=Text 3=Line Enquiry			
F3=Exit F10=Header maintenance F12=Previous F15=Summary requirements			
F24=More keys			
11-3 SA MW KS CL IM DM II STUD140 KB PET178S1			
Ready R:11 C:003 ID:a LU: NUM			

Fields:

Sel

Select. Enter the required option:

1 - Confirm Details. To select an item to be actioned when **F8=Confirm Planned Despatch** or **F9=Confirm Despatch** are selected.

2 - Text. Displays the Text Window to allow you to add additional text to the screen. The text is displayed on the printed shipping documentation.

3 - Line Enquiry. Displays the Breakdown Of Requirements Window which details the total quantity of item requirements to be shipped.

Confirm Qty

Enter the quantity to be despatched. This value cannot be a negative figure as quantities can only be added to a consignment.

Functions:

F8

Confirm Planned Despatch. This function allows you to confirm shipment details. To add packing details to the consignment, enter 1 in the Add Pack Details Window. For more information, refer to the Fastpath Packing Details Screen.

If you are using the detailed packing method, or your customer needs shipping labels printed, then you will be taken into the Confirm Packaging And Labels option.

F9

Confirm Despatch. This function allows you to confirm shipment details and despatch in one step. To add packing details to the consignment, enter 1 in the Add Pack Details Window. For more information, refer to the Fastpath Packing Details Screen.

If you are using the detailed packing method, or your customer needs shipping labels printed, then you will be taken into the Confirm Packaging And Labels option.

F10

Header Maint. Select this function to display the Consignment Header Screen in Amend mode. For more information, see the Consignment Header Screen section.

F13

Add Charges. This function allows you to add the consignment charges.

F15

Summary/Individual Requirements. This function allows you to toggle the list of requirements between individual and summary mode.

F16

Select all '1'. Automatically applies option 1 to all items on the screen which are then activated when **F8=Confirm Planned Despatch** is selected.

F21

Address Override. This function displays the Name And Address Maintenance Screen where you can amend customer delivery addresses.

Fastpath Packing Details Screen (Option 1)

This option allows you to add single level packing details to a consignment before you confirm despatch. Specify the container type and quantity.



Enter 1 in the Sel field and select **F8=Confirm Planned Despatch** or **F9=Confirm Despatch** on the Create Shipment Details Screen to display the Add Pack Details Window. Enter 1 to display the Fastpath Packing Details Screen.

AS140	Version 3 Demonstration Company		User QAAUT01	1/07/97
16:24:13				
Advanced Shipping - Fastpath Packing Details				
Customer	CG02	000	Automotive customer	
			31 Lenton Boulevard	
Despatch Date :	24/06/97		Consignment : 00000005	
Despatch Time :	9:31		3	
Sel Pack	Quantity	Tare Weight	Volume	Charge or
Type				Deposit
				Return
				(0/1)
4=Delete				
F3=Exit F6=Add F8=Update F12=Previous F13=Add Charges				
01-02	SP	MK	KS	IM II EDN400A PE9106S2

Fields:

Sel

Select. The following option is available:

4 - Delete. Deletes a pack type.

Pack Type

Enter pack type. **F6=Add** displays a list of pack types available.

Quantity

Enter quantity. This is displayed from the Add Packing Details Window when **F6=Add** is used.

Tare Weight

This is displayed when a pack type is entered. It can be amended.

Volume

This is displayed when a pack type is entered. It can be amended.

Charge Or Deposit

This is displayed when a pack type is entered. It can be amended.

Return (0/1)

Enter one of the following options:

0 - No. The pack is not returnable.

1 - Yes. The pack type is returnable.



Select **F8=Update** to confirm the data you have entered.

Functions:

F6

Add. This function displays the Add Packing Detail Window showing a list of pack types. Select the required pack type and enter the quantity.

F13

Add Charges. This function allows you to add consignment charges.

Consignment Charges Screen (F13)

This function allows you to add any additional consignment and shipping level charges.



Select **F13=Add Charges** on the Create Shipment Details Screen, the Confirm Shipment Details Screen or the Packing Details Screen to display the Consignment Charges Screen.

AS360	Version 3 Demonstration Company	User QAUT01	2/07/97
14:23:39			
Advanced Shipping Consignment Charges			
Customer.....	CG02	000	Automotive customer number 2 !!!
			31 Lenton Boulevard
Consignment Number..	00000014		Revision.....
Despatch Date.....	2/07/97		Despatch Time.... 14:16
Despatch Method.....			
Charge Description	Prime amount	VAT	VAT
code(?)		ode(?)	rate
—	—	—	—
—	—	—	—
—	—	—	—
Charge Summary			
Charge total.....			
Charge VAT total....			
Charge grand total..			
F3=Exit F4=Prompt F12=Previous F13=Confirm charges			
14-04	SF	MK	KS IM II EDN400A PE9106S2

Fields:

Charge Code

Enter the charge code.

Prime Amount

Enter the charge value.

VAT Code

Enter the VAT code.



Select **F13=Confirm Charges** to display the previous screen.

Functions:

F13

Confirm Charges. This function confirms the details you have entered and displays the previous screen.

Text Window (Option 2)

Additional line level text can be added to each consignment. The text is displayed on the printed shipping documentation.



Enter 2 in the Sel field on the Create Shipment Details Screen or the Confirm Shipment Details Screen to display the Text Window.

AS110 Version 3 Demonstration Company User QAAUT01 3/07/97 14:26:57

Advanced Shipping Create Shipment Details NEW

Customer : CG02 000 Automotive customer number 2 !!!
31 Lenton Boulevard
Despatch date : 2/07/97 Consignment : 00000014
Despatch time : 14:16 TESTING

Sel Item Contract Re
2 CGQA1 0000002
CG QA Item1

Lin External Text

1	
2	
3	
4	
5	
6	

Position to ___ Insert ___ after ___
Delete ___ from ___

F5=Refresh F8=Update F12=Previous

1=Confirm Details 2=Text 3=Line Enquiry
F3=Exit F8=Confirm planned despatch F9=Confirm despatch F10=Header Maint.
F12=Previous F13=Add charges F15=Individual requirements F24=More keys
12-42 SF MK KS IM II EDN400A PE9106S2

Fields:

External Text

Enter text on each line as required.

Position To

Enter the line to be displayed at the top of the screen.

Insert

Enter the number of blank lines to be inserted, and the line number after which they should be inserted.

Delete

Enter the number of lines to be deleted, and the line number from which you want to start.



Select **F8=Update** to update the data you have entered and display the Create Shipment Details Screen.

Breakdown Of Requirements Window (Option 3)

This window displays the requirement records which make up the total quantity to ship for each item. The records are displayed in date/time sequence.



Enter 3 in the Sel field on the Create Shipment Details Screen to display the Breakdown Of Requirements Window.

PS110 Version 3 Demonstration Company User QAUT01 3/07/97 14:28:21

Advanced Shipping Create Shipment Details NEW

Breakdown of Requirements				
Shipment Date	Shipmt Time	Contract	RAN/Call Off Reference	Outstanding Requirement
10/06/97		0000002	REF-120697-120	33.000
12/06/97		0000002	REF-150697-120 (SUN->THU ?)	120.000
13/06/97		0000002	REF-170697-120	120.000

F12=Previous

1=Confirm Details 2=Text 3=Line Enquiry
F3=Exit F8=Confirm planned despatch F9=Confirm despatch F10=Header Maint.
F12=Previous F13=Add charges F15=Individual requirements F24=More keys
01-02 SF MK KS IM II EDN400A PE9106S2

Fields:

For each shipment the following fields are displayed and are for your information only:

Shipment Date

Shipmt Time

Contract

RAN/Call off Reference

Outstanding Requirement



Select **F12=Previous** to display the Create Shipment Details Screen.

Name And Address Maintenance Screen (F21)

This screen allows you to make any necessary changes to the customer delivery address and contact details.



Select **F21=Address Override** from the Create Shipment Details or the Confirm Shipment Details Screen to display the Name And Address Maintenance Screen.

AS425		Z1 - GB Demonstration Company		User GBJBA1MS		7/07/97	
						13:21:50	
Name and Address Maintenance							
Consignment		00000290		K			
Despatch Date		20/06/97		Despatch Time		14:17	
Type code.....		CGEE		Consignee (Delivery Customer)			
Address code.....		FORDDAY					
Name.....		Ford Motor Co DAVENTRY					
Address line 1.....		room 12/207					
Address line 2.....							
Address line 3.....							
Address line 4.....							
Address line 5.....							
Post code.....				Country Code?.			
Telephone number....				Extension number...			
Fax number.....				Internal ID.....			
Telex number.....				Teletext number....			
Contact name.....							
Department code.....							
Comments.....							
F3=Exit F4=Prompt F12=Previous							
08-23		SP		MK		KS	
				IM		II EDN400A PET149S2	

Fields:

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Address Line 5

Enter the fifth line of the required address.

Post Code

Enter the post code.

Country Code

Enter the country code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the required contact name.

Department Code

Enter the department code for the contact.

Comments

This is a free format field. Enter any additional information



Press **Enter** to display the previous screen.

Fastpath Confirmation



4/ADP

This option allows you to confirm consignments or amend quantities against consignments created using the Fastpath Shipping option. When you confirm a consignment, inventory values are updated and invoice records are created. The consignment now has a 'sent' status.



Select Fastpath Confirmation on the menu to display the Fastpath Confirm Despatch Screen.

Fastpath Confirm Despatch Screen

When the initial screen is first displayed, a list of all non-confirmed consignments is shown.



Select Fastpath Confirmation on the menu to display the Fastpath Confirm Despatch Screen.

```

AS130              Z1 - GB Demonstration Company   User GBJBA1MS   25/06/97
                                           10:06:31

Advanced Shipping Fastpath Confirm Despatch

                                Position to : Customer ....?.
                                           Consignment .??.

Sel Customer      Consignment      Desp. Date & Time
ABC01      000 Customer c01
           00000149 BIGCON149      4/06/96   :00
AC01      000 Schedule Customer
           00000234 DAILY SHIP      1/10/96   :00
JTMC      000 Jane Troth's Motor Company
           00000150 CONS150          5/06/96   :00
-          00000151 CONS151          15/06/96   :00
-          00000247 CONSIGNMENT 247  27/01/97   :00
PVANCE      000 Pickavance Truck Co.
           00000161                  19/06/96   :00
RCMC      000 Costello Motor Company
           00000061 CONS61          31/12/96   :00 +

1=Confirm in Full  2=Amend Quantities
F3=Exit  F4=Prompt F5=Refresh F8=Confirm Despatch
F14=Consignments by Item F16=Select all '1'
14-02      S2      MW      KS      IM      II EDN400A PE9106S2
  
```

Fields:

Position To Customer

Enter a customer code to display a list of non-confirmed consignments relating to a specific customer.

Position To Consignment

Enter the consignment number.

Sel

Select. The following options are available:

1 - Confirm In Full. To select a consignment to be actioned when **F8=Confirm Despatch** is selected.

2 - Amend Quantities. To display the Confirm Shipment Details Screen which allows you to amend quantities to be despatched.



Select **F8=Confirm Despatch** to confirm the despatch of consignments which have 1 in the Sel field.

Functions:

F14

Consignments By Item. Select this function to display the Consignment By Item Window. This window allows you to select a specific item which limits the displayed consignments to those containing that item.

F16

Select all '1'. This function automatically enters 1 in the Sel field of all items on the screen.

Confirm Shipment Details Screen (Option 2)

This screen allows you to amend the quantity of items to be despatched.



Enter 2 in the Sel field on the Fastpath Confirm Despatch Screen to display the Confirm Shipment Details Screen.

```

AS135                      Version 3 Demonstration Company   User QA AUT01   10/07/97
                                           15:27:19

Advanced Shipping Confirm Shipment Details

Customer      : CG02      000  Automotive customer number 2 ↑↑↑
                31 Lenton Boulevard
Despatch date : 3/07/97      Consignment : 00000017
Despatch time : 15:41                TESTING

Sel Item      Contract Despatch Qty      Confirm Qty
█ CGQA1       0000002      45              45
  CG QA Item1

1=Confirm Details  2=Text
F3=Exit  F8=Confirm despatch  F10=Header maintenance  F12=Previous
F13=Add charges  F16=Select all '1'  F21=Address override
11-03      SF      MK      KS      IM      II  EDN400A  PET149S2
  
```

Fields:

Sel

Select. The following options are available:

1 - Confirm Details. Selects an item to be actioned when **F8=Confirm Despatch** is selected.

2 - Text. Displays the text window to allow you to add additional text to the screen. For more information, refer to Text Window.

Confirm Qty

Enter the new quantity if an amendment is required.



Select **F8=Confirm Despatch** to confirm the despatch and display the Fastpath Confirm Despatch screen.

Functions

F10

Header Maintenance. For more information, see the Consignment Header Screen.

F13

Add Charges. For more information, see the Consignment Charges Screen.

F16

Select all '1'. Automatically applies option 1 to all items on the screen which are then activated when **F8=Confirm Despatch** is selected.

F21

Address Override. Displays the Name And Address Maintenance Screen where you can amend customer delivery addresses. For more information, see the Name And Address Maintenance Screen.

Consignments By Item Window (F14)

This window allows you to enter a specific item code, which limits the displayed consignments to those containing that specified item.



Select **F14=Consignments By Item** from the Fastpath Confirm Despatch Screen to display the Consignments by Item Window.

AS130		Z1 - GB Demonstration Company		User GBJBA1MS		7/07/97	
						14:44:08	
Advanced Shipping Fastpath Confirm Despatch							
				Position to : Customer?.		_____	
				Consignment .?.		_____	
Set Customer	Consignment					Desp. Date & Time	
ABC01	000 ABC Holiday Shop Ltd						
	000000149 BIGCON149					4/06/96	:00
AC01	000 Schedule Customer						
- JTMC	0	Consignments by Item				96	:00
		Item ..?.				96	:00
						96	:00
						96	:00
- PVANCE	0					97	:00
- RCMC	0	Position to Customer ...?.				96	:00
						96	:00
		F4=Prompt F12=Previous F14=All consignments				96	:00 +
1=Confirm in Full 2=Amend Quantities							
F3=Exit F4=Prompt F5=Refresh F8=Confirm Despatch							
F14=Consignments by Item F16=Select all '1'							
14-30		SF	ML	KS	IM	II	EDN400A PET149S2

Fields:

Item

Enter the item code.

Position To Customer

Enter the customer code for the customer that you want to display at the top of the list.



Press **Enter** to display Fastpath Confirm Despatch Screen.

Functions:

F14

All Consignments. This is used when you want to redisplay the Fastpath Confirm Despatch Screen listing all consignments and not just those for selected items.

ASN Maintenance And Send



5/ADP

Advance Shipping Notifications (ASNs) are electronically transmitted messages which provide advance information relating to shipments or consignments.

This option allows you to maintain, cancel or send ASNs.

ASN Maintenance And Send Screen

From this screen, you can maintain, cancel or transmit an ASN. The completed shipments are listed in customer/consignment sequence.

Transmit ASNs

This is achieved by pressing **F8=Transmit ASNs** on the ASN Maintenance And Send Screen. All ASNs with 2 in the selection field are sent.

These ASNs will sit in the system until the ASN EDI send background sleeper process is started. They will then be passed to EDI for transmission.

The process of sending an ASN is an EDI function. Details of the ASN are sent to a data queue, locking the ASN to prevent further maintenance until the send function is complete. The send function is also prohibited until any previous send has been completed.



Select ASN Maintenance And Send on the menu to display the ASN Maintenance And Send Screen.

```

AS400          Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96
                                     14:33:33
Advanced Shipping ASN Maintenance & Send

                                     Position to : Customer ....?. 
                                     Consignment .?. 
S Customer      Consignment      Desp. Date & Time Sts
IP02      001  Ian Powdrell Name IP02----->
-          00000142  Manual ASN                      1/08/96   :00 R
-  TE        001  Tracy Eastwood
-          00000143  Test consignment                  8/08/96   :00 R
-          00000144  Another test consignment           8/08/96   :00 R
-          00000145  Control consignment                 8/08/96   :00 R
-          00000146  consignment with changes           8/08/96   :00 R
-  ZDJ1      001  ZDJ1 the customer ltd
-          00000141  Woof                               10/10/97   :00 R

1=Maintain Details  2=Send ASN  4=Cancel ASN
F3=Exit  F4=Prompt  F5=Refresh  F6=Add a Manual ASN  F8=Transmit ASNs
F14=Consignments by Item  F16=Select all '2'
05-68  SF  MW  KS  IM  II  KENB20A  PET087S2
  
```

Fields:

Position To Customer

You can position the listing to a particular customer, by entering a customer code. This will start the list at the beginning of the chosen customer's consignments.



Note: If there are no 'Ready to pass to EDI' ASNs for the selected customer, the next customer with outstanding ASNs will head the display.

Position To Consignment

You can position the listing to a particular consignment, by entering a consignment number. This will start the list at the beginning of the chosen consignment.

Select

Enter an option next to a consignment to perform the following tasks:

- 1 - Display the ASN Maintenance Header Screen.
- 2 - Select a consignment for transmission to EDI.
- 4 - Cancel an ASN.



Note: If you cancel an ASN the status will be updated to Not Sent, and it will be removed from the display when next refreshed. You can resend an ASN which has a Not Sent status.



Select the option or function key to perform the task you want.

Functions:

F6

Add a manual ASN. This allows you to create an ad hoc ASN via the maintenance screens, without validating the data to underlying Schedule/Sales Order data. It is the users responsibility to ensure any necessary adjustments to Inventory/Contract cumulatives etc. are carried out.

F8

Transmit ASNs. All ASNs selected with a 2 in the selection field are transmitted via EDI.

F14

Consignments by Item. This displays the consignments by Item Window which allows you to select a specific item. The current screen will then be redisplayed with the consignments in the listing restricted to those carrying the selected item. The screen will also display the item at the top left hand side of the refreshed screen.


F16

Select all 2. This will prefill all the selection fields with a 2.

Consignments by Item Window (F14)

This window allows you to select a specific item which limits the consignments displayed to those containing that item. You can also specify a customer and address to position to when you return to the previous screen.

-  Select **F14=Consignments by Item** on the ASN Maintain and Send Selection Screen to display the Consignments by Item Window.



AS400 Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96 14:33:33

Advanced Shipping ASN Maintenance & Send

Position to : Customer?. _____
Consignment ..?. _____

S	Customer	Consignment	Consignment Name	Disp. Date & Time	Sts
IP02	001	Ian Powdrell Name IP02----->			
		00000142	Manual ASN	1/08/96	:00 R
TE	001	Tracy Eastwood			
		00000143	Test consignment	8/08/96	:00 R
					:00 R
					:00 R
					:00 R
ZDJ1	001				
					:00 R

Consignments by Item

Item ..?. _____

Position to Customer ...?. _____

F4=Prompt F12=Previous F14=All consignments

1=Maintain Details 2=Send ASN 4=Cancel ASN
F3=Exit F4=Prompt F5=Refresh F6=Add a Manual ASN F8=Transmit ASNs
F14=Consignments by Item F16=Select all '2'

14-30 SF MW KS IM II KENB20A PET087S2

Fields:

Item

Enter the item code you want to use to display consignments.

Position To Customer

Enter the customer code for the customer which you want to display at the top of the list.

Untitled

Address. Enter the address which you want to display at the top of the list.

-  Press **Enter** to redisplay the ASN Maintenance & Send Screen with the selected consignments.

Functions:

F14

All consignments. This is used when you want to redisplay the ASN Maintenance & Send Screen listing all consignments, and not just those for selected items.

ASN Maintenance Header Screen (Option 1)

This screen allows you to maintain the header details for a selected ASN.



Enter option 1 on the ASN Maintenance & Send Screen to display the ASN Maintenance Header Screen.

AS410	Z1 - GB Demonstration Company	User GBJBACHG	16/10/97 9:47:51
Advanced Shipping ASN Maintenance - Header			
Consignment number...	00000262	<u>FILE</u>	
Customer.....	CS1 000	Customer 1	
		1 High St	
Mode of transport.....?	2	Own Propulsion	
Despatch date.....	30/01/97	Despatch time.....	0:00
Est. arrival date....	30/01/97	Est. arrival time..	0:00
Supplier code.....?			
Plant number.....?			
Final delivery point..?			
Additional dest. code.?			
Freight forwarder.....?			
Carrier code.....?			
Vehicle registration....			
Trailer reference.....			
F3=Exit F4=Prompt F8=Update F10=Additional ASN Details F12=Previous F14=Weights & Totals F15=Items F21=Name & Addresses F22=ASN Text			
5-43	SA	NW KS CL IM DM II	EDN400A KB PET178S1

Fields:

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Despatch Date

Enter the date of despatch.

Despatch Time

Enter the time of despatch using the 24 hour clock.

Est Arrival Date

Enter the estimated arrival date. This date must be the same as or later than the despatch date.

Est Arrival Time

Enter the estimated arrival time using the 24 hour clock.

Supplier Code

The system displays the value from Customer Defaults, if you are in Add mode (F6), otherwise it will be returned from the consignment header.

Plant Number

Enter a valid plant number. This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Enter a valid final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Destination

Enter a valid additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

Enter a valid freight forwarder code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Carrier Code - Type of Truck

Enter a type of truck code. This field is optional and will default to the customer default.

Vehicle Registration

Enter the vehicle registration number transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.



Select the option or function key to perform the task you want.



Note: All fields will be returned from the consignment details unless it is a manual ASN in which case the details are returned from customer defaults.

Functions:

F8

Update. This process first checks whether you are printing shipping labels. If you are, you will see the Print Shipping Labels Screen.

F10

Additional Details. The system displays a window to enter additional data related to this consignment.

F14

Weights & Totals. This displays the 856 Maintenance Weights And Totals Screen.

F15

Items. This displays the ASN Item Summary Screen.

F21

Name & Addresses. This displays the ASN Maintenance Names And Addresses Screen 1.

F22

ASN Text. This displays a window which allows the entry of free format text.

Additional Details Window (F10)

This window allows you to enter additional data related to this consignment.



Select **F10=Additional Details** from the ASN Maintenance Header Screen to display the Additional Details Window.

AS410	Z1 - GB Demonstration Company	User GBJBACHG	16/10/97 11:26:47
Advanced Shipping ASN Maintenance - Header			
Consignment number...	00000233	FIRST SHIP	
Customer.....	AC01	000	Schedule Customer 1 Main Plant
Mode of Despatch	Authentication ..		
Est. an	Conveyance Reference		
Supplier	Transport Document Number		
Plant n	Method of Transport-Detailed..?		
Final d	Freight Payment (ICMM) Term...?		
Additio	Carriage Payment Terms ..?		
Freight	Packing List Date		
Carrier	Type of Truck.....		
Vehicle	Enter=Continue F4=Prompt F12=Previous		
Trailer			
F3=Exit F4=Prompt F8=Update F10=Additional ASN Details F12=Previous F14=Weights & Totals F15=Items F21=Name & Addresses F22=ASN Text			
13-45 SA MW KS CL IM DM II EDN4000 KB PET178S1			

Fields:

Authentication

Enter the authentication details.

Conveyance Reference

Enter a conveyance reference.

Transport Document Number

Enter the transport document number.

Method of Transport - Detailed

Enter the method of transport.

Freight Payment (ICCM) Term

Enter the freight payment term.

Carriage Payment Terms

Enter the carriage payment terms.

Packing List Date

Enter the packing list date.

Type of Truck

Enter the type of truck code.



Press **Enter** to validate the entries you have made, then press **Enter** again to display the ASN Maintenance - Header Screen.

ASN Maintenance Weights And Totals Screen (F14)



Select **F14=Weights and Totals** from the ASN Maintenance Header Screen to display the Weights and Totals Screen.

The screen allows you to overwrite the system calculated ASN totals (calculated from all the packs and pallets on the ASN). The system calculates and creates all pack & pallet records (into a work file) for the consignment. It then summarises Consignment Pack & Pallet Totals and allows user overrides of total figures.

```

AS415          Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96
                                                    14:40:33
ASN Maintenance - Weights & Totals

Consignment Number .. 00000143      West consignment
Customer ..... TE          001      Tracy Eastwood
Despatch Date ..... 8/08/96      DELivery Address
Weight UOM ..... KG Kilogrammes   Despatch time .. 0:00
Volume UOM ..... M3 Cubic metre

Pallet   No. of   No. of   Net Weight   Gross Weight   Volume
Type     Pallets   Packs

          No pallets exist for this consignment number

Calculated      0         0         .000         .000         .000
Actual .....         .000         .000         .000
Vehicle Capacity .....         0         0
Percentage Used .....         0         0

F3=Exit F12=Previous

19-30  SF  MW  KS  IM  II  KENB20A  PET087S2
  
```

Fields:

Pallet Type

The pallet type for this contract is taken from the customer/item/pack/pallet details file.

No. Of Pallets

The calculated number is based on the contract and customer/item/pack/pallet details file.

No. Of Packs

The calculated number is based on the contract and customer/item/pack/pallet details file.

Net Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Gross Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Volume

The calculated number is based on the contract and customer/item/pack/pallet details file.

Calc. Totals

This represents the system calculated totals for this consignment.

Actual Totals

These fields default to the system calculated values but may be overridden.

Vehicle Capacity

These fields default to the system calculated values but may be overridden.

Percentage Used

This is calculated by the system.



Press **Enter** to validate the screen, then press **Enter** again to display Maintenance Header Screen.



Enter option 1 against the name and address code that you want to maintain.

ASN Maintenance Names and Addresses Screen 2 (Option 1)



Enter option 1 against a name and address code on the first Names and Addresses Screen to display the second Names and Addresses Screen.

This screen displays full details for a selected code, and allows you to make changes to the name and address as required.

```

AS425          Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96
                                           15:33:43

ASN Maintenance - Name and Addresses
Consignment ..... 00000141      Woof
Despatch Date ..... 10/09/06      Despatch Time ..... :00
Type code..... CGEE      Consignee (Delivery Customer)
Address code..... CGEE01
Name..... Elvis Frodsham Ltd
Address line 1..... Pendeford Industrial Estate
Address line 2..... Wollaston Lane
Address line 3..... Pendeford
Address line 4..... Wolverhampton
Address line 5..... West Midlands
Post code..... WVS 8KJ      Country Code ....?. UK
Telephone number.... 01902 765487      Extension number...
Fax number..... 01902 765486      Internal ID.....
Telex number.....      Teletext number....
Contact name..... Eddie Revel
Department code....
Comments..... Any special comments or instructions
                █

F3=Exit  F4=Prompt  F12=Previous

21-23  S2  MW  KS  IM  II  KENB20A  PET087S2
  
```

Fields:

Type Code

This is the address type code which was entered previously.

Address Code

This is the address code which was entered previously.

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Post Code

Enter the post code.

Country Code

Enter the country code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the contact name as required.

Department Code

Enter the department code for the contact as required.

Comments

This is a free format field. Enter any required comments.



Press **Enter** to validate the screen, then press **Enter** again to display the previous screen, after saving the new details.

ASN Text Window (F22)

External Text can be maintained for each ASN consignment.



Select **F22=External Text** from the ASN Maintenance Header Screen to display the ASN Text Window.

AS410		Distribution V3 -> V3 Financials 3F User GBJBA1MS		19/09/96
				14:41:37
Advanced Shipping ASN Maintenance - Header				
Consignment number...	00000143	West consignment		
Customer.....	TE	001	Tracy Eastwood	
			Delivery Address	
Despatch date.....	8/08/96			
Est. arrival date....	19/09/96			
Supplier code.....?				
Plant number.....?	PLN02			
Final delivery point..?	FDEL02			
Additional dest. code.?	JOHN			
Freight forwarder.....?	FFWD01			
Carrier code.....?	CARR01			
Vehicle registration....				
Trailer reference.....				
Mode of transport.....?	3			

ASN Text	
Lin	External Text
1	
2	
3	
4	
5	
6	
Position to ____ Insert ____ after ____	
Delete ____ from ____	
F5=Refresh F8=Update F12=Previous	

F3=Exit	F4=Prompt	F8=Update	F10=Additional Details	F12=Previous
F14=Weights & Totals	F15=Items	F21=Name & Addresses	F22=ASN Text	
12-42	SA	MW	KS	IM
			II	KENB20A
				PET087S2

Fields:

Line Number

Key in text on each line as required.

Position To

Enter the line you want to display at the top of the screen.

Insert

Enter the number of blank lines you want to insert, and the line number after which they should be inserted.

Delete

Enter the number of lines you want to delete, and the line number from which you want to start the delete.



Press **F8=Update** to update the text file and display the ASN Maintenance - Header Screen.

ASN Item Summary Screen (F15)



Select **F15=Items** from the ASN Maintenance Header Screen to display the ASN Item Summary Screen.

This screen displays the items, contracts, lots, despatch quantities, kanbans, and call off/RAN references on an ASN.

There are two modes of operation for this screen. In restricted mode you cannot amend the item details themselves, this screen is used to select items to maintain packaging details.

In amend mode you can change all the details, including quantities. Such amendments can create data integrity issues - as you must put through separate amendments to invoice, stock, order and contract details. Access to amend mode is therefore controlled by a function key (**F9=Restricted Mode**) which has user level authority attached to it. In amend mode you can automatically regenerate packaging details. When you are in amend mode the system will display the following message on the screen - 'Changes will not update invoice, stock, order or contract details'.

AS420		Distribution V3 -> V3 Financials 3F User GBJBA1MS			19/09/96
					15:38:01
ASN Maintenance - Item Summary					
Consignment number .. 00000141		Woof			
Customer ZDJ1		001	ZDJ1 the customer ltd		
Despatch date 10/09/06		Despatch time		0:00	
Sel	Item	Contract?	Lot	Despatch Qty	Kanban
-	ZDJLOT1	0000202	ZDJLOT1.301	160.000	
-	ZDJ'S Lot Item 1	-----		Ref: WOOF	
-	ZDJLOT1	0000202	ZDJLOT1.302	10.000	
-	ZDJ'S Lot Item 1	-----		Ref: WOOF	
-	ZDJLOT1	0000202	ZDJLOT1.303	15.000	
-	ZDJ'S Lot Item 1	-----		Ref: WOOF	
-	ZDJLOT1	0000202	ZDJLOT1.304	5.000	
-	ZDJ'S Lot Item 1	-----		Ref: WOOF	
-	ZDJLOT1	0000202	ZDJLOT1.305	10.000	
-	ZDJ'S Lot Item 1	-----		Ref: WOOF	+
1=Item pallet summary					
F3=Exit F8=Verify details F9=Item & qty changes F12=Previous					
F15=Expand/summary					
11-03		SP	MW	KS	IM II KENB20A PET087S2

Fields:

Selection

4 - Delete a line. (This is only available in restricted mode. Select **F9=Item & Qty Changes** to get restricted mode).

Item

This is the item code, with the item description displayed below.

Contract/Order

This is the contract number.

Lot

This is the lot number.

Despatch Quantity

The quantity despatched.

Kanban

This is the kanban reference code.



Enter 1 in the selection field to display the pallet and pack details.

Functions:**F5**

Maintain Packs And Pallets. This takes you to the Confirm Pack Screen (refer to the Confirm Packaging And Labels option) to create or maintain pack and pallet details.

F6

Add. This allows you to add a new line. The system will display a window with the input fields. Item, Order/Contract and Quantity are mandatory fields.

F8

Verify Details. This calculates the total pack quantity, compares it to the item quantity, and displays a warning if there is a discrepancy. This warning also tells you how to resolve the problem.

If you do not select **F8=Verify Details** then the system performs this check anyway, when you exit the option.

F9

Item & Qty Changes/Restricted Mode. This switches back and forth to restricted mode, if your User ID has the correct authority level, otherwise it will not appear on the screen.

F15

Expand/Summary. This is a toggle switch which either shows or hides the second line of information.

ASN Maintenance Item Pallet Summary Screen (Option 1)



Enter option 1 against an item from the ASN Item Summary Screen to display the ASN Maintenance Item Pallet Summary Screen.

This screen displays a summary of the pallets on the ASN which contain the relevant item in pallet number sequence.



Note: When packs are not on real pallets, a dummy pallet reference of 999999999 is used to access them.

AS430		Distribution V3 -> V3 Financials 3F User GBJBA1MS		19/09/96	
				14:43:29	
ASN Maintenance - Item Pallet Summary					
Consignment Number .. 00000143		West consignment			
Customer TE		001		Tracy Eastwood	
Despatch Date 8/08/96				DElivery Address	
Item 01				Despatch Time 0:00	
Lot LOT 1				Despatch Qty 100.000	
Sel	Pallet	Type	Tracking Ref.	No. Packs	
1				500	
1=Details 4=Delete					
F3=Exit F5=Refresh F6=Add Pallet F8=Verify Details F12=Previous					
F15=Expand/Summarise F17=Consignment Pack Enquiry					
13-03 SF MW KS IM II KENB20A PET087S2					

Fields:

Select

Enter one of the following:

1' to display the pallet details.

4 to delete the pallet.



Note: The system will not allow the delete if other items are also on the pallet.

Pallet

This is the unique number assigned to the pallet.

Type

This is the pallet type code from the pallet file.

Tracking Ref

This field may be maintained from this screen.

No. Packs

This shows the number of packs of this item assigned to each pallet.

Description

This is the pallet description assigned to the pallet type code.



Select 1 to display the pallet details.

Functions:

F6

Add Pallet. This allows you to create a new pallet record, assigning the next pallet number, but allowing amendment. The pallet must be unique within a consignment. The input fields are displayed in a window.

F15

Expand/Summarise. This toggles between displaying/hiding pallet descriptions.

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

ASN Maintenance Pallet Details Screen (Option 1)



Enter option 1 against an item from the ASN Maintenance Item Pallet Summary Screen to display the ASN Maintenance Pallet Details Screen.

This screen allows you to maintain the pack range details associated with the selected pallet/item. You can maintain 'actual' weights, volumes, and quantities or select the range to amend.

```
AS435          Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96
                                           15:28:02

ASN Maintenance - Pallet Details

Consignment number .. 00000141      Woof
Customer ..... ZDJ1      001      ZDJ1 the customer ltd

Despatch date ..... 10/09/06      Despatch time ..... 0:00
Pallet ..... 7      Pallet type ..... B01
Item ..... ZDJLOT1      Despatch Qty ..... 10.000
Contract ..... 0000202      Ref. WOOF
Lot ..... ZDJLOT1.302

Sel From Pack    To Pack Type Net Wt      Gross Wt      Volume      Qty/Pack
-              494      495 A01      10.000      20.000      5.000      5

1=Amend additional details  4=Delete
F3=Exit  F6=Add pack range  F8=Verify details  F12=Previous
F17=Consignment pack enquiry
      15-71      52      MW      KS      IM      II      KENB20A      PET087S2
```

Fields:

Select

Enter one of the following:

1 - Amend pack details.

4 - Delete the pack range.

From/To Pack Reference

The beginning and end pack numbers which have identical weight, volume etc.

Pack Type

The pack type description from the pack file.

Net Weight

This displays the 'actual' net weight of the pack, and will be the same as the calculated net weight unless it has been manually overridden.

Gross Weight

This displays the 'actual' gross weight of the pack, and will be the same as the calculated gross weight unless it has been manually overridden.

Volume

This displays the 'actual' volume of the pack, and will be the same as the calculated volume unless it has been manually overridden.

Quantity

Shows the quantity of the item in each pack.



Select 1 to display the pack details screen.

Functions:

F6

Add Pack Range. This allows you to add additional packs of the item to the pallet. The Pack Details Screen is displayed for you to enter the new details.

F8

Verify Details. This verifies that the total quantity assigned to the packs/pallets is equal to the quantity being despatched. When **F8=Verify Details** is taken either a window will be displayed confirming that there are no discrepancies, or the Packaging Discrepancies Screen will be displayed.

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

ASN Maintenance Pack Details Screen (Option 1)

 Enter option 1 against a pack from the ASN Maintenance Pallet Details Screen.

This screen allows you to maintain the item and pack details associated with the selected pack. It is mainly display, but does allow update on some fields. This screen can be used for entering pack marks, kanban details and amending lots.

AS440		Distribution V3 -> V3 Financials 3F User GBJBA1MS		19/09/96
				15:28:35
ASN Maintenance - Pack Details				
Customer	ZDJ1	001	ZDJ1 the customer ltd	
Consignment Number ..	00000141	Contract Ref.		0000202
Item Reference	ZDJLOT1	ZDJ'S Lot Item 1----->		
Call Off Ref	000F			
Stockroom	?			
Lot No	ZDJLOT1.302			
Rotation Date	0/00/00	Workstation		QPADEV0016
Pallet Ref	7	Pallet Type		B01 pallet type
Packs .	494 to 495	Pack Type		A01 pack type
Pack Quantity	5	EA Single of.....*		
Pack Gross Wt (Calc)...	151.000	Pack Gross Wt (Act)...		20.000
Pack Net Wt (Calc)...	150.000	Pack Net Wt (Act)....		10.000
Pack Volume (Calc)...	10.000	Pack Volume (Act)....		5.000
Pack Marks				
Kanban Card Ref				
F3=Exit F4=Prompt F12=Previous F17=Consignment Pack Details				
09-24	SA	MW	KS	IM II KENB20A PET007S2

Fields:

Call Off Ref

This is the call off reference number.

Stockroom

This is the stockroom code for the item.

Lot No

This is the lot number for the item.

Rotation Date

This is the rotation date for the item.

Workstation

This is the workstation which generated the pallet details.

Pallet Ref

This is the pallet reference number which is a unique identifier for the pallet.

Pallet Type

This is the pallet type code.

Packs

These are the pack reference numbers for the packs in this pallet. These are unique identifiers for each pack.

Pack Type

This is the pack type code used to describe the way in which the item is packed.

Pack Quantity

This is the number of items in a pack.

Pack Gross WT (Calc)

This is the calculated gross weight of the pack.

Pack Gross WT (Act)

This is the actual gross weight of the pack.

Pack Net WT (Calc)

This is the calculated net weight of the pack.

Pack Net WT (Act)

This is the actual net weight of the pack.

Pack Volume (Calc)

This is the calculated pack volume.

Pack Volume (Act)

This is the actual pack volume.

Pack Marks

This identifies particular groups of packs in a consignment.

Kanban Ref Card

This is the kanban reference card code.



Press **Enter** to validate any details you have entered, then press **Enter** again to continue.

Functions:

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

ASN Maintenance Packaging Discrepancies Screen



This screen is displayed as a result of quantity discrepancies when **F8=Update** is selected from the Item Summary/Pallet/Pallet Details and Pack Details Screen.

You can delete lines, add lines, or amend the ranges and/or qty per pack. This screen forces discrepancies to be resolved, therefore if any packing information is entered, total packed quantity must equate to the item despatched quantity.

```
AS450          Distribution V3 -> V3 Financials 3F User GBJBA1MS 19/09/96
                                           15:29:42
ASN Maintenance - Packaging Discrepancies          ** Last Discrepancy **

Item ..... ZDJLOT1          ZDJ'S Lot Item 1----->
Contract Ref ..... 0000202  Lot No ..... ZDJLOT1.302
Call Off Ref ..... W00F
Quantity Despatched . 10.000      Quantity Packed ..... 20.000

Stock-      Pallet      Pack From  Pack To  Qty per  Total No.  Total Qty
room                Pack              Pack    Pack    Of Packs  in Packs
-      B01          3 A01      63      64      5          2          10
-      B01          7 A01      494     495     5          2          10

1=Pack Details  4=Delete
F3=Exit  F5=Recalc.  F6=Add  F12=Previous  F15=Pallet Summary
F17=Consignment Pack Enquiry
      13-02      S2      MW      KS      IM      II  KENB20A  PET087S2
```

Fields:

Select

Enter one of the following:

1 to view the pack details.

4 to delete the line.

Stockroom

This is the stockroom code.

Pallet

This is the pallet reference number which is unique identifier for this pallet.

Pack From/To

Displays the pack reference numbers which are unique identifiers for each pack.

Qty Per Pack

Displays the item quantity in each pack.

Total No Of Packs

This is the total number of packs in the pack range.

Total Qty In Packs

This displays the total quantity in all the packs in the pack range.

Functions:**F5**

Recalc. This recalculates the total number of packs, total quantity in packs, and grand total of packs, and then refreshes the display. This is used after manual adjustments have been made.

F6

Add. This allows you to add a new line. The Pack Details Screen is displayed.

F15

Pallet Summary. This returns you to the pallet summary screen providing the opportunity to continue editing prior to re-verifying the package details.

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging information.

Consignment Pack Enquiry Screen (F17)



Select **F17=Consignment Pack Enquiry** from the Packaging Discrepancies, Pack Details, Pallet Details and Item Pallet Summary Screen.

This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging information.

AS470		Distribution V3 -> V3 Financials 3F User GBJBA1MS				27/09/96
						12:13:17
ASN Maintenance - Consignment Pack Enquiry						
Consignment		00000141		Woof		
Last Pallet Number Used ..		5		Last Pack Number Used ..		463
Pallet Type	Pallet Reference	Pack Type	From Pack	To Pack	Item	Lot
B01	2	A01	31	62	ZDJLOT1	ZDJLOT1.301
B01	3	A01	63	64	ZDJLOT1	ZDJLOT1.302
B01	3	A01	65	67	ZDJLOT1	ZDJLOT1.303
B01	3	A01	68	68	ZDJLOT1	ZDJLOT1.304
B01	3	A01	69	70	ZDJLOT1	ZDJLOT1.305
B01	3	A01	71	72	ZDJLOT1	ZDJLOT1.306
B01	4	A01	400	409	ZDJLOT1	ZDJLOT1.306
B01	5	A01	440	463	ZDJLOT1	ZDJLOT1.308
F12=Previous						
01-02			MW	KS	IM	II KENB20A PET087S2



Select **F12=Previous** to display the previous screen.

Resend ASNs

1... **2...** 6/ADP

This option lists ASNs which have either already been sent, or cancelled via the ASN Maintenance & Send option. You can maintain the details or resend the ASN.

The Resend ASNs selection screen is the same as the ASN Maintenance & Send Screen except it only lists ASNs which have previously been sent or cancelled. The maintenance functions are identical, and re-sending an ASN works in exactly the same way as sending an ASN.

The Resend screens do not provide a cancel facility, or a Manual Add ASN facility. ASNs may be sent/resent up to eight times.

ANSIX12 856 Maintenance And Send



7/ADP

Advanced Shipping Notifications (ASNs) are electronically transmitted messages which provide advance information about the details of shipments or consignments.

The ANSIX12 856 ASN is similar to a European ASN but differs in its use of hierarchical levels and does not have a fixed structure. It is becoming increasingly important if you trade in, or with clients in North America. The ANSIX12 856 ASN is only available if your system has been specifically set up to transmit this type of ASN.

This option allows you to maintain, send and cancel ANSIX12 856 ASNs.

ANSIX12 856 ASN Maintenance And Send Screen

This screen allows you to send and maintain ANSIX12 856 ASNs. Consignments that have been confirmed but not sent as an 856 ASN will automatically be shown on this screen.



Select ANSIX12 856 Maintenance And Send on the menu to display the ANSIX12 856 ASN Maintenance And Send Screen.

```

AS400                                Version 3 Demonstration Company   User QAAUT01   11/07/97
                                      10:12:48

Advanced Shipping ANSIX12 856 ASN Maintenance & Send

                                     Position to : Customer ....?.
                                     Consignment .?.
S Customer      Consignment      Desp. Date & Time Sts
CG01           000 Automotive customer
-              000000001 CHG QA STD 856           11/06/97   :00 R

1=Maintain Details  2=Send 856  4=Cancel 856 Pre-Send
F3=Exit  F4=Prompt  F5=Refresh  F6=Add a Manual 856  F8=Transmit 856s
F14=Consignments by Item  F16=Select all '2'
05-68  SP  MK  KS  IM  II  KENB20A  PED201S2
  
```

Fields:

Position To Customer

Enter the customer code to display consignments starting from a particular customer. The list of customers is displayed alphabetically starting from that customer.

Position To Consignment

Enter the consignment number to display a list of consignments starting from the specified number.

S

Select. Enter an option to perform the following tasks:

- 1 - Maintain Details. Displays the 856 Maintenance Header Screen which allows you to add and amend the header details for a selected ASN.
- 2 - Send 856. Selects a consignment to be actioned when **F8=Transmit 856s** is selected.

4 - Cancel 856 Pre-Send. Removes an 856 ASN from the list displayed on the screen. When you cancel an 856 ASN the status is updated to Not Sent. You can resend an 856 ASN with a Not Sent status.



Enter 1 in the select field and press **Enter** to display the 856 Maintenance Header Screen.



Select **F14=Consignments By Item** to display the Consignments By Item Window.

Functions:

F6

Add A Manual 856. This option allows you to create a manual 856 ASN from a consignment.



Note: A manual 856 ASN is a memo document only and does not update inventory, schedules or invoices. It is your responsibility to make the necessary adjustments.

F8

Transmit 856s. Sends all 856 ASNs marked with a 2 in the select field.

F14

Consignments By Item. Allows you to enter an item code, which on display the previous screen, only lists consignments related to the specified item.

F16

Select All '2'. Automatically applies option 2 (Send 856) to all consignments on the screen, which are then activated when **F8=Transmit 856s** is selected.

856 Maintenance Header Screen (Option 1)

This screen allows you to enter and amend data for a selected 856 ASN.



Enter 1 in the select field on the ANSIX12 856 ASN Maintenance And Send Screen and press **Enter** to display the 856 Maintenance Header Screen.

AS410		Version 3 Demonstration Company		User QAUT01	11/07/97 10:23:28
Advanced Shipping 856 Maintenance - Header					
Consignment number...	00000001	CHG QA STD 856			
Customer.....	CG01	000	Automotive customer		
			31 Lenton Boulevard		
Mode of transport.....?	3		Road		
Despatch date.....	11/06/97		Despatch time.....	0:00	
Est. arrival date....	13/07/97		Est. arrival time..	0:00	
Supplier code.....?					
Plant number.....?	PLN001		paint number 01		
Final delivery point..?	FDEL01		Final Delivery Point		
Additional dest. code.?	ADES01		ADDITIONAL ADDRS de		
Freight forwarder.....?	FFWD01		Freight Forwarder 01		
Carrier code.....?	CARR01		Transport carrier co		
Vehicle registration....					
Trailer reference.....					
ASN map sequence & 856 hierarchical levels.... 01 S T O I P					
F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text 05-43 SC MK KS IM II KENB20A PED201S2					

Fields

Mode Of Transport

Enter the mode of transport for the consignment. This field is mandatory.

Despatch Date

Enter the date of despatch.

Despatch Time

Enter the time of despatch using the 24 hour clock.

Est Arrival Date

Enter the estimated arrival date. This date must be the same as or later than the despatch date.

Est Arrival Time

Enter the estimated arrival time using the 24 hour clock.

Supplier Code

The system displays the value entered in the Customer Contract Defaults Screen in the Maintenance option if you are in Add mode (F6), otherwise it will be returned from the consignment header.

Plant Number

This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Dest Code

Additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Carrier Code

This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Vehicle Registration

Enter the registration number of the vehicle transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.

ASN Map Sequence & 856 Hierarchical Levels

The system displays the sequence code which is entered when the consignment is created or amended.



Select **F8=Update** to update the data and display the ANSI X12 856 ASN Maintenance And Send Screen.



Note: Detailed field values will be returned from the consignment details unless it is a manual ASN in which case the details are returned from customer defaults.

Functions:

F10

Additional 856 Details. This function displays the Additional 856 Details Window which allows you to select screens to add and amend additional 856 ASN data against a consignment.

F14

Weights & Totals. This function displays the 856 Maintenance Weights And Totals Screen which allows you to overwrite the system calculated 856 ASN totals.

F15

Items. This function displays the first 856 Maintenance Item Summary Screen which lists item details.

F21

Name & Addresses. This function displays the 856 Maintenance Names And Addresses Screen which allows you to amend address details.

F22

856 Text. This displays the 856 Text Window which allows you to enter free format text to be sent with an 856 ASN.

Additional 856 Details Window (F10)

This window allows you to send 856 ASN data over and above the essential common message data. From this menu you can select the screens which allow you to add further 856 ASN details.

All the additional 856 ASN details are optional, your trading relationship determines which additional details must be included.

The first five options from this window are appropriate to only one level of details. The remaining options are appropriate to more than one level.

The fields and their names have been included to match the names used by the 856 ASN message itself.



Select **F10=Additional 856 Details** on the 856 Maintenance Header Screen to display the Additional 856 Details Window.

AS410		Version 3 Demonstration Company		User QAUT01	14/07/97
					9:00:29
Advan	Additional 856 Details				
Consi	Sel				
Custo	■ Additional Shipment Level Details				
	- Additional Tare Level Details				
Mode	- Additional Order Level Details				
Despa	- Additional Pack Level Details				
Est.	- Additional Item Level Details				
	References				
Suppl	- Charges & Allowances				
Plant	- Hazardous Materials				
Final	- Product/Service Identification				
Addit	- Product Characteristics				
Freig	- Subline Details				
Carri	- VICS Product Marks/Package Specification				
Vehic	1=Select				
Trail	F12=Previous				
ASN m					
F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous					
F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text					
06-10 82 MK KS IM II KENB20A PED201S2					

Fields:

Sel

Select. Enter 1 against the required option. The following options are available:

Additional Shipment Level Details Screen

Additional Tare Level Details which displays the 856 Additional Tare Container References Screen.

Additional Order Level Details which displays the 856 Additional Order Level Details Screen.

Additional Pack Level Details which displays the 856 Additional Pack Container References Screen.

Additional Item Level Details which displays the 856 Additional Item Details Window.

References which displays the 856 References Screen.

Charges And Allowances which displays the 856 Charges And Allowances Screen.

Hazardous Materials which displays the 856 Hazardous Materials Screen.

Product/Service Identification which displays the Product/Service Identification Screen.

Product Characteristics which displays the Product Characteristics Screen.

Subline Details which displays the Subline Details Screen.

VICS Product Marks/Package Specification Screen.



Enter 1 in the Sel field to select the required option and display the associated screen.

856 Additional Shipment Level Details Screen

This screen allows you to add additional shipment details to be sent with an 856 ASN.



Enter 1 in the Sel field of the Additional Shipment Level Details option on the Additional 856 Details Window to display the 856 Additional Shipment Level Details Screen.

AS263		Version 3 Demonstration Company		User QA AUT01		14/07/97 11:28:18	
Advanced Shipping 856 Additional Shipment Level Details							
Shipment Number ...		00000001		Hierarchical Structure S T O I P			
Original Carrier ?		Type ?	Carrier Name			Status ?	
CARR01		—	Transport carrier company 01			—	
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	3	—	—	0:00	—
1st After Original ?		Type ?	Carrier Name			Status ?	
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	—	—	—	0:00	—
2nd After Original ?		Type ?	Carrier Name			Status ?	
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	—	—	—	0:00	—
Equipment :		Type ?	—	Initial	Number		
F3=Exit F4=Prompt F8=Update F10=Transport Charges & Goods Title							
F12=Previous							
07-02		SA	ML	KS	IM	II	KENB20A PED201S2

Fields:

Original Carrier

Carrier Code. This is displayed from the 856 Maintenance Header Screen and can be overridden.

Type

Enter the code for the carrier type.

Carrier Name

This is the carrier name that corresponds to the carrier type code.

Status

Enter the carrier status code.

Carrier Location

Enter the carrier location. This is a free format field.

Type

Enter the carrier location type code.

Mode

Mode of Transport. This is displayed from the 856 Maintenance Header Screen and can be overridden.

Service

Carrier Service Level. Enter the carrier service level code.

Transit Time

Enter transit time.

Type

Enter the carrier transit time type.

1st After Original

The fields 1st After Original and 2nd After Original allow you to add additional carriers.

Equipment

Type

Equipment Type. Enter the equipment type code.

Initial

Enter the equipment initial. This is a free format field.

Number

Enter the equipment number. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Window.

Functions:

F10

Transport Charges & Goods Title. This function allows you to enter and amend additional specific transport charges.

Transport Charges Window (F10)

This function allows you to enter and amend additional transport charges specific to the shipment.



Select **F10=Transport Charges & Goods Title**
on the 856 Additional Shipment Level Details
Screen to display the Transport Charges
Window.

AS263		Version 3 Demonstration Company		User QAAUT01	14/07/97
					11:28:18
Advanced Shipping 856 Additional Shipment Level Details					
Shipment Number ...		00000001		Hierarchical Structure S T O I P	
Transport Charges					
Origi	Payment Terms	P1	Cash	?	
CARR0	Responsibility Location Type.?	01	Location type 1		
Carri	Location			ype ?	
	Payment Terms Identification ?.				
	Payment Type Code				
1st A	Title of Goods			?	
	Change Location Type				
Carri	Change Location			ype ?	
	Premium Transport				
	Reason for use Code				
2nd A	Responsibility for Excess ...?			?	
Carri	Authorisation for Excess			ype ?	
F4=Prompt F12=Previous					
Equipment :	Type ?		Initial		Number
F3=Exit F4=Prompt F8=Update F10=Transport Charges & Goods Title					
F12=Previous					
06-42	SP	MW	KS	IM	11 KENB20A PED201S2

Fields:

Payment Terms

Enter the payment terms code.

Responsibility Location Type

Enter the code corresponding to the type of location of the party responsible for the transport charges.

Location

Enter the location. This is a free format field.

Payment Terms Identification

Enter the code corresponding to the payment terms identification.

Payment Type Code

Enter the code corresponding to the payment type.

Title Of Goods

Change Location Type

Enter the code corresponding to the type of carrier location.

Change Location

Enter text. This is a free format field.

Premium Transport

Reason For Use Code

Enter the code corresponding to the reason for using the premium transport.

Responsibility For Excess

Enter the code corresponding to the party responsible for the excess charges relating to the use of premium transport.

Authorisation For Excess

Enter the authorisation reference. This is a free format field.



Press **Enter** to validate the data and display the 856 Additional Shipment Level Details Screen.

856 Additional Tare Container References Screen

This option allows you to enter additional specific 856 ASN Tare information, such as alternative Tare references. Tare is the weight of the empty pallet.



Enter 1 in the Sel field of the Additional Tare Level Details option on the Additional 856 Details Window to display the 856 Additional Tare Container References Screen.

AS266		Version 3 Demonstration Company		User QAUT01	14/07/97
					11:45:21
Advanced Shipping 856 Additional Tare Container References					
Shipment Number ... 00000001		Hierarchical Structure S T O I P			
Int. Ref.	Typ	UCC Serial No.	Shipper's Reference	Carrier's Reference	
1	QAP	1234 3	SHIPPERS CONTAINER PALLET	CARRIERS CONTAINER PALLE	
2	QAP	-	-	-	
3	QAP	-	-	-	
4	QAP	-	-	-	
5	QAP	-	-	-	
6	QAP	-	-	-	
7	QAP	-	-	-	
8	QAP	-	-	-	
9	QAP	-	-	-	
10	QAP	-	-	-	
11	QAP	-	-	-	
12	QAP	-	-	-	
13	QAP	-	-	-	
14	QAP	-	-	-	
15	QAP	-	-	+	
F3=Exit F8=Update F12=Previous					
07-16 S2 MK KS IM II KENB20A PED201S2					

Fields:

UCC Serial No

Enter the UCC Standard Shipping serial number.

Shipper's Reference

Enter the shipper's reference. This is a free format field.

Carrier's Reference

Enter the carrier's reference. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Window.

856 Additional Order Level Details Screen

This option allows you to associate reason codes with each order on the consignment.



Enter 1 in the Sel field of the Additional Order Level Details option on the Additional 856 Details Window to display the 856 Additional Order Level Details Screen.

AS279	Version 3 Demonstration Company	User QAUT01	14/07/97 11:49:29
Advanced Shipping 856 Additional Order Level Details			
Shipment number 00000001		Hierarchical structure S T O I P	
Order	Reason Code .?.	Resp.for Excess.?.	Auth.for Excess
0000001	__	-	_____
			Bottom
F3=Exit F4=Prompt F8=Update F12=Previous			
09-10	SF	MK	KS IM II KENB20A PED201S2

Fields:

Reason Code

Enter the code corresponding to the reason for using premium transport.

Resp For Excess

Enter the code corresponding to the party responsible for the excess charges.

Auth For Excess

Enter the authority reference for the excess charges. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Window.

856 Additional Pack Container References Screen

This option allows you to enter additional pack container details, such as alternative pack container references.



Enter 1 in the Sel field of the Additional Pack Level Details option on the Additional 856 Details Window to display the 856 Additional Pack Container References Screen.

AS271		Version 3 Demonstration Company		User QAUT01	14/07/97
					12:01:36
Advanced Shipping 856 Additional Pack Container References					
Shipment Number ...		00000001		Hierarchical Structure S T O I P	
Int. Ref.	Typ	UCC Serial No.	Shipper's Reference	Carrier's Reference	
1	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
2	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
3	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
4	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
5	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
6	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
7	QAB		SHIPPERS CONTAINER CODE-X	CARRIERS CONTAINER CODE-C	
Assigned Pack ID:			Size of Suppliers Units	UOM .?.	
F3=Exit F4=Prompt F8=Update F12=Previous F15=Show/Hide Additional Details					
08-16		SA	ML	KS	IM II KENB20A PED201S2

Fields:

UCC Serial No

Enter the UCC Standard Shipping serial number.

Shipper's Reference

Enter the shipper's reference. This is a free format field.

Carrier's Reference

Enter the carrier's reference. This is a free format field.

Assigned Pack ID

Enter the assigned pack ID. This is a free format field and is displayed when in **F15=Show /Hide Additional Details** is selected.

Size Of Suppliers Units

Enter the size of the suppliers units. This is a free format field and is displayed when **F15=Show/Hide Additional Details** is selected.

UOM

Enter the unit of measurement. This field is displayed when in **F15=Show/Hide Additional Details** is selected.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Window.

Functions:

F15

Show/Hide Additional Details. Select this function to toggle between Show and Hide Additional Details mode.

Additional 856 Item Details Window



Enter 1 in the Sel field of the Additional Item Level Details option on the Additional 856 Details Window to display the Additional 856 Item Details Window.

AS410	Version 3 Demonstration Company	User QAUT01	14/07/97
			11:25:06
Advan	Additional 856 Item Details		
Consi	Sel		
Custo	CGQA1	CG QA Item1	
Mode			
Despa			
Est.			
Suppl			
Plant			
Final			
Addit			
Freig	1=Select		
Carri	F12=Previous		
Vehic			
Trail			
ASN m			
F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous			
F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text			
06-11 S2 MK KS IM II KENB20A PED201S2			

Fields:

Sel

Select. The following options are available:

1 - Select. Enter 1 against the item you want to add additional 856 ASN details to.



Enter 1 in the Sel field and press **Enter** to display the 856 Additional Item Level Details Screen.

856 Additional Item Level Details Screen



Enter 1 in the Sel field on the Additional 856 Item Details Window and press **Enter** to display the 856 Additional Item Level Details Screen.

AS267	Version 3 Demonstration Company	User QAUT01	16/07/97
			15:22:59
Advanced Shipping 856 Additional Item Level Details			
Shipment Number ... 00000001		Hierarchical Structure S T O I P	
Item CGQA1		CG QA Item1	
Size of Supplier Units in a Pack		UOM .?.. _	
Number of Customer Selling Units per Pack ..			
Item Dimensions Unit of Measure?		CM Centimeters	
Item Chemistry Unit of Measure?			
Item Shipment Status?			
Item Expiration Date			
<u>Premium Transport</u>			
Reason for use Code?		01 Customer emergency	
Responsibility for Excess?		2 Customer 50%	
Authorisation for Excess		COLIN G	
F3=Exit F4=Prompt F8=Update F9=Pack Type Summary F10=Measurements			
F12=Previous			
07-47 SE MK KS IM II KENB20A PE9106S2			

Fields:

Size Of Supplier Units In A Pack

Enter the size of supplier units in a pack.

This field must be filled when a value is entered in the UOM field.

UOM

Enter the unit of measurement code.

This field must be filled when a value is entered in the Size of Supplier Units In A Pack field.

Number Of Customer Selling Units Per Pack

Enter the number of customer selling units per pack.

Item Dimensions Unit Of Measure

Enter the item dimensions unit of measure code.

Item Chemistry Unit Of Measure

Enter the item chemistry unit of measure code.

Item Shipment Status

Enter the item shipment status code.

Item Expiration Date

Enter an item expiration date. This must be a valid future date.

Premium Transport

Reason For Use Code

Enter the code corresponding to the reason for using the premium transport.

Responsibility For Excess

Enter the code corresponding to the party responsible for the excess charges relating to the use of premium transport.

Authorisation For Excess

Enter the authorisation reference. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the 856 Item Details select Screen.

Functions:

F9

Pack Type Summary. This window allows you to add and maintain additional pack summary data. For further information, refer to the Company Items Default Pack Type Summary Window in the Maintenance section.

F10

Measurements. This window allows you to add and maintain item measurement data. For further information, refer to the 856 Item Measurements Screen 2 in the Maintenance section.

856 References Screen

This screen allows you to add specific reference details to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN and Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add reference details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number is the first level and is automatically displayed.

When you have selected the level you require, press **Enter** and further fields are displayed on the screen.



Enter 1 in the Sel field of the References option on the Additional 856 Details Window to display the 856 References Screen.

AS272	Version 3 Demonstration Company	User QAUT01	18/07/97
			14:46:24
Advanced Shipping 856 References			
Shipment Number		00000001	Hierarchical Structure S T O I P
Tare Reference		1	
Order/Contract			
Item			
Pack			
Pack Type			
Input for Order/Pack Type or Item/Pack Type References Only			
Sel Type ?		Reference	
-	<u>FS</u>	Reference FS	
-	<u>01</u>	Reference 01	
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
F15=Hide/Show Descriptions			
14-07	<u>SF</u>	<u>ML</u>	KS IM II KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Pack Type

Enter the pack type code. This code is only valid when the data being entered is at item or order level.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Type

Enter the type code.

Reference

Enter the reference. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

F15

Hide/Show Descriptions. Toggles between hiding/displaying the second line of the description.

856 Charges And Allowances Screen

This screen allows you to add specific charges and allowances to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN And Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add charges and allowances to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number the first level and is automatically displayed.

When you have selected the level you require, press **Enter** and further fields are displayed on the screen.



Enter 1 in the Sel field of the Charges & Allowances option on the Additional 856 Details Window to display the 856 Charges And Allowances Screen.

AS273	Version 3 Demonstration Company	User QA AUT01	18/07/97	
			14:59:10	
Advanced Shipping 856 Charges & Allowances				
Shipment Number		00000001 Hierarchical Structure S T O I P		
Tare Reference		1		
Order/Contract				
Item				
Pack				
Sel Ind.?	Type ?	Agency ?	Code ?	Amount
1	1 A001	Freight 01	First Agen	
1=More Details 4=Delete				
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart				
11-03	SA	MK	KS	IM II KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

1 - More Details. Displays the 856 Charges And Allowances Additional Details Window.

4 - Delete. Deletes a line.

Ind

Indicator. Enter an indicator code.

Type

Enter a type code.

Agency

Enter the agency code.

Code

Enter the charge code.

Amount

Enter the value. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

856 Charges And Allowances Additional Details Window

This window allows you to enter additional charges and allowances data.



Select option 1 and press **Enter** on the 856 Charges And Allowances Screen to display the 856 Charges And Allowances Additional Details Window.

```
AS273                               Version 3 Demonstration Company   User QAUT01   18/07/97
                                      15:00:44

Advanced Shipping 856 Charges & Allowances
Shipment Number .... 00000001      Hierarchical Structure S T O I P
Tare Reference ..... 1
Order/Contract .....
Item
Pack
Sel 1
1
ASN 856 Charges & Allowances - Additional Details
Charge Percentage.....
Charge Percentage Based On .?. -
Charge Monetary Rate ..... UOM ? __
Charge Quantity .....
Free Quantity .....
Method of Handling Code ....?.
Reference .....
Option Number .....
Description .....
Allowance on Charge Number ...

F4=Prompt F12=Previous

1=More Details 4=Delete
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart

09-40  SP MK KS IM II KENB20A PET178S2
```

Fields:

Charge Percentage

Enter the charge percentage value.

Charge Percentage Based On

Enter the charge percentage based on code.

Charge Monetary Rate

Enter the charge monetary rate code.

UOM

Enter the unit of measurement code.

Charge Quantity

Enter the charge quantity if the quantity the charge is based upon differs from the despatch quantity.

Free Quantity

Enter the quantity of free goods.

Method Of Handling Code

Enter the handling method code.

Reference

Enter a reference. This is a free format field.

Option Number

Enter an option number. This is a free format field.

Description

Enter a description. This is a free format field.

Allowance Or Charge

Enter an allowance or charge number. This is a free format field.



Press **Enter** to validate the data you have entered and display the 856 Charges And Allowances Screen.

856 Hazardous Materials Screen

This screen allows you to add specific hazardous materials codes to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN And Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add hazardous materials code to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number is level one and is automatically displayed.

When you have selected the level you require, press **Enter** and the remaining fields are displayed on the screen.



Enter 1 in the Sel field of the Hazardous Materials option on the Additional 856 Details Window to display the 856 Hazardous Materials Screen.

AS274	Version 3 Demonstration Company	User QAUT01	18/07/97
			11:58:12
Advanced Shipping 856 Hazardous Materials			
Shipment Number	00000001	Hierarchical Structure S T O I P	
Tare Reference	1		
Order/Contract	0000001		
Item			
Pack			
Sel Qualifier and Class Code ? Handling ?			
- B ABCD FLAMMABLE AT 50 C AT 20,000 FT K1 k1			
DESCRIPTION : _____			
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03	SA	MK	KS IM II KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.



```

AS275                               Version 3 Demonstration Company   User QAAUT01   18/07/97
                                      12:01:09

Advanced Shipping 856 Product/Service Identification
Shipment Number .... 00000001      Hierarchical Structure S T O I P
Tare Reference ..... 1
Order/Contract ..... 00000001
Item .....
Pack .....
Subline Id .....

Sel  Identifier Type ?                Identifier Code
  █   BP Customer Item Code           CCFD

4=Delete
F3=Exit  F4=Prompt  F6=Add  F8=Update  F12=Previous  F14=Restart

12-03  SA MW KS IM II KENB20A PET178S2

```

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Subline ID

Enter the subline identifier code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Identifier Type

Enter the identifier type code.

Identifier Code

Enter the identifier code which must be entered when the identifier type code has been added. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.

856 Product Characteristics Screen

This screen allows you to add specific product characteristics detail to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN And Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add reference details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number is automatically displayed as level one.

When you have selected the level you require, press **Enter** and the remaining fields are displayed on the screen.



Enter 1 in the Sel field of the Product Characteristics option on the Additional 856 Details Window to display the 856 Product Characteristics Screen.

AS276	Version 3 Demonstration Company	User QA AUT01	18/07/97
			12:03:51
Advanced Shipping 856 Product Characteristics			
Shipment Number	00000001	Hierarchical Structure S T O I P	
Tare Reference	1		
Order/Contract	00000001		
Item			
Pack			
Sel	Desc. Type ?	Charac. Code ?	Agency ?
-	A Fixed 15	A01 Coating	01 First Agen
	Desc. :		Position Code ? : _
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03	SA	MK	KS
	IM	II	KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. You can enter the following options:

4 - Delete. Deletes a line.

Desc Type

Enter the description type code.

Charac Code

Enter the character code.

Agency

Enter the agency code.

Description Code

Enter the description code. You must enter this code or the description in the Desc field.

Desc

Enter the description. You must enter the description or enter the code in the Description Code field.

Position Code

Enter the position code.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.

856 Subline Details Screen

This screen allows you to add specific subline details to any level of the 856 ASN hierarchical structure. Subline information is normally added to the Pack or Item levels.

When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN And Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number is automatically displayed as level one.

When you have selected the level you require, press **Enter** and the remaining fields are displayed on the screen.



Enter 1 in the Sel field on the Additional 856 Details Window to display the 856 Subline Details Screen.

AS277	Version 3 Demonstration Company	User QAUT01	18/07/97
			12:08:00
Advanced Shipping 856 Subline Details			
Shipment Number 00000001		Hierarchical Structure S T O I P	
Tare Reference 1			
Order/Contract			
Item			
Pack			
Sel	Subline Id	Rel. To Line ?	Despatch Qty UOM ? Unit Price
-	SUMMARY	B Both	10.000 BT Bottles o 25.00000
Price Basis ? : C Current		Rel. To Line Price ? : B Both	
1=Subline Identifiers 4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03 SF MK KS IM II KENB20A PET178S2			

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

1 - Subline Identifiers. Displays the 856 Product/Service Identification Screen which allows you to add up to ten identifiers to each subline.

4 - Delete. Deletes a line.

Subline ID

Enter the unique subline identifier. This field is mandatory.

Rel To Line

Relationship to line. Enter the relationship to line code.

Despatch Qty

Enter the quantity to despatch. This field is mandatory.

UOM

Enter the unit of measurement.

Unit Price

Enter the unit price. This is a free format field and is optional.

Price Basis Code

Enter the price basis code.

Rel To Line Price

Enter the relationship to line price code.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.

856 Product/Service Identification Screen (Option 1)

This window allows you to add up to ten identifiers to each subline.



Enter option 1 in the Sel field on the 856 Subline
Details Screen to display the 856
Product/Service Identification Screen.

AS275	Version 3 Demonstration Company	User QAAUT01	28/07/97 12:28:38
Advanced Shipping 856 Product/Service Identification			
Shipment Number	00000001	Hierarchical Structure S T O I P	
Tare Reference	1		
Order/Contract			
Item			
Pack			
Subline Id	TEST		
Sel	Identifier Type ?	Identifier Code	
■	BP Customer Item Code		
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
12-3	SA	MM	KS CL IM DM II KENB20A KB PET16SS1

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

The system displays this field from the previous screen.

Order/Contract

The system displays this field from the previous screen.

Item

The system displays this field from the previous screen.

Pack

The system displays this field from the previous screen.

Subline ID

The system displays this field from the previous screen.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Identifier Type

Enter the identifier type code.

Identifier Code

Enter the identifier code. This is a free format field.



Note: Both fields must be filled.



Press **Enter** to validate the data and display the 856 Subline Details screen.

Functions:

F6

Add. This allows you to add a line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.

856 VICS Product Marks/Package Specifications Screen

This screen allows you to add specific product/package marks details to any level of the 856 ASN hierarchical structure. This information is normally added to item or pack levels.

When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to Company ASN And Pack Details Screen.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add product/package marks details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values. The Shipment Number is automatically displayed as level one.

When you have selected the level you require, press **Enter** and the remaining fields are displayed on the screen.



Enter 1 in the Sel field of the VICS Product Marks/Package Specification option on the Additional 856 Details Window to display the 856 VICS Product Marks/Package Specifications Screen.

AS278	Version 3 Demonstration Company	User QAUT01	18/07/97
			12:09:42
Advanced Shipping 856 VICS Product Marks/Package Specifications			
Shipment Number		00000001	Hierarchical Structure S T O I P
Tare Reference		1	
Order/Contract			
Item			
Pack			
Sel Product/Package Mark ?			
- AS		as	
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03 SP MK KS IM II KENB20A PET178S2			

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Product/Package Mark

Enter the product/package mark code.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details Screen.

Functions:

F6

Add. This function allows you to add a new line.

F14

Restart. This function ignores the data you have entered, providing you have not selected **F8=Update**, and allows you to start again.

856 Maintenance Weights And Totals Screen (F14)

This Screen will allow you to overwrite the system calculated 856 ASN totals (calculated from all the packs and pallets on the ASN). The system calculates and creates all pack & pallet records (into a work file) for the consignment. It then summarises Consignment Pack & Pallet Totals and allows user overrides of total figures.



Select **F14=Weights And Totals** on the 856 Maintenance Header Screen to display the 856 Maintenance Weights And Totals Screen.

AS415		Version 3 Demonstration Company		User QAAUT01	14/07/97 9:31:29	
856 Maintenance - Weights & Totals						
Consignment Number .. 00000001			CHG QA STD 856			
Customer CG01 000			Automotive customer			
Despatch Date 11/06/97			31 Lenton Boulevard			
Weight UOM			Despatch time .. 0:00			
			Volume UOM			
Pallet Type	No. of Pallets	No. of Packs	Net Weight	Gross Weight	Volume	
QAP	17	34	2.000	119.000	17.000	
Calculated	17	34	2.000	119.000	17.000	
Actual			2.000	119.000	17.000	
Vehicle Capacity				0	0	
Percentage Used				0	0	
F3=Exit F12=Previous						
19-30		SF	MK	KS	IM	II KENB20A PED201S2

Fields:

Pallet Type

The pallet type for this contract is taken from the customer/item/pack/pallet details file.

No Of Pallets

The calculated number is based on the contract and customer/item/pack/pallet details file.

No Of Packs

The calculated number is based on the contract and customer/item/pack/pallet details file.

Net Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Gross Weight

The calculated number is based on the contract and customer/item/pack/pallet details file.

Volume

The calculated number is based on the contract and customer/item/pack/pallet details file.

Calculated

Calculated Totals. This represents the system calculated totals for this consignment.

Actual

Actual Totals. These fields default to the system calculated values but may be overridden.

Vehicle Capacity

These fields default to the system calculated values but may be overridden.

Percentage Used

This is calculated by the system.



Press **Enter** to validate the screen and display the 856 Maintenance Header Screen.

856 Maintenance Item Summary Screen (F15)

This screen displays the items, contracts, lots, despatch quantities, kanbans and call off/RAN references on an 856 ASN. There are two modes of operation for this screen. In restricted mode you cannot amend the item details themselves, this screen is used to select items to maintain packaging details.

In amend mode you can change all the details, including quantities. Such amendments can create data integrity issues - as you must put through separate amendments to invoice, stock, order and contract details. Access to amend mode is therefore controlled by a function key (**F9=Restricted Mode**) which has user level authority attached to it. In amend mode you can automatically regenerate packaging details. When you are in amend mode the system will display the following message on the screen - 'Changes will not update Invoice, stock, order or contract details'.



Select **F15=Items** on the 856 Maintenance Header Screen to display the 856 Maintenance Item Summary Screen.

```
AS420                      Version 3 Demonstration Company  User QAAUT01  14/07/97
                                           10:44:07

856 Maintenance - Item Summary

Consignment number .. 00000001  *****
Customer ..... CG01      000  * Changes will not update invoice, *
                                           * stock, order or contract details *
                                           *****
Despatch date ..... 11/06/97  Despatch time ..... 0:00

Sel Item      Contract? Lot      Despatch Qty  Kanban
_  CGQA1      00000001           102.000    _

1=Item pallet summary  2=856 Codes  4=Delete
F3=Exit  F4=Prompt  F5=Generate Packs & Pallets  F6=Add  F8=Verify details
F9=Restricted mode  F12=Previous  F15=Expand/summary
11-03  SP      MK      KS      IM      II  KENB20A  PED201S2
```

Fields:

Sel

Select. The following options are available:

- 1 - Item Pallet Summary. Displays the 856 Maintenance Item Pallet Summary Screen.
- 2 - 856 Codes. Displays the 856 Additional Item Level Details Screen.
- 4 - Delete. Deletes an item entry. This option is not available in restricted mode.

Item

The system displays the item code. The description is displayed below when **F15=Expand/Summary** is selected.

Contract

Enter the contract number.

Lot

Enter the lot number.

Despatch Qty

Enter the quantity to be despatched.

Kanban

Enter the Kanban reference code.



Press **Enter** to display the 856 Maintenance Header Screen.

Functions:

F5

Generate Packs and Pallets. This generates pack and pallet information afresh, replacing the work files. If any pack/pallet/item/customer records are missing an appropriate message will prompt you to manually enter records for those items, but continue to generate details for other items on the consignment where possible. (This is not available in restricted mode).

F6

Add. This allows you to add a new line. The system will display a window with the input fields. Item, Order/Contract and Quantity are mandatory fields.

F9

Restricted Mode/Item & Qty Changes. This toggles between restricted and amend mode, when your User ID has the correct authority level.

F15

Expand/Summary. This is a toggle switch which either shows or hides the second line of information.

856 Maintenance Item Pallet Summary Screen (Option 1)

-  Enter 1 in the Sel field on the 856 Maintenance Item Summary Screen to display the 856 Maintenance Item Pallet Summary Screen.

```

AS430                      Version 3 Demonstration Company   User QA AUT01   14/07/97
                                           10:53:08

856 Maintenance - Item Pallet Summary

Consignment Number .. 000000001      CHG QA STD 856
Customer ..... CG01      000      Automotive customer
                                   31 Lenton Boulevard
Despatch Date ..... 11/06/97      Despatch Time ..... 0:00
Item ..... CGQA1      Despatch Qty ..... 102.000
Lot .....

Sel   Pallet   Type   Tracking Ref.   No. Packs
-     1       QAP           _____      2
      1       QA Pallet
-     2       QAP           _____      2
      2       QA Pallet
-     3       QAP           _____      2
      3       QA Pallet
-     4       QAP           _____      2
      4       QA Pallet
                                           +

1=Details 2=856 Codes 4=Delete
F3=Exit  F5=Refresh F6=Add Pallet F8=Verify Details F12=Previous
F15=Expand/Summarise F17=Consignment Pack Enquiry
      13-03      SF      MK      KS      IM      II KENB20A PED201S2
  
```

Fields:

Sel

Select. The following options are available:

- 1 - Details. Displays the 856 Maintenance Pallet Details Screen.
- 2 - 856 Codes. Displays the 856 Additional Tare Container References Screen.
- 4 - Delete. Deletes a line.

Tracking Ref

Enter the unique tracking reference for this pallet.

-  Select **F8=Verify Details** to validate the data.

Functions:

F6

Add Pallet. This allows you to create a new pallet record, assigning the next pallet number, but allowing amendment. The pallet must be unique within a consignment. The input fields are displayed in a window.

F15

Expand/Summarise. This toggles between displaying/hiding pallet descriptions.

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

856 Maintenance Pallet Details Screen (Option 1)

This screen allows you to maintain the pack range details associated with the selected pallet/item. You can maintain 'actual' weights, volumes, and quantities or select the range to amend.



Enter 1 in the Sel field on the 856 Maintenance Item Pallet Summary Screen to display the 856 Maintenance Pallet Details Screen.

```

AS435                      Version 3 Demonstration Company   User QA AUT01   14/07/97
                                           13:14:01

856 Maintenance - Pallet Details

Consignment number .. 00000001      CHG QA STD 856
Customer ..... CG01      000      Automotive customer
                                           31 Lenton Boulevard

Despatch date ..... 11/06/97      Despatch time ..... 0:00
Pallet ..... 1      Pallet type ..... QAP
Item ..... CGQA1      Despatch Qty ..... 102.000
Contract ..... 00000001      Ref.
Lot .....

Sel From Pack  To Pack Type Net Wt      Gross Wt      Volume      Qty/Pack
-      1      2 QAB      1.000      1.000      1.000      3

1=Amend additional details  2=856 Codes  4=Delete
F3=Exit  F6=Add pack range  F8=Verify details  F12=Previous
F17=Consignment pack enquiry
      15-03      82      MK      KS      IM      II      KENB20A      PED201S2
  
```

Fields:

Sel

Select. The following options are available:

1 - Amend Additional Details. Displays the 856 Maintenance Pack Details Screen which allows you to maintain item and pack details associated with the selected pack.

2 - 856 Codes. Displays the 856 Additional Pack References Screen.

4 - Delete. Deletes a pack range.

From/To Pack

The beginning and end pack numbers which have identical weight, volume etc.

Type

The pack type description from the pack file.

Net Wt

This displays the 'actual' net weight of the pack, and will be the same as the calculated net weight unless it has been manually overridden.

Gross Wt

This displays the 'actual' gross weight of the pack, and will be the same as the calculated gross weight unless it has been manually overridden.

Volume

This displays the 'actual' volume of the pack, and will be the same as the calculated volume unless it has been manually overridden.

Qty/Pack

Shows the quantity of the item in each pack.



Select **F8=Verify Details** to verify the data and display the No Discrepancies window or the Packaging Discrepancies Screen.

Functions:

F6

Add Pack Range. This allows you to add additional item packs to the pallet. The 856 Maintenance Pack Details Screen is displayed for you to enter the new details.

F8

Verify Details. This verifies that the total quantity assigned to the packs/pallets is equal to the quantity being despatched. When F8=Verify Details is selected either a window will be displayed confirming that there are no discrepancies, or the Packaging Discrepancies Screen will be displayed. For more information, refer to the ASN Maintenance Packaging Discrepancies Screen in the Processing option.

F17

856 Maintenance Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

856 Maintenance Pack Details Screen (Option 1/F6)

This screen allows you to maintain the item and pack details associated with the selected pack. It is mainly display, but does allow update on some fields. This screen can be used for entering Pack Marks, Kanban details and amending Lots.



Enter option 1 in the Sel field on the 856 Maintenance Pallet Details Screen to display the 856 Maintenance Pack Details Screen.



Select **F6=Add Pack Range** to display the 856 Maintenance Pack Details Screen.

```

AS440                      Version 3 Demonstration Company   User QAUT01   14/07/97
                                           13:18:29

856 Maintenance - Pack Details

Customer ..... CG01      000      Automotive customer
                                   31 Lenton Boulevard
Consignment Number .. 00000001      Contract Ref. .... 00000001
Item Reference ..... CGQA1      CG QA Item1
Call Off Ref ..... █
Stockroom .....? 01
Lot No .....
Rotation Date ..... 0/00/00      Workstation ..... QPADEV0004

Pallet Ref ..... 1      Pallet Type ..... QAP QA Pallet
Packs . 1 to 2      Pack Type .....? QAB QA Box
Pack Quantity ..... 3      EA Single of
Pack Gross Wt (Calc).. 1.000      Pack Gross Wt (Act).. 1.000
Pack Net Wt (Calc)... .000      Pack Net Wt (Act).... 1.000
Pack Volume (Calc)... 1.000      Pack Volume (Act).... 1.000
Pack Marks .....
Kanban Card Ref .....

F3=Exit F4=Prompt F12=Previous F17=Consignment Pack Details

09-24  S#  MK  KS  IM  II  KENB20A  PED201S2
  
```

Fields:

Call Off Ref

This is the call off reference number.

Stockroom

This is the stockroom code for the item.

Lot No

This is the lot number for the item.

Rotation Date

This is the rotation date for the item.

Workstation

This is the workstation which generated the pallet details.

Pallet Ref

This is the pallet reference number which is a unique identifier for the pallet.

Pallet Type

This is the pallet type code.

Packs

These are the pack reference numbers for the packs in this pallet. These are unique identifiers for each pack.

Pack Type

This is the pack type code used to describe the way in which the item is packed. The **F4=Prompt** key is available.

Pack Quantity

This is the number of items in a pack.

Pack Gross Wt (Calc)

This is the calculated gross weight of the pack.

Pack Gross Wt (Act)

This is the actual gross weight of the pack.

Pack Net Wt (Calc)

This is the calculated net weight of the pack.

Pack Net Wt (Act)

This is the actual net weight of the pack.

Pack Volume (Calc)

This is the calculated pack volume.

Pack Volume (Act)

This is the actual pack volume.

Pack Marks

This identifies particular groups of packs in a consignment.

Kanban Card Ref

This is the Kanban reference card code.



Press Enter to update the data and display the 856 Maintenance Pallet Details Screen.

Functions:

F17

Consignment Pack Details Screen. Select this function to display pallet and pack details for a consignment on the 856 Maintenance Consignment Pack Enquiry Screen.

856 Maintenance Consignment Pack Enquiry Screen (F17)

This is an enquiry screen designed to provide pallet and pack details when you are adding new packaging information to a consignment .



Select **F17=Consignment Pack Details** on the 856 Maintenance Pack Details Screen to display the 856 Maintenance Consignment Pack Enquiry Screen.



Select **F17=Consignment Pack Enquiry** on either the 856 Maintenance Item Pallet Summary or 856 Maintenance Pallet Details Screens to display the 856 Maintenance Consignment Pack Enquiry Screen.

AS470	Version 3 Demonstration Company	User QAUT01	14/07/97	
			13:19:59	
856 Maintenance - Consignment Pack Enquiry				
Consignment		00000001	CHG QA STD 856	
Last Pallet Number Used ..		17	Last Pack Number Used .. 34	
Pallet Type	Pallet Reference	Pack Type	From Pack To Item Lot	
QAP	1	QAB	1 2 CGQA1	
QAP	2	QAB	3 4 CGQA1	
QAP	3	QAB	5 6 CGQA1	
QAP	4	QAB	7 8 CGQA1	
QAP	5	QAB	9 10 CGQA1	
QAP	6	QAB	11 12 CGQA1	
QAP	7	QAB	13 14 CGQA1	
QAP	8	QAB	15 16 CGQA1	
QAP	9	QAB	17 18 CGQA1	
QAP	10	QAB	19 20 CGQA1	
QAP	11	QAB	21 22 CGQA1	
QAP	12	QAB	23 24 CGQA1	+
F12=Previous				
01-02	SP	MK	KS IM II KENB20A PED201S2	

Fields:

Pallet Type

This field is for your information only and cannot be amended.

Pallet Reference

This field is for your information only and cannot be amended.

Pack Type

This field is for your information only and cannot be amended.

From Pack

This field is for your information only and cannot be amended.

To Pack

This field is for your information only and cannot be amended.

Pack

This field is for your information only and cannot be amended.

Lot

This field is for your information only and cannot be amended.



Press **F12=Previous** to display the previous screen.


```
AS425                      Version 3 Demonstration Company    User QA AUTO1           14/07/97
                                                                14:19:38
```

B56 Maintenance - Name and Addresses
Consignment Number .. 00000001 CHG QA STD B56
Customer CG01 000 Automotive customer

Sel Type Code ?		Address Code ?	Override
[F1] CGEE	Consignee (Delivery Customer)	CGEE01	
- PLNO	Plant Number	PLN001	
- FDEL	Final Delivery Point	FDEL01	
- ADES	Additional Destination Details	ADES01	
- FFWD	Freight Forwarder	FFWD01	
- CARR	Transport Carrier Company	CARR01	
_____		_____	
_____		_____	
_____		_____	
_____		_____	
_____		_____	
_____		_____	
_____		_____	
_____		_____	+

1=Details 4>Delete

F3=Exit F4=Prompt F12=Previous

Selections have been abandoned by pressing F12



Override

This field displays a + when the code has been overridden.



Enter 1 in the Sel field on the first 856 Maintenance Name And Addresses Screen and press **Enter** to display the second screen.

856 Maintenance Name And Addresses Screen 2 (Option 1)

This screen displays full details for a selected code, and allows you to make changes to the name and address as required.



Enter 1 in the Sel field on the first 856 Maintenance Name And Addresses Screen and press **Enter** to display the second screen.

AS425	Version 3 Demonstration Company	User QAUT01	14/07/97
			14:21:19
856 Maintenance - Name and Addresses			
Consignment	00000001	CHG QA STD 856	
Despatch Date	11/06/97	Despatch Time	:00
Type code.....	CGEE	Consignee (Delivery Customer)	
Address code.....	CGEE01		
Name.....	Consignee (delivery customer) 01		
Address line 1.....	line1		
Address line 2.....	line2		
Address line 3.....	line3		
Address line 4.....	line4		
Address line 5.....	line5		
Post code.....		Country Code?	___
Telephone number....		Extension number...	___
Fax number.....		Internal ID.....	___
Telex number.....		Teletext number....	___
Contact name.....	___		
Department code....	___		
Comments.....	___		
F3=Exit F4=Prompt F12=Previous			
08-23 SP MK KS IM II KENB20A PED201S2			

Fields:

Type Code

This is the address type code which was entered previously.

Address Code

This is the address code which was entered previously.

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Address Line 5

Enter the fifth line of the required address.

Post Code

Enter the post code.

Country Code

Enter the country code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the contact name as required.

Department Code

Enter the department code for the contact as required.

Comments

This is a free format field. Enter any required comments.



Press **Enter** to validate the screen, then press **Enter** again to save the new details after saving the new details and display the previous screen.

856 Text Window (F22)

This window allows you to maintain external text each 856 ASN consignment.



Select **F22=856 Text** on the 856 Maintenance Header Screen to display the 856 Text Window.

AS410		Version 3 Demonstration Company		User QAUT01	14/07/97
					14:45:35
Advanced Shipping 856 Maintenance - Header					
Consignment number...		00000001	CHG QA STD 856		
Customer.....		CG01	000	Automotive customer	
				31 Lenton Boulevard	
				Road	
Mode of transport.....?		3			
Despatch date.....		11/06/97			
Est. arrival date....		23/07/97			
Supplier code.....?					
Plant number.....?		PLN001			
Final delivery point..?		FDEL01			
Additional dest. code..?		ADES01			
Freight forwarder.....?		FFWD01			
Carrier code.....?		CARR01			
Vehicle registration....					
Trailer reference.....					
ASN map sequence & 856 hierarchic					

Lin External Text	
1	
2	
3	
4	
5	
6	
Position to ____ Insert ____ after ____	
Delete ____ from ____	
F5=Refresh F8=Update F12=Previous	

F3=Exit	F4=Prompt	F8=Update	F10=Additional 856 Details	F12=Previous
F14=Weights & Totals	F15=Items	F21=Name & Addresses	F22=856 Text	
12-42	SA	MK	KS	IM
			II	KENB20A PED201S2

Fields:

Lin

Line Number. This field is for your information only and cannot be amended.

External Text

Enter text on each line as required.

Position To

Enter the line number you want to display at the top of the screen.

Insert

Enter the number of blank lines you want to insert, and the line number after which they should be inserted.

Delete

Enter the number of lines you want to delete, and the line number from which you want to start the delete.



Select **F8=Update** to update the text file and display the 856 Maintenance Header Screen.

Resend ANSIX12 856s



8/ADP

This option lists 856 ASNs which have either already been sent, or cancelled via the ANSIX12 856 Maintenance & Send option. You can maintain the details or resend the 856 ASN.

The Resend ANSIX12 856s selection screen is the same as the ANSIX12 856s Maintenance & Send Screen except it only lists 856 ASNs which have previously been sent or cancelled. The maintenance functions are identical, and re-sending an 856 ASN works in exactly the same way as sending an 856 ASN.

The Resend Screens do not provide a cancel facility, or a Manual Add 856 ASN facility. 856 ASNs may be sent/resent up to eight times.

Record Consignment Stock Consumption



10/ADP

This option allows you to manually record goods taken by customers from a consignment warehouse. It is used when you cannot receive EDI messages.

Record Consignment Stock Consumption Screen 1

This screen allows you to select a customer and consignment stockroom that you want to manually record stock consumption for.



Select Record Consignment Stockroom Consumption from the menu to display the first Record Consignment Stockroom Consumption Screen.

```
AS480          Z1 - GB Demonstration Company  USER GBUBA1MS  15/10/97
                                           9:57:48
Record consignment stock consumption
Customer.....?..
Consignment Stockroom..?.
F3=Exit F4=Prompt
5-28  SR  MW  KS  CL  IM  DM  II  STUD140  KB  PET178S1
Ready  R:05 C:028  ID:a  LU:  NUM
```

Fields:

Customer

Enter the customer number.

Consignment Stockroom

Enter the consignment stockroom code.



Note. You can enter either the customer number, the consignment stockroom code or both.



Press **Enter** to display the second Record Consignment Stock Consumption Screen.

Record Consignment Stock Consumption Screen 2



Press **Enter** from the first Record Consignment Stock Consumption Screen to display the second Record Consignment Stock Consumption Screen.

AS480	Z1 - GB Demonstration Company	USER GBUJA1MS	15/10/97 12:19:48
Record consignment stock consumption			
Customer..... CSSBTEST 001 CSSBTEST			
Consignment Stockroom.... CB		Consignment stockroom1	
Sel Item	Movement Qty.	Lot	UOM Price/Unit
1=Amend			
Item Ref. 1 (1-Cust 2-Supp) Item.?. █			
Movement qty.....		Lot.....?..	
Quantity units....?..		Price/unit.....	
		Reason code.?..	
Ref.no.date		15/10/97	
F3=Exit F4=Prompt F8=Update F12=Previous			
16-38	SA	MW KS CL IM DM II	STUD140 KB PET178S1
Ready	R:16 C:038	ID:a	LU: NUM

Fields:

Sel

Select. Enter 1 to select an item.

Item Ref

Identifies if customer or supplier item reference is used. Enter one of the following:

- 1 - Customer reference.
- 2 - Supplier reference.

Item

Enter the item number.

Movement Qty

Enter the quantity taken from the consignment stockroom.

Quantity Units

Enter the unit quantity code.

Lot

Enter the lot number. This is mandatory if the item is Lot controlled.

Price/Unit

This is displayed from the contract that the stock was consumed against. You can not change this.

Reason Code

Enter the code set up to indicate the reason for the consumption of the goods. This field is optional.

Ref No & Date

Enter the number and date used to identify the transaction. This field is optional.



Select **F8=Update** to confirm the data that you have entered.

Confirm Packaging And Labels



11/ADP

Use this option if you need to create your packs (and print your labels, if you are using labels) before you confirm despatch of the goods. You can create pack and pallet details for an entire consignment, or for selected lines within the consignment.

Once you have created the pack and pallet details, you can if you wish print shipping labels for the consignment. You can also print a packing control log, which is a printed summary of which items or packs belong on which pallets.

This packing information can be amended many times up to the time the ASN has been sent for the consignment.

Confirm Pack Selection Screen



Take the Confirm Packaging And Labels option from the menu to see the Confirm Pack Selection Screen.

AS150	Z1 - GB Demonstration Company	User GBJBANB1	25/02/98 10:19:18
Advanced Shipping Confirm Pack			
Customer.....?.. <u>AUTOCUS1 000</u>			
Despatch date..... <u>0/00/00</u>			
OR			
Consignment no...?.. <u>00000357</u>			
F3=Exit F4=Prompt			

Fields:

Customer

Enter the customer and relevant address.

Despatch Date

Enter the despatch date.

Consignment No

Enter the consignment number.



Select the consignment you wish to pack on the Confirm Pack Selection Screen, then press **Enter** to see the Confirm Pack Screen.

Confirm Pack Screen

-  Select the consignment you wish to pack on the Confirm Pack Selection Screen, then press **Enter** to see the Confirm Pack Screen.
-  The other ways into this screen are via the Consignment Confirm Despatch option, the Fastpath Shipping option, and the ASN Maintenance And Send option.
-  *If you enter this screen from the ASN Maintenance And Send option, then a lot number is displayed for each line.*

Each line on this screen is a summary of the lines on the consignment with the same item, contract and RAN.

```

AS150              Z1 - GB Demonstration Company   User GBJBANB1   25/02/98
                                                    10:20:14

Advanced Shipping - Confirm Pack

Consignment number.. 00000357   GTEST
Customer.....     AUTOCUS1 000   Automotive customer eg ROVER
Despatch date.....   98/02/24     Despatch time..... 14:16

Sel      Item      Contract Lot      Ship      Packed      Despatch
      Item      Number Reference Quantity Quantity Quantity
- F-ITEM1      DOC1      RAN/Ref      10.000      15      10.000
  FORDNET ITEM 1 (COST'S' LOT 'N')

1=Maintain Pack Details
F6=Create Pack/Pallet Details  F8=Update  F9=Update/Print Ship Labels
F3=Exit  F12=Previous  F13=Detail/Summary
  
```

Fields:

Sel

Selection field.

1 - Maintain pack details manually. You would select this option if you wish to enter your own customer's pack references, for example. You can change the packed quantity before selecting this option, as long as the consignment has not yet been despatched.

This option takes you into the Manual Packing Maintenance Screen.

Packed Quantity

For items which are not yet packed or despatched, this field is 0.

For items which are packed but not yet despatched, this field shows the total quantity that has been packed for the item, contract and RAN.

This field is maintainable only if the consignment has not yet been despatched. If it has, then you can still amend the packing details, but you cannot confirm the pack until the Packed Quantity field equals the Despatch Quantity field.

Functions:

F6

Create Pack/Pallet Details. The system will create the pack details for you. If these already exist, you will be warned (see the Warning Window), and can either accept the existing packs or repack the consignment.

When you are confirming the pack details, if some items are batch or lot controlled, you will see the Order Entry Batch/Lot Number Window. You must enter the batch/lot numbers to be assigned to the consignment.

F8

Update. Update the pack and pallet details.

When you are confirming the pack details, if some items are batch or lot controlled, you will see the Batch/Lot Number Window. You must enter the batch/lot numbers to be assigned to the consignment.

F9

Update/Print Ship Labels. This updates the pack and pallet details, and prints shipping labels for the consignment.

This key is only available if shipping labels are required by this customer for this consignment. It is unavailable if you accessed this screen via the ASN Maintenance And Send option, because you must update the ASN before printing labels.

When you are confirming the pack details, if some items are batch or lot controlled, you will see the Batch/Lot Number Window. You must enter the batch/lot numbers to be assigned to the consignment.

F13

Detail/Summary. When you first enter this screen it displays two lines of details for each item, including the item description and RAN/Call Off Reference. If you wish to reduce this to a single line of detail, so you can see more items on the screen, then select **F13=Detail/Summary**, and you will see the summary format. You can toggle between the two formats.



Enter 1 against an item and press **Enter** to see the Manual Packing Maintenance Screen.

Warning Window



Select **F6=Create Pack/Pallet Details** from the Confirm Pack Screen to see the Warning Window.

If pack and pallet details exist for this consignment, you will see the Warning Window.

Fields:

Proceed

0 - This simply returns you to the Confirm Pack Screen, and does no processing.

1 - This regenerates the packing of the whole consignment, and generates new package label numbers.



Press **Enter** to proceed.

Manual Packing Maintenance Screen



Enter 1 against a consignment line on the Confirm Pack Screen and press **Enter** to see the Manual Packing Maintenance Screen.

This screen lets you change the packing details recommended by the system.

AS160	Z1 - GB Demonstration Company	User GBJBANB1	25/02/98 10:35:47																								
Advanced Shipping - Manual Packing Maintenance																											
Consignment number. 00000357 Item... F-ITEM1																											
Contract/RAN ref... D0C1 /																											
Customer..... AUTOCUS1 000 Automotive customer eg ROVER																											
Units..... EA Minimum layers.. 1																											
Quantity to pack... 10 Layers/pallet... 1 Complete layers. 0																											
Packed quantity.... 10 Packs/layer..... 1 Odd Packs..... 0																											
<table border="1"><thead><tr><th>Sel</th><th>Pallet Reference</th><th>Pallet Type</th><th>Pack No From</th><th>Pack No To</th><th>Pack Type</th><th>Qty per Pack</th><th>Lot Number</th></tr></thead><tbody><tr><td>-</td><td>2000085</td><td>PAL</td><td>3000088</td><td>3000088</td><td>BOX</td><td>5</td><td></td></tr><tr><td>-</td><td>2000086</td><td>PAL</td><td>3000089</td><td>3000089</td><td>BOX</td><td>5</td><td></td></tr></tbody></table>				Sel	Pallet Reference	Pallet Type	Pack No From	Pack No To	Pack Type	Qty per Pack	Lot Number	-	2000085	PAL	3000088	3000088	BOX	5		-	2000086	PAL	3000089	3000089	BOX	5	
Sel	Pallet Reference	Pallet Type	Pack No From	Pack No To	Pack Type	Qty per Pack	Lot Number																				
-	2000085	PAL	3000088	3000088	BOX	5																					
-	2000086	PAL	3000089	3000089	BOX	5																					
1=Maintain Range 2=Maintain Pallet 4=Delete																											
F3=Exit F5=Refresh F6=New Range F7=New Pallet F10=Confirm changes F12=Prev.																											

Fields:

Sel

Selection field.

- 1 - Maintain the range. This brings up the Maintain Range Window.
- 2 - Maintain pallet. This brings up the Maintain Pallet Window.
- 4 - Delete and existing range.
- 5 - Maintain 856 pallet codes. This option is only available to customers for whom the ANSI 856 ASN features have been set.
- 6 - Maintain 856 pack codes. This option is only available to customers for whom the ANSI 856 ASN features have been set.

Functions:

F5

Refresh. Use this key to recalculate the total packed quantity for this item/contract/RAN. This result is displayed in the Packed Quantity field towards the top of the screen.

F6

New Range. Enter a new range. This brings up the Maintain Range Window.

F7

New Pallet. Enter a new pallet. This brings up the Maintain Pallet Window.

F10

Confirm Changes. When you have made all necessary changes, select this key to confirm your changes. The total quantity for the pack ranges must equal the total quantity to be packed, and the quantity packed for each lot number must equal the quantity shipped or confirmed for the lot. The system warns you of any discrepancy.



Either select an existing range with 1 or select **F6=New Range** to see the Maintain Range Window.

Maintain Range Window



Either select an existing range with 1 or select **F6=New Range** on the Manual Packing Maintenance Screen to see the Maintain Range Window.

```
AS160                Z1 - GB Demonstration Company    User GBJBANB1    25/02/98
                                      10:21:54

Advanced Shipping - Manual Packing Maintenance

Consignment number. 00000357  Item... F-ITEM1
Contract/RAN ref... D0C1      /
Customer..... AUTOCUS1 000 Automotive customer eg ROVER
Units
Quant
Packe
Pallet No.. 2000064    No. of Packs.. 1    *Amend    s. 0
Pack range. 3000068    to 3000068    .. 0
Pack type.? BOX Qty per Pack. 5 Label Format?. C01
Lot Number...
Sel 1 Weight Net.. .000 Gross.. .500
- Volume..... .500
- Pack Marks... Kanban...
F4=Prompt F8=Update F12=Previous

1=Maintain Range 2=Maintain Pallet 4=Delete
F3=Exit F5=Refresh F6=New Range F7=New Pallet F10=Confirm changes F12=Prev.
```

Fields:

Pallet No

Enter a pallet number which already exists on this consignment. It must exist for the item currently being packed.

No Of Packs

If you want to create new packs, then leave the range fields blank and enter the number of packs you wish to create. The system assigns the pack numbers.

Pack Range

Enter the pack range. If you have entered a value in the No Of Packs field, you must leave the range fields blank.

Pack Type

Enter a valid pack type.

Qty Per Pack

This field is used to calculate the packed quantity, and is also used in weight and volume calculations.

Label Format

Enter a label format for the pack. This is only valid if you are printing shipping labels.

Lot Number

You must enter a lot number if the item you are packing is batch/lot controlled. The exception to this is dummy packs, where the quantity per pack is zero.

Weight Net

If you enter a weight, it must not be zero unless the quantity per pack is zero (that is, it is a dummy pack).

If you do not enter a weight, the system will calculate it.

Gross

If you enter a gross weight, it must not be zero unless the quantity per pack is zero (that is, it is a dummy pack).

If you do not enter a gross weight, the system will calculate it.

Volume

If you enter a volume, it must not be zero unless the quantity per pack is zero (that is, it is a dummy pack).

If you do not enter a volume, the system will calculate it.

Pack Marks

This is an optional memo field.

Kanban

This is an optional memo field.



Select **F8=Update** to accept your changes and return to the Manual Packing Maintenance Screen.

Maintain Pallet Window



On the Manual Packing Maintenance Screen, either select an existing range with 2 or select **F7=New Pallet** from to see the Maintain Pallet Window.

```
AS160                Z1 - GB Demonstration Company    User GBJBANB1    25/02/98
                                      10:23:45

Advanced Shipping - Manual Packing Maintenance

Consignment number. 00000357  Item... F-ITEM1
Contract/RAN ref... D0C1      /
Customer..... AUTOCUS1  000  Automotive customer eg ROVER
Units..... EA              Minimum layers.. 1
Quantity to pack... 10      Layers/pallet... 1  Complete layers. 0
Packed quant      dd Packs..... 0

Pallet
Sel  Referen
 2   20000
-   20000
-   20000

Pallet No..... 2000064      *Amend
Pallet Type?... PAL
Label Format?... P01
Tracking Ref....

F4=Prompt F8=Update F12=Previous

1=Maintain Range 2=Maintain Pallet 4=Delete

F3=Exit F5=Refresh F6=New Range F7=New Pallet F10=Confirm changes F12=Prev.
```

Fields:

Pallet No

Enter the relevant pallet number, if no default is there. The pallet number must be unique for this shipment.

Pallet Type

Enter a valid type.

Label Format

Enter an existing label format.

Tracking Ref

This is an optional memo field.



Press **F8=Update** to keep your changes.

Print Shipping Labels Screen



Select **F9=Update/Print Ship Labels** from the Confirm Pack Screen to see the Print Shipping Labels Screen.

There are five ways of arriving at this screen:

From within the Consignment Confirm Despatch option.

From within the Fastpath Confirmation option.

From within the Confirm Packaging And Labels option.

From the ASN Maintenance & Send option.

From within the ANSI12 856 Maintenance & Send option.

This screen enables you to select shipping labels to print.

AS520		Z1 - GB Demonstration Company		User GBJBANB1	25/02/98 10:28:49	
Advanced Shipping - Print Shipping Labels						
Customer .. AUTOCUS1 000		Automotive customer eg ROVER Unit 5				
Despatch Date .. 98/02/24		Consignment : 00000357				
Despatch Time .. 14:16		GTEST				
Label Sel	Format Code	Description		No of Copies	Total Labels	Unprinted Labels
<u>1</u>		Packing Control Log		1	0	0
<u>1</u>	C01	Pack:Standard	(Odette V1R4)	1	1	0
<u>1</u>	P01	Pallet:Single Item	(Odette V1R4)	2	2	0
						Bottom
1=Select for printing						
F8=Print all Labels F9=Print Unprinted Only F12=Previous						

Fields:

No Of Copies

This displays the number of physical copies of each individual label that will be printed.

Total Labels

This is the number of packs multiplied by the number of labels per pack. The result is the total number of physical labels which the printer will print.

Unprinted Labels

This displays the total number of labels, either new or amended, which are not yet printed.

Sel

Selection field.

1 - Select the label for printing. All the Sel fields are preset to this value by the system. Once you have printed the labels, all the Sel fields are reset to empty, except the one against the Packing Control Log, which stays set to 1 unless you change it.

Packing Control Log

This is an audit report of the consignments you have packed, in pallet within consignment order. It prints a record of the range numbers, contract numbers, items, and so on.

Functions:

F8

Print All Labels.

F9

Print Unprinted Only.