

-
-
-
-
-

Chapter 1

Maintenance



Model Maintenance



1/FCM

You use this procedure to create and maintain Forecasting Models. You can use these Models to create and transfer forecasts for individual locations or groups of locations.

Maintain Model Selection Screen



Select Model Maintenance.

Use this screen to select the Model and Stockrooms you want to maintain.

FC100	Z1 - Demonstration Company	USER SP1	6/09/94 16:14:24
Maintain Model - Select			
Model.....?.. <u>C1</u> Include all Stockrooms <u>0</u> (0=No 1=Yes)			
F3=Exit F4=Prompt			

Fields:

Model

Select the two-character Model Code. To create a new model, enter a new model code.

Include All Stockrooms

When you create a new Model, enter one of the following:

- 0 - To manually enter individual stockroom codes.
- 1 - To include all stockrooms in the Model.

The system will then display all existing stockrooms, as defined in Inventory Management, in the maintenance screen. You can delete stockrooms not required for the Model.



Note: When maintaining an existing model, enter 0 to maintain stockrooms individually.



Press **Enter**. If this is a new model the system displays a confirmation window:
Model Code not known to the application. Select **F8=Update** to add or **F12=Previous** to reselect.



Press **Enter** to display the Maintain Model Details screen.

Model Type 2 must have a DRP Centre as its destination.

Model Type 3 must have a Production Model as its destination.

Model Type 4 cannot have any destination - the target model must be blank.

Simulation Period

Enter the number of periods used when comparing forecasts with actuals to decide which forecasting method to use.

It is normally set to 3, but must be in the range 0 - 13.

Enter Stockrooms To Be Included

Enter the stockroom codes you wish to include in the Model. Blank out any stockrooms that you do not require.



Press **Enter** to check all fields on the screen

Or select **F8=Update** to check all fields on the screen and exit.

Profile Maintenance



2/FCM

You use this option to maintain a profile for each group of items, and individual items, within each Model in the Forecasting application.



Warning: The application only processes groups and items that have a profile defined. The Transfer Product Details processing option creates these profiles, therefore you should run this processing option before maintaining item/group profiles.

Profile Maintenance Selection Screen



Select Profile Maintenance

Use this screen to enter the selection criteria for Group/Item Profile Maintenance.

FC005	Z1 - Demonstration Company	USER SP1	6/09/94 16:15:03
Group/Item Profile Maintenance - Select			
Model...?.. <u>C1</u>	Midlands DRP Centre		
Group...?.. <u>3</u>	Sun Protection		
Item...?.. <u>5001</u>	Suncream Factor 4 225ml		
F3=Exit F4=Prompt			

Fields:

Model

Enter the Model code to specify the Forecasting Model you want to maintain the Group/Item profile.

Group

Select a Group code.



Note: A Group code is a Minor Item Group extracted from the Inventory application, (using the Transfer Product Details processing option).

Item

Optionally enter an Item code. The code must be extracted from Inventory.



Note: If you enter a Group code with Item left blank, then the system displays the details screen for the specified Group. If you enter both codes, the system displays the details screen for the specific item.



Press **Enter** to display the Profile Maintenance Details screen.

Profile Maintenance Details Screen



To display this screen, specify a forecast model, forecast group, and optionally an item, on the Profile Maintenance Selection screen and press **Enter**.

Use this screen to maintain profile details for the selected item, or group of items within the selected Model. You can also maintain text.

FC005	Z1 - Demonstration Company	USER SP1	6/09/94 16:15:07
Profile Maintenance - Details			
Model..... C1 Forecast Group..... 3 Item..... 5001			
Description..... Suncream Factor 4 225ml			
Lock in Forecast...?		Simulation Period..... 3	
Cost Price..... - 52.000		Sales Price..... 105.0000	
Conversion Factor.... .0000			
8	.00	9	.00
11	.00	12	.00
1	.00	2	.00
4	.00	5	.00
7	.00	6	.00
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Text			

Fields:

Any details found for this selection are displayed and are available for input.

Description

Enter a description for the Group or Item.

Lock In Forecast

Enter a code for the Forecast Method required for this item.

Leave this field blank for the application to select a forecasting method in the Period-end run. Otherwise enter * to specify that you want to manually forecast the item, that is, to accept the item, but not perform forecasting calculations upon it.



Note: You can enter manual forecasts through the Forecast Manipulation option.

Simulation Period

Enter the length of the simulation period. If the currently used company profile has 13 periods defined per year, then the valid range is from 0 to 13, otherwise from 0 to 12.

During the Period End Run the value entered here determines the number of periods to which the Forecast method is applied in simulating the actual demand.

If zero for an Item, the system used the period defined for the Group. If both periods are zero (Item and Group) then the system uses a default value of 3.

Cost Price

Enter the cost price of the item. The default is one of the following, depending on the settings of the item's inventory details:

1. The latest cost value from the stockroom balance record if you have set the item's costing to latest.
2. The average cost value from the stockroom balance record if you have set the item's costing to average.
3. The standard cost value from the stockroom balance record if you have set the item's costing to standard.
4. If the item's costing method is blank, the system uses the costing method from the Inventory Company Profile to determine the cost used from the stockroom balance record.

Sales Price

This is the sales price of the item. It defaults to the Base List Price from Inventory Management.

Conversion Factor

Optionally enter a factor to convert items sold in different pack sizes into equivalent units. If you enter either a 0 or 1 the quantities are not converted. Otherwise the conversion factor is applied if you have set the appropriate flag on the Company Profile to yes.



Note: The cost price, sales price and conversion factor are blank if maintaining a group profile.

Marketing Masks

These fields are not named on the screen. You may optionally enter 12 or 13 sets of adjustment factors, depending on whether the current company profile supports 12 or 13 periods per year. These adjustment factors correspond to the next 12 or 13 periods respectively. They are used to multiply the original forecast to produce a final forecast. They are also used to adapt the calculated forecast to a changing market situation that is not evident from the sales history.

If the factor is 1 or 0 the forecast is unchanged.

These masks are used in the Forecast Period-end run. If all the masks for an item are zero, the application applies the masks for it's group, if any.

Example: Entering 1.10 adds 10% to the original forecast.



Select **F11=Delete** to delete the profile from the file. This action writes an audit record.



Note: New profiles are written by the Transfer Item Details processing run. This creates profiles for new Minor Item Groups and new items.

Functions:

F15

Text: Display Text screen for this Group or particular item



Select **F8=Update** to write the details to the Group/Item Profiles file. An audit record is also written with before and after images.

Maintain Text Window (F15)



To display this window, select **F15=Text** on the Profile Maintenance Details screen.

Use this window to maintain text for the selected Group of Items, or for a specific Item within the selected Forecasting Model.

Any lines of text found for this Group or Item are displayed.

FC005	Z1 - Demonstration Company	USER SP1	6/09/94 16:15:37																		
Profile Maintenance - Details																					
Model..... C1	Forecast Group..... 3	Item..... 5001																			
Description..... Suncream Factor 4 225ml																					
Lock in Forecast...?	-	Simulation Period.....	3																		
Cost Price.....	52.000	Sales Price.....	105.0000																		
Conversion Factor....		Maintain Text																			
8	.00	9																			
11	.00	1																			
1	.00	2																			
4	.00	5																			
7	.00																				
<table border="1"> <tr> <th>Lin</th> <th>Text</th> </tr> <tr> <td>1</td> <td>This item is NOT to be locked into</td> </tr> <tr> <td>2</td> <td>any particular Forecast Method.</td> </tr> <tr> <td>3</td> <td></td> </tr> <tr> <td>4</td> <td></td> </tr> <tr> <td>5</td> <td></td> </tr> <tr> <td>6</td> <td></td> </tr> <tr> <td colspan="2">Position ____ Insert ____ after ____</td> </tr> <tr> <td colspan="2">Delete ____ from ____</td> </tr> </table>				Lin	Text	1	This item is NOT to be locked into	2	any particular Forecast Method.	3		4		5		6		Position ____ Insert ____ after ____		Delete ____ from ____	
Lin	Text																				
1	This item is NOT to be locked into																				
2	any particular Forecast Method.																				
3																					
4																					
5																					
6																					
Position ____ Insert ____ after ____																					
Delete ____ from ____																					
F3=Exit F4=Prompt F8=Update		F5=Refresh F8=Update F12=Previous																			

Fields:

Text Lines

Enter up to 99 lines of text. Use the Page Up and Page Down keys to view.

Position To

Specify the line number to position at the top of the window and press **Enter**.

Insert Lines

Specify the number of blank lines to insert and the line number after which to begin insertion. Press **Enter** to insert.

Delete Lines

Specify the number of lines to delete and the line number at which to begin deletion. Press **Enter** to delete.

Functions:

F5

Refresh: Re-display text details as at last update.



Select **F8=Update** to update the file.

Demand History Maintenance



3/FCM

You use this option to maintain the last 3 years' sales history, for either a Group of items or a specific item within a selected Forecasting Model.

Initially extract the history using the Transfer Full Sales History processing run, and then use the Period-end run to maintain it.



Note: If you do not run the Transfer Full Sales History process before maintaining demand history, all fields on the detail screen are zero.

Demand History Maintenance Selection Screen



Select Demand History.

Use this screen to select the Forecasting Model and the Group or Item for which you want to maintain Demand History.

FC017	Z1 - Demonstration Company	USER SP1	6/09/94 16:16:04
Demand History Maintenance - Select			
Model.....?	<u>C1</u>	Midlands DRP Centre	
Group.....?	<u>3</u>	Sun Protection	
Item.....?	<u>5001</u>	Suncream Factor 4 225ml	
F3=Exit F4=Prompt			

Fields:

Model

Specify the Forecasting Model for which you want to maintain demand history.

Group

Enter a Group Code.

Item

Optionally enter an Item code. This code must be extracted from Inventory.



Note: If you enter a Group code, with Item left blank, the system displays the details screen for this Group of Items. If you enter both codes, the system displays the details screen for the specific item.



Press **Enter** to display the Demand History Maintenance Details screen.

Demand History Maintenance Details Screen



To display this screen, specify a forecast model, forecast group, and optionally an item, on the Demand History Maintenance Selection screen and press **Enter**.

Use this screen to maintain the last 3 years of sales history for the selected Item or Group of items within the selected Forecasting Model.

FC017	Z1 - Demonstration Company	USER SP1	6/09/94 16:16:05
Demand History Maintenance - Details			
Model..... C1	Group..... 3	Item..... 5001	
Suncream Factor 4 225ml		Delete Forecast (1=Yes,0=No). <u>1</u>	
Period	91/92	92/93	93/94
8	10	15	195
9	25	30	210
10	40	45	225
11	55	60	240
12	70	75	255
13	85	90	270
1	100	105	285
2	115	120	300
3	130	135	315
4	145	150	330
5	160	165	345
6	175	180	360
7	190	200	400
F3=Exit F8=Update F12=Previous			

Fields:

Model

This is the forecast model selected.

Group

This is the selected group.

Item

This is the item selected.

Description

This field is not named on the screen, but contains a description for the Group or Item from the profile record.

Delete Forecast

Identify whether you wish to delete the Item and/or Item Group forecasts.

The default is to delete the forecasts when the history is amended, ensuring that misleading forecasts are not retained. Enter 0 if you do not want to delete this information.

The system displays any sales history quantities found for the selected item, or group of items.

Period

You can change any of the 36 or 39 quantities, depending on the period parameter in the company profile.



Select **F8=Update**. The quantities are written to the Demand History file, and before/after images written to the Demand History Audit file.

Last Period Demand



4/FCM

You use this procedure to maintain the last Period's sales history quantity for a group of items, or a specific item within a selected Forecasting Model. This quantity is originally extracted by the Transfer Last Period Sales processing option, and is updated in the Demand History, and zeroised, by the Period-end run.

Last Period Demand Maintenance Selection Screen



Select Last Period Demand.

Use this screen to select the Forecasting Model and the Group or Item for which you wish to maintain Last Periods Sales History.

FC020	Z1 - Demonstration Company	USER SP1	6/09/94 16:16:31
Last Periods Demand Maintenance - Select			
Model.....?..	C1	Midlands DRP Centre	
Group.....?..	3	Sun Protection	
Item.....?..	5001	Suncream Factor 4 225ml	
F3=Exit F4=Prompt			

Fields:

Model

Enter a Model Code to specify the Forecasting Model for which you wish to maintain last period's demand history.

Group

Enter a Group code.

Item

Optionally enter an Item code. This code must be extracted from Inventory.



Note: If you enter a Group code with Item left blank, the system displays the details screen for this Group of Items. If you enter both codes, the system displays the details screen for the specific item.



Press **Enter** to display the Last Period Demand Maintenance Details screen.

Last Period Demand Maintenance Details Screen



To display this screen, specify a forecast model, forecast group, and optionally an item, on the Last Period Demand Maintenance Selection screen and press **Enter**.

Use this screen to maintain the quantity extracted as the Last Period's Demand, for this selected group of items or individual item within the selected Forecasting Model.

FC020	Z1 - Demonstration Company	USER SP1	6/09/94 16:16:33
Last Periods Demand Maintenance - Details			
Model..... C1	Group..... 3	Item..... 5001	
Suncream Factor 4 225ml			
Demand.....	<u>345</u>		
F3=Exit F8=Update F12=Previous			

Fields:

Model

This is the forecast model selected.

Group

This is the selected group.

Item

This is the item selected.

Description

This field is not named on the screen, but displays the description for the Group or Item, from its profile record.

Demand

You can change the current figure for last periods demand by overtyping it and then selecting **F8=Update**.



Note: Before and after images are written to the Demand History Audit File.



Select **F8=Update** to write this quantity to the Demand History File.

DRP Spread Profile



11/FCM

You use this option to specify how you wish to spread the period forecasts created by Forecasting over the weekly DRP forecast records. You must do this for each Centre or DC in DRP you wish to transfer forecasts.

DRP Spread Profile Maintenance Selection Screen

 Select **DRP Spread Profile**.

Use this screen to select the **DRP location (Centre or DC)**, and calendar year you want to maintain.

FC021

Z1 - Demonstration Company

User SP1

6/09/94
16:16:49

DRP Spread Profile Maintenance - Select

Centre/DC.....?.. C1

Year..... 94

F3=Exit F4=Prompt

Fields:

Centre/DC

Enter a **DRP Centre or DC** code.

Year

Enter a year in **YY** format.

 Press **Enter** to display the **DRP Spread Profile Maintenance Details** screen.

DRP Spread Profile Maintenance Details Screen



To display this screen, enter a Centre/DC and year on the **DRP Spread Profile Maintenance Selection** screen and press **Enter**.

Use this screen to specify how to spread each periodical forecast over the weeks within the period.

FC021	Z1 - UK Demonstration Company	User GBJBANB4	9/04/98 10:41:35
DRP Spread Profile Maintenance - Details			
Centre/DC..... C1 AS			
Year..... 98		Period..... 1	
Week	Period Start Date	No. working days	Percent of Period
1	5/01/98	0	0
2	12/01/98	1	25
3	19/01/98	5	25
4	26/01/98	5	50
F3=Exit F8=Update F12=Previous			

Fields:

Centre/DC

This is the **DRP Centre** or **DC** code selected.

Year

This is the entered year.

Period

This is the forecasting period number in the range 01 - 13. The system displays one screen per period.



*Note: For each period, the system displays all weeks starting on a Monday, together with the number of working days in the week. These details are obtained from the **DRP calendar** defined to this Centre or DC.*

Week

Week number within the **DRP** associated Calendar.

Period Start Date

The date of the first day of the DRP week in this period.

No. Working Days

As specified in the DRP calendar, the number of working days in this week.

You can enter information for the following:

Percent Of Period

Enter the percentage of the period forecast you want to apply to this week.



Warning: A warning message is displayed if the total percentage for the period is not 100%



Select **F8=Update** to write the entered period percentages to the Spread Profiles file. The screen is redisplayed for the next period. After you reach year end (period 12 or 13) the system displays period 1 details again.

MPS/MRP Spread Profile



12/FCM

You use this procedure to specify how to spread the period forecasts created by Forecasting over the weekly MPS/MRP forecast records. You must do this for each Model defined to Production into which you wish to transfer forecasts.

MPS/MRP Spread Profile Maintenance Selection Screen

 Select MPS/MRP Spread Profile.

Use this screen to select the Model and calendar year you want to maintain.

FC041

Z1 - Demonstration Company

User SP1

06/09/94
11:24:55

MPS/MRP Spread Profile Maintenance - Select

Model Number...?.. ?

Year..... 9

Select Model

	Model Description.
1	01 Production Model

1=Select

Position to:

F12=Previous

F3=Exit F4=Prompt

Fields:

Model Number

Enter a valid Production Model Number.

Year

Enter a valid year, for example 95 for 1995.

 Press **Enter** to display the MPS/MRP Spread Profile Maintenance Details screen.

MPS/MRP Spread Profile Maintenance Details Screen



To display this screen enter a Model Number and Year on the MPS/MRP Spread Profile Maintenance Selection screen and press **Enter**.

Use this screen to specify how to spread each period forecast over the weeks within the period.

FC041	Z1 - Demonstration Company	User SP1	06/09/94 11:25:30
MPS/MRP Spread Profile Maintenance - Details			
Model Number..... 01		Year..... 94	Period..... 1
Week	Period Start Date	No. working days	Percent of Period
1	3/01/94	5	25
2	10/01/94	5	25
3	17/01/94	5	25
4	24/01/94	5	25
F3=Exit F8=Update F12=Previous			

Fields:

Period

Period number in Forecasting, in the range 01 - 13 inclusively.



Note: The system displays one screen per period.



Note: For each period, the system displays all weeks starting on a Monday, together with the number of working days in the week. Enter the percentage of the period forecast you wish to transfer against each week.

Week

Week number within the MPS/MRP Calendar.

Period Start Date

Week commencing date, in the relevant date format.

No Working Days

As defined in the MPS/MRP calendar, the number of working days in this week.

You can enter the following:

Percent Of Period

Enter the percentage of the period forecast you wish to apply to this week.



Warning: If the sum of the total period percentages does not equal 100 the system displays a warning message.



Select **F8=Update** to write the period percentages to the Spread Profiles file. The screen is redisplayed for the next period. After the you reach year end (period 12 or 13) the system displays period 1 details again.