

-
-
-
-
-

Chapter 3

Enquiries



Outstanding Orders



14/TPP

Use the outstanding orders enquiry to review pending transport requirements that are awaiting assignment to specific loads. Transport Planning presents the details in the same manner as those for the build loads function.

Enquire On Outstanding Orders Selection Screen



To display this screen, select Outstanding Orders (Enquiry).

Use the criteria on this screen to select the outstanding orders you want to display the details for.

TP260A Z1 - Demonstration Company User SP1 4/04/95
 Demonstration Transport Centre 14:54:31

Enquire On Outstanding Orders

Ship date..... 1/01/94 to 4/04/95

Route from.....?.. _____

Drop..... _____

Route to.....?.. _____

Drop..... _____

OR

Carrier.....?.. _____

OR

Origin.....?.. _____

Destination.....?.. _____

Summary/detail..... 1 (1=Drops,2=Orders)

F3=Exit F4=Prompt

Fields:

Ship Date

Enter the ship date range for which you want to review orders. This defaults to today's date plus the planner's time fence days for planning.

Route From and Route To

Enter the range of routes for which you want to review order requirements.

Drop (Sequence From) and Drop (Sequence To)

Enter the range of drop sequences for which you want to review order requirements for a particular route.

Carrier

Enter the internal or external carrier for which you want to review orders.

Origin

Enter the start point for which you want to review orders.

Destination

Enter the end point for which you want to review orders.

Summary/Detail

Enter one of the following:

- 1 - To summarise transport requirements by drop for a particular delivery point.
- 2 - To detail transport requirements by order or despatch note number for a particular delivery point.



Enter the selection information and then press
Enter to display the Enquire on Outstanding
Orders Detail Screen.

Enquire On Outstanding Orders Detail Screen



To display this screen, on the Enquire On Outstanding Orders Selection Screen, enter the selection information and then press **Enter**.

This screen displays the customer, route, drop and gross weight of all outstanding orders.



*Note: To change the information displayed on this screen, select **F14=Orders/Drops** or **F15=Weight/Volumes**.*

TP260B	Z1 - Demonstration Company	User SP1	4/04/95
	Demonstration Transport Centre		14:54:49
Enquire On Outstanding Orders			
Ship date	Ship Route	Drop	Gross weight
Customer			Vehicle type
23/08/94	BHAM	010	972.9 2.2
— The Make-Up Shop			16T
23/08/94	CANBS	010	49.4 .3
— Bunting Pharmaceuticals			16T
23/08/94	YORKS1	010	22.5 .9
— Reeves Chemist's			38T
26/08/94	YORKS1	010	.3 .0
— Reeves Chemist's			38T
31/08/94	YORKS1	010	1.6 .1
— Reeves Chemist's			38T
2/09/94	BHAM	010	32.3 .6
— The Make-Up Shop			16T
2/09/94	BHAM	020	68.1 .8
— A & G Chemicals Ltd			16T
1=Load details 2=Delivery profile enquiry			+
F3=Exit	F5=Refresh	F12=Previous	F14=Orders F24=More keys

Transport Planning highlights orders with external text, by a flashing asterisk.

Transport Planning displays a flashing asterisk, against the customer delivery point code and customer names, for all customers who require delivery confirmation. You set this flag to draw the planner's attention to specific delivery time slots or planner text or both, assigned to the delivery point (this usually indicates fixed delivery requirements).

Fields:

S

Selection field. Enter one of the following:

- 1 - To display the load details enquiry.
- 2 - To display the delivery profile enquiry.
- 3 - To display the sales order enquiry (at order level).



Note: Transport Planning selects the outstanding order requirements according to the original

selection criteria you entered.

Functions:

F14

Orders / Drops. Use this function to toggle the display between order and drop information for customers.

F15

Volume / Weight. Use this function to toggle the display between volume and gross weight capacities for transport requirements.

F16

Pending loads. Use this function to display pending loads headers that conform to the selection criteria.



To leave the enquiry, select **F3=Exit**.

Load Details Enquiry



15/TPP

Use this enquiry to review loads at various stages through their process. You can review load details, drops and order information.

You can access most of the screens in this enquiry from several different options and functions and from the Loads by Order Enquiry. The product information only includes one access method for each screen.

Load Details Enquiry Selection Screen



To display the Load Details Enquiry Selection Screen, select Load Details (Enquiry).

Use this screen to enter the selection criteria for the Load Details Enquiry.

TP265	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:00:06
Load Details Enquiry			
Ship date.....	13/03/95	to 13/03/95	
Load status.....?	10	to 90	
Route from.....?	_____		
Drop.....	_____		
Route to.....?	_____		
Drop.....	_____		
OR			
Carrier.....?	_____		
OR			
Origin.....?	_____		
Destination.....?	_____		
OR			
Load number.....	_____		
F3=Exit F4=Prompt			

Fields:

Ship Date

Enter the ship date range for which you want to review orders. This defaults to today's date plus the planner's time fence days for planning.

Load Status

Enter a range of transport load statuses for enquiry.

You define the statuses in the Inventory descriptions file under a major type TPLS.

Route Range

Enter the route range for which you want to review loads.

Drop Range

Enter the drop range, assigned to a delivery point along a particular route, for which you want to review loads.

Carrier

Enter the carrier for which you want to review loads.

Origin

Enter the origin or start point for which you want to review loads.

Destination

Enter the destination or end point for which you want to review loads.

Load Number

Enter the reference of the load you want to review.



To display the Select Load Detail Screen, enter the selection criteria and press **Enter**.

Select Load Detail Screen



To display this screen, on the Load Details Enquiry Selection Screen, enter the selection criteria and press **Enter**.

This screen displays when more than one load matches the selection criteria. Use this screen to select the load required.

TP265A	Z1 - Demonstration Company		User SP1		13/03/95			
	Demonstration Transport Centre				15:00:09			
Select Load								
	Ship date	Ship time	Route	Origin	Destination	Carrier	Load Number	Load Status
	13/03/95	10:30	BHAM	TC01	BHAM	CARRIER1	A5	Pending
2	13/03/95	16:00	CAMBS			CARRIER1	A7	Pending
	13/03/95	16:00	YORKSI	TC01	YORKS	OWN	A6	Pending

1=Select

2=Load totals

Bottom

F3=Exit

F12=Previous

F15=All statuses

Fields:

(Untitled)

Select. Enter one of the following:

- 1 - Select. To display the Load Details Enquiry Screen for the load.
- 2 - Totals. To display the Load Totals Enquiry Window for the load.

Functions:

F15

All statuses. Use this function to display loads with all statuses that match the search criteria.



To display the Load Details Enquiry Screen, select a load with option 1.

Load Details Enquiry Screen (Option 1)



To display this screen, on the Select Load Detail Screen, select a load with option 1.

The information displayed on this screen includes the load number, master load and drop, consolidation load, ship date and time, route and rating information.

TP265B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:03:27
Load Details Enquiry			
Load number	A7	Load status	Pending
Master load		Consolidation Load ..	
Master drop		Master Area	
Ship date	13/03/95	Ship time	16:00
Route	CAMBS	Cambridge Route	
Carrier	CARRIER1	BMZ Distribution Services	
Vehicle type	38T	38 Tonne Artic	
Origin		Destination	
Vehicle		Seal number	
Driver		Crew	
Temperatures		Skeleton Load	0
Agent contact ...		Payment method	01
Exclusive load ..	0	P & L override	
Confirmation	0	Rating status	1 0
Bill required	0	Rate method	01
Bill format		Rate code	C01STD
Copies	1		
F3=Exit F12=Previous F14=Drops F15=Orders F16=Totals F20=Consignee F21=Text			

Functions:

F14

Drops. Use this function to display the details of all customer drops for a load.

F15

Orders. Use this function to display the details of all orders on a load.

F16

Totals. Use this function to display the details of the load totals.

F17

Sub-loads / consolidation loads. This function is only available if the current load is a master load or primary consolidation load. Use this function to display the Sub-loads or Secondary loads details.

F20

Consignee. Use this function to display the carrier details.

F21

Text. Use this function to display the text associated with a load.



To display the Select Load Detail Screen, press **Enter**.

Enquire On Drops For A Load Screen (F14)



To display this screen, on the Load Details Enquiry Screen, select **F14=Drops**.

Use this screen to view details of all customer drops on a load.

The screen displays the load number, ship date, route, load status and ship time and, for each drop, the weight, volume, number of containers and customer name.

TP275	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:03:53
Enquire on Drops for a Load			
Load number.....	A7	Load status.....	Pending
Ship date.....	13/03/95	Ship time.....	16:00
Route.....	CAMBS	Cambridge Route	
S	Drop	Weight	Volume Containers Customer name
-	010	246.3	180.5 8.5 Bunting Pharmac
1=Delivery profile enquiry			
F3=Exit F12=Previous			

Fields:

S

Selection field. Enter 1 against a drop to display the Delivery Profile Enquiry.



To view the Delivery Profile Enquiry, enter 1 against a drop.

Delivery Profile Enquiry Screen



To display this screen, on the Enquire On Drops
For a Load Screen, enter 1 against a drop.

This screen displays information about the delivery profile. The information includes the sales company, the customer code, name and address.

TP224B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:12:22
Delivery Profile Enquiry			
Sales company..... Z1 Demonstration Company			
Customer..... GC02 000 Bunting Pharmaceuticals			
27 College Avenue			
Histon			
Default planning parameters:			
Route..... CAMBS Cambridge Route			
Drop..... 010			
Carrier..... CARRIER1 BMZ Distribution Services			
Area..... A2 Area 2 - Up to 150 Miles			
Customer exclusive loads.... 0 (0=No,1=Yes)			
Confirm delivery time slot.. 0 (0=No,1=Yes)			
Deliveries allowed: Mon Tue Wed Thu Fri Sat Sun			
1 0 0 0 0 0 0 (0=No,1=Yes)			
F3=Exit F12=Previous F13=Delivery time slots F21=Text			

This screen shows whether the loads are exclusive to a single customer and whether you must confirm delivery time slots. You can also see whether the customer allows deliveries on a particular day.

Functions:

F13

Delivery time slots. Place the cursor over 1 on any day and select this function to view the delivery time slots for that day.

F21

Text. Use this function to display the customer text which is for internal information only. It does not print on documentation.



To return to the menu, select **F3=Exit**.

Enquire On Delivery Time Slots Window (F13)

 To display this screen, on the Delivery Profile Enquiry Screen, select **F13=Delivery Time Slots**.

This screen displays times you can make deliveries for the selected day.

TP224B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:12:22
Delivery Profile Enquiry			
Sales company..... Z1 Demonstration Company			
Customer..... GC02 000 Bunting Pharmaceuticals			
27 College Avenue			
Histon			
Default planning parameters:			
Route..... CAMBS Cambridge Route			
Drop..... 010			
Carrier..... CARRIER1			
Area..... A2			
Customer exclusive loads... 0 (0=No.			
Confirm delivery time slot.. 0 (0=No.			
Deliveries allowed: Mon Tue Wed Thu F			
1 0 0 0			
F3=Exit F12=Previous F13=Del F12=Previous			

Enquire on delivery time slots

Delivery Time Slots

Day..... Monday

Time slot 1..... 9:00 17:30

Time slot 2.....

Time slot 3.....

Time slot 4.....

 To return to the Delivery Profile Enquiry Screen, select **F12=Previous**.

Enquire On Orders For A Load Screen (F15)



To display this screen, on the Load Details Enquiry Screen, select **F15=Orders**.

This screen displays details of all orders on a load. The screen displays the load number, ship date, route, load status and ship time, and for each order, the weight, volume, number of containers, order number, and whether the order is ready.

TP280A	Z1 - Demonstration Company	User SP1	13/03/95			
	Demonstration Transport Centre		15:04:09			
Enquire on Orders for a Load						
Load number.....	A7	Load status.....	Pending			
Ship date.....	13/03/95	Ship time.....	16:00			
Route.....	CAMBS	Cambridge Route				
S	Drop	Weight	Volume	Containers	Order number	Ready
_	010	246.3	180.5	8.5	0000123	0
1=Order enquiry 2=Delivery profile enquiry 3=Order lines						
F3=Exit F12=Previous						

Fields:

S

Selection field. Enter one of the following:

- 1 - To display the Whole Order Enquiry Screen, for more details, see the Order Entry product information.
- 2 - To display the Delivery Profile Enquiry.
- 3 - To display the Display Order Lines Screen.



To leave the enquiry, select **F3=Exit**.

Display Order Lines Screen (Option 3)



To display this screen, on the Enquire On Orders
For A Load Screen, select a load with option 3.

This screen shows details on the lines on the order. The information displayed includes the order number, stockroom, despatch date and time, load number and status, drop and route. For each line the screen displays the line quantity, weight, volume, and number of containers.

TP281	Z1 - Demonstration Company	User SP1	13/03/95 15:05:22
-------	----------------------------	----------	----------------------

Display Order Lines

Order number 0000123 Stockroom 01 Central Stockroom
Despatch date ... 13/03/95 Despatch time ... 16:00
Load number A7 Load status Pending Drop 010
Route CAMBS Cambridge Route

	Line	Quantity	Weight	Volume	Containers
1	1	50.000	109.5	10.5	.1
-	2	200.000	45.0	60.0	.9
-	3	100.000	30.6	35.0	2.5
-	4	150.000	61.2	75.0	5.0

1=Order line enquiry
F3=Exit F12=Previous

Fields:

Untitled

Selection. Enter 1 against the order line you want to view the details for. For more information on the Order Line Enquiry, see the Order Entry product information.



To return to the previous screen, select
F12=Previous.

Load Totals Enquiry Window (F16)



To display this screen, on the Load Details Enquiry Screen, select **F16=Totals**.

This window displays, for the load, the gross, tare and net weight, the number of containers, orders and drops and charging information.

TP265A		Z1 - Demonstration Company		User SP1	13/03/95
		Demonstration Transport Centre			15:00:09
Select Load					
	Ship date	Ship time	Route	Origin	
	13/03/95	10:30	BHAM	TC01	
<u>2</u>	13/03/95	16:00	CAMBS		
-	13/03/95	16:00	YORKS1	TC01	

Load Totals Enquiry	
Load number.....	A7
Gross weight.....	246.3
Tare weight.....	1.8
Net weight.....	244.5
Volume.....	180.5
Containers.....	8.5
Customer drops.....	1
Orders.....	1
Ready for loading..	
Total charge.....	.00
Grand total.....	.00
Payment amount.....	.00
Adjustment amount..	.00

F12=Previous F15=Availability

Bottom

1=Select	2=Load totals	
F3=Exit	F12=Previous	F15=All statuses

Functions:

F15

Availability/Totals. Use this function to toggle the display between available quantities and total load quantities.



To return to the previous screen, select **F12=Previous**.

Consolidation / Sub-Loads Details (F17)



To display this screen, on the Load Details Enquiry Screen, select **F17=Consolidation Loads/Sub Loads**.



Note: This function is only available if you are displaying the details for a master, or primary consolidation, load.

This screen displays the details of the consolidation, or sub-loads, for the selected load. It shows the load and route.

TP265B		Z1 - UK Demonstration Company		User: GBJBAPS		18/12/97	
		Demonstration Transport Centre				11:07:46	
Load Details Enquiry				Consolidated Load			
Load number	A59	Load	Consolidation Details				
Master load		Conso	Load	A59	More:		
Master drop		Maste	Containers				
Ship date	19/11/97	Ship	Load	Route	Containers		
Route	TORONTO	TORON	A59	TORONTO			
Carrier	CPET	CPET	A60	TORONTO			
Vehicle type			A61	TORONTO			
Origin	TC01	Desti					
Vehicle		Seal					
Driver		Crew					
Temperatures		Skele					
Agent contact ...							
Exclusive load ..	0	Payme					
Confirmation	0	P & L					
Bill required ...	0	Ratin					
Bill format		Rate					
Copies	1	Rate code	C01STD				
F3=Exit		F12=Previous		F14=Drops		F15=Orders	
F17=Consolidation Loads				F20=Consignee		F21=Text	
				F16=Totals			

Functions:

F14

Volume. Use this function to display the volume of each load.

F15

Weight. Use this function to display the weight of each load.

F16

Containers. Use this function to show the number of containers for each load.



Select **F12=Previous** to return to the previous screen.

Consignee Details Enquiry Window (F20)

 To display this screen, on the Load Details Enquiry Screen, select **F20=Consignee**.

This screen shows the address details of the carrier, unless the bill of lading format is 02 (one bill of lading per drop) when this screen is blank.


TP265B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:03:27
Load Details Enquiry			
Load number	A7	Load status	Pending
Master load		Consolidation Load ..	
Master drop		Master Area	
Ship date	13/03/95	Ship time	16:00
Route	CAMBS	Cambridge Route	
Carrier	CARRIER1	BMZ Distribution Services	
Vehicle type	38T	38 Tonne Artic	
Origin			
Vehicle			
Driver			
Temperatures			
Agent contact ...			
Exclusive load ..			
Confirmation ...			
Bill required ...			
Bill format			
Copies			
Consignee Details			
Name.....		BMZ Distribution Services	
Address.....		UN IT 2	
		MATFORD INDUSTRIAL ESTATE	
		SKETCHLEY WAY	
		HINKLEY	
Post code.....		LE1 5EU	
F12=Previous			
F3=Exit	F12=Previous	F14=Drops	F15=Orders
F20=Consignee	F21=Text		F16=Totals

 To return to the previous screen, select **F12=Previous**.

Loads by Order

1... **2...** 16/TPP

Use this enquiry to display the current position of the sales order within Transport Planning. You can then easily track the order's progress. The Loads By Order diagram shows the screens accessed from this option.



Transport Loads By Order Number Enquiry Screen



To display this screen, select the Loads by Order (Enquiries) option.

Use this screen to select the order to enquire upon, or to use a customer or customer order reference to identify the order.

TP261A	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:01:08
Transport Loads by Order Number Enquiry			
Sales Company.....?.. <u>Z1</u> Demonstration Company			
Enter a valid Sales Order Number or select a valid Customer to enquire on Orders by Customer. The Customer Order Reference may optionally be entered.			
Sales Order Number..... _____			
OR			
Customer?.. <u>GC02</u> <u>000</u>			
Customer Order Reference... _____			
F3=Exit F4=Prompt			

Fields:

Sales Company

Enter the sales company. This defaults to the present company.

Sales Order Number

Enter a sales order number. You cannot enter a manual requirement order number.

OR

Customer

Select a customer and customer address.

Customer Order Reference

Enter a customer order reference number.



To display the Transport Loads by Order Number Enquiry Select Order Screen, enter a customer and address, and press **Enter**.

Transport Loads by Order Number Enquiry Select Order Screen



To display this screen, on the Transport Loads By Order Number Enquiry Screen enter a customer and address, and press **Enter**.

Use this screen to select an order for which you want to see the transport load details.

TP261A	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:01:08
Transport Loads by Order Number Enquiry - Select Order			
Sales Company.....	Z1	Demonstration Company	
Customer	GC02	000 Bunting Pharmaceuticals	

Fields:

Untitled

Select. Enter 1 to select the order.

Functions:

F13

Change Level of Detail. Use this function to toggle between different levels of detail.



Select an order to display the Transport Loads by Order Number Enquiry Display Loads Screen.

Transport Loads by Order Number Enquiry Display Loads Screen



To display this screen, on the Transport Loads By Order Number Enquiry Select Order Screen, select an order.

Use this screen to view the details of loads.

TP261B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		15:03:09
Transport Loads by Order Number Enquiry - Display Loads			
Sales Company.....	Z1	Demonstration Company	
Customer	GC02 000	Bunting Pharmaceuticals	
Order.. 0000123	Customer Ref.. A001235	Order Priority.. 50	
Load	Status	Ship date/time	Route
<u>1</u> A7	Pending	13/03/95 16:00	CAMBS
		010 CARRIER1	SR Dsp Veh
		01	38T
1=Load Enquiry 2=Order lines			
F3=Exit F12=Previous F14=Delivery profile enquiry F16=Sales Order enquiry			

Fields:

(Untitled)

Select. Enter one of the following:

- 1 - Load Enquiry. To display the Load Details Enquiry Screen.
- 2 - Order Lines. To display the Display Order Lines Screen.

Functions:

F14

Delivery Profile Enquiry. Use this function to display the Delivery Profile Enquiry Screen.

F16

Sales Order Enquiry. Use this function to display the Whole Order Enquiry Screen. For more details, see the Order Entry product information.



To leave the enquiry, select **F3=Exit**.