

-
-
-
-
-

Chapter 5

WIP Inventory Control



WIP Inventory Control Introduction

This section reviews facilities available for the management of WIP inventory. That is, part processed items on the shop floor. WIP inventory is transparent to Inventory Management and is a Production system function only.

WIP Inventory Management

It is sometimes necessary to adjust work-in-progress (WIP) inventory balances or to report changes in location (physical or logical). In addition, the status of WIP inventory may change from available to held or scrap. WIP reporting consists of activities which support these types of WIP inventory movements.

Remember that with one exception (scrap inventory) only count point operations relate to WIP inventory



Note: In the following sections, the Route code field applies to flow route operations only.

Hold Inventory

1... 2... 1/MJI

This option allows you to change the status of available WIP inventory to held and thus to exclude it from WIP availability. This might be applied to WIP inventory of questionable quality, pending a quality inspection.



When Hold Inventory is selected on the menu, the WIP Inventory Hold Entry screen is displayed.

The following fields and functions are displayed:

MJ212	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:36:27
WIP Inventory Hold Entry			
Date	8/12/95	Shift	__
WIP Location.....?	__		
Item.....?	_____		
Order.....?	_____		
Operation.....?	_____		
Lot Number.....?	_____		
Held Reference.....	_____		
Quantity.....	.000		
Unit of Measure....?	__		
Reason Code.....?	__		
F3=Exit F4=Prompt F12=Previous F19=Held WIP Inventory Details			
05-26	SA	MW	KS IM II KENB20A PET166S2

Fields:

Date

You must enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift with which the transaction is associated.

WIP Location

Enter the work station WIP location at which the held, released or scrapped quantity is to be recorded. The system validates any quantity against the on-hand quantity at this location.

It is essential that the (work station) WIP location balance relates to the order/operation or item/operation for which the transaction is being recorded. This is of particular importance when bookings have been made to more than one work station with different associated WIP locations.



Note: When an item/operation/WIP location or

*order/operation/WIP location has been entered, use **F19=Held WIP Inventory Details** to view any existing held WIP inventory details.*

Item

This field is only relevant for schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (yes).

In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only relevant in an environment operating production orders. Enter a valid order number.

In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number of the available WIP intended to be held. WIP balances exist at operation level, so it is essential to enter an operation which must be a standard operation as defined as a count point on the planning route for the item entered. WIP balances can only exist for count point operations.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being adjusted. The lot number is only required if 1 (Yes) is entered in the WIP Lot Tracking Flag field in the Organisational Model

Held Reference

If the Held Inventory Tracking Flag field on the Organisational Model is set to 1 (held) then you must enter a value in this field. This unique reference can be used for a QA control number, container ID or simply as a functional notation.

Quantity

The quantity to be held must be less than or equal to the available quantity at the item/operation or order/operation at the WIP location specified.



Note: When releasing or scrapping held inventory, the quantity specified must be less than or equal to the quantity recorded as held at the item/operation or order/operation, at the WIP location specified.

Quantities must correlate to any lot control references (WIP Lot Tracking) and held references (Held Lot Tracking) previously assigned where used. The quantity entered must be in the same unit of measure as the booked WIP inventory.

Unit Of Measure

Enter the unit of measure in which the held quantity is to be expressed. This should be a valid unit of measure for the item. The quantity is converted to the

equivalent quantity in the issuing unit of measure in the primary stockroom of the item if appropriate.

Reason Code

You must enter a reason code to indicate why the inventory is being held. Any reason code must first be defined on the Inventory Descriptions File.



Press **Enter** once to validate your entries. Press **Enter** for a second time to apply the transaction to the database. You may then continue with additional transactions or select **F3=Exit** to return to a menu.

Functions:

F19

Held WIP Inventory Details. When you select this function, the existing Held WIP inventory Details for the item/operation or order/operation entered is displayed.

Release Inventory

1...
2... **2/MJI**

This transaction is used to make previously held WIP inventory available again. This might occur following inspection, sorting or rework.



When Release Inventory is selected on the menu, the WIP Held Inventory Release Entry screen is displayed.

The following fields and functions are displayed:

MJ212	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:36:45
WIP Held Inventory Release Entry			
Date	8/12/95	Shift	■
WIP Location.....?	_____		
Item.....?	_____		
Order.....?	_____		
Operation.....?	_____		
Lot Number.....?	_____		
Held Reference.....	_____		
Quantity.....	.000		
Unit of Measure....?	_____		
Reason Code.....?	_____		
F3=Exit F4=Prompt F16=Output F12=Previous F19=Held WIP Inventory Details			
05-26 82 MW KS IM II KENB20A PET166S2			

Fields:

Date

Enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift during which the held, released or scrapped quantity is to be recorded. This provides a more precise time frame for recording the quantity on the stated date.

If entered, this should be a shift number on the shift profile in force at the work station on the day specified.

WIP Location

Enter the (work station) WIP location from which the held quantity is to be released.

The system validates any quantity against the on-hand quantity at this location; it is essential that the work station WIP location balance relates to the order/operation or item/operation at which the transaction is being recorded. This

is of particular importance when bookings have been made to more than one work station with different associated WIP locations.

Item

This field is only relevant for schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (yes). In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only relevant for production orders. Enter a valid order number. In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number of the held WIP quantity to be released. WIP balances exist at operation level, so it is essential to enter an operation. This must be a standard operation and defined as a count point on the planning route for the item entered.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being released. The lot number is only required if 1 (Yes) is entered in the WIP Lot Tracking Flag field in the Organisational Model.

Held Reference

If the Held Inventory Tracking Flag on the Organisational Model is set to 1 (held) then you must enter a value in this field. This unique reference can be used for a QA control number, container ID or simply as a functional notation.



*Note: The quantity to be released must be less than or equal to the held quantity. Use **F19=Held WIP Inventory Details** to view held inventory after entering item/operation or order/operation.*

Quantity

Enter the quantity you wish to release from held. Enter a positive quantity to decrease the held balance.

Unit Of Measure

Enter the unit of measure in which the release quantity is to be expressed. This should be a valid unit of measure for the item. The quantity is converted to the equivalent quantity in the issuing unit of measure in the primary stockroom of the item if appropriate.

Reason Code

Enter a reason code to indicate why the inventory is being released. The reason code must be defined on the Inventory Descriptions File.

Functions:

F16

Output. When you select this function, the outputs window for process group items is displayed. Outputs can be maintained from this window. If the held WIP inventory is being released from the last operation, this allows you to see the inventory receipts quantity resulting.

F19

Held WIP Inventory Details. When you select this function, the existing Held WIP inventory Details for the item/operation or order/operation entered is displayed.

Scrap Held Inventory

1...
2... **3/MJI**

This transaction is used to scrap previously held WIP inventory that cannot be reworked.



When Scrap Held Inventory is selected on the menu, the WIP Held Inventory Scrap Entry screen is displayed.

The following fields and functions are displayed:

MJ212	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:37:01
WIP Held Inventory Scrap Entry			
Date	8/12/95	Shift	___
WIP Location.....?	___		
Item.....?	_____		
Order.....?	_____		
Operation.....?	_____		
Lot Number.....?	_____		
Held Reference.....	_____		
Quantity.....	.000		
Unit of Measure....?	___		
Reason Code.....?	___		
F3=Exit F4=Prompt F12=Previous F19=Held WIP Inventory Details			
05-26	S	MW	KS IM II KENB20A PET166S2

Fields:

Date

Enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift during which the held, released, or scrapped quantity is to be recorded.

This provides a more precise time frame for recording the quantity on the stated date. If entered, this should be a shift number on the shift profile in force at the work station on the day specified.

WIP Location

Enter the WIP location from which the held WIP quantity is to be scrapped. The system validates any quantity against the on-hand quantity at this location; it is essential that the work station WIP location balance relates to the order/operation or item/operation at which the transaction is being recorded. This is of particular importance when bookings have been made to more than one work station with different associated WIP locations.

Item

This field is only relevant for schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (yes). In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only relevant to production orders. Enter a valid order number. In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number of the held WIP inventory quantity to be scrapped. WIP balances exist at operation level, so it is necessary to enter an operation, which must be a standard operation, and defined as a count point on the planning route for the item entered.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being scrapped. The lot number is only required if you enter 1 (Yes) in the WIP Lot Tracking Flag field in the Organisational Model.

Held Reference

If the Held Inventory Tracking Flag on the Organisational Model is set to 1 (held) then you must enter a value in this field. This unique reference can be used for a QA control number, container ID or simply as a functional notation.

Quantity

Enter the quantity you wish to scrap from held. Enter a positive quantity to decrease the held balance.



*Note: Use **F19=Held WIP Inventory Details** to view held WIP inventory after entering item/operation or order/operation.*

Unit Of Measure

Enter the unit of measure in which the scrap quantity is expressed. This should be a valid unit of measure for the item. The quantity is converted to the equivalent quantity in the issuing unit of measure in the primary stockroom of the item.

Reason Code

Enter a reason code to indicate why the inventory is being scrapped. The reason code must be defined on the Inventory Descriptions File.

Functions:

F19

Held WIP Inventory Details. When you select this function, the existing Held WIP inventory Details for the item/operation or order/operation entered is displayed.

Scrap Available Inventory

**4/MJI**

Warning: This unique transaction is the only exception to the rule that only count point operations relate to WIP inventory.

This option allows the recording of scrapped work in process. WIP can be scrapped at any operation whether or not it is a count point; except at the last operation.

At count point operations, only existing WIP balances may be scrapped. The transaction reduces the on hand and available balances at the operation.

If the operation is not a count point, then the on hand and available balances are reduced at the previous count point if there is one.

Materials are backflushed and costs are recovered for the operations which follow the previous count point, up to and including the operation at which the scrap is recorded.



When Scrap Available Inventory is selected on the menu, the WIP Inventory Scrap Entry screen is displayed.

MJ215	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95
			17:37:28
WIP Inventory Scrap Entry			
Date	8/12/95	Shift	1
WIP Location	?		
Item	?		
Order	?		
Operation	?		
Lot Number	?		
Scrap Reference			
Subcontractor	?		
Shipper Number	?		0
Quantity			.000
Unit of Measure	?		
Reason Code	?		
F3=Exit F4=Prompt			
05-26	Sr	MW	KS IM II KENB20A PET166S2

Fields:

Date

Enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift during which the scrapped quantity is to be recorded. This provides a more precise time frame for recording the scrap quantity on the stated date.

If entered, this should be a shift number on the shift profile in force at the work station on the day specified.

WIP Location

Enter the WIP location at which the WIP quantity is to be scrapped. The WIP location may be any location where balances of the entered item/operation exist. If the operation entered is not a count point, then the WIP location entered should be a WIP location where there is a balance at the previous count point operation for the item.

Item

This field is only relevant to schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (yes).

In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only for production orders.

In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number at which the scrap occurred. The operation entered must be defined on the planning route for the item. The system assumes that the activity entered has occurred and backflushes materials and recover costs accordingly.

WIP scrap may be recorded for any valid operation. If it is a count point then the available WIP balance is reduced for the operation. If it is not a count point, the balance is reduced at the previous count point, and materials and costs are recovered for all operations which follow the previous count point operation up to and including the operation at which the scrap booking is made.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being scrapped. The lot number is only required if you enter 1 (Yes) in the WIP Lot Tracking Flag field in the Organisational Model.

Scrap Reference

You can enter a reference by which this scrap transaction may be identified.

Subcontractor

If the scrap has been produced at a subcontract operation, then enter the code of the subcontractor where the scrap occurred. There should be a subcontractor balance at the operation. This is the balance currently at the subcontractor. It does not become a balance at the subcontract operation itself until it has been received back from the subcontractor.

Shipper Number

Enter the shipment reference number for which the scrap took place. Position the cursor on this field and select **F4=Prompt** for a list of available numbers.

Scrap Quantity

Enter the quantity scrapped at the WIP location. The quantity must be less than or equal to the available quantity at the item/operation or order/operation, at the WIP location specified.

Quantities must also correlate to lot control references if WIP Lot Tracking is used, and must be in the same unit of measurement as the booked WIP inventory.

Unit Of Measure

Enter the UOM in which the scrap quantity is to be expressed. This should be a valid unit of measure for the Item. The quantity is converted to the equivalent quantity in the issuing unit of measure in the primary stockroom of the item.

Reason Code

If a scrap quantity is reported, then a reason code must be entered. If scrap transactions are associated with a reason code, the Scrap reason Code Analysis Report totals the quantities of an item/operation scrapped, detailed by reason code.



Press **Enter** once to validate your entries. Press **Enter** for a second time to apply the transaction to the database. You can then continue with additional transactions or select **F3=Exit** to return to a menu.

Transfer Location

1...
2... **5/MJI**

This transaction supports the transfer of WIP inventory from one WIP location to another. The inventory transferred may be held inventory.



When Transfer Location is selected on the menu, the WIP Location Transfer screen is displayed.

MJ211	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:37:54
WIP Location Transfer			
Date	8/12/95	Shift	__
From Location.....?	__		
To Location.....?	__		
Item.....?	_____		
Order.....?	_____		
Operation.....?	_____		
Lot Number.....?	_____		
Inventory Status....	0	0=Available 1=Held Inventory	
Held Reference.....?	_____		
Quantity.....	.000		
Unit of Measure....?	__		
Reason Code.....?	__		
F3=Exit F4=Prompt			
05-26	82	MW	KS IM II KENB20A PET166S2

Fields:

Date

Enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift during which the transfer is to be recorded. This provides a more precise time frame for recording the transfer on the stated date. If entered, this should be a shift number on the shift profile in force at the work station on the day specified.

From Location

Enter the WIP location from which the inventory is to be moved. If the transaction makes the WIP balance negative, a warning message is issued.

To Location

Enter the WIP location which is the destination of the transfer.

Item

This field is only relevant to schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (yes).

In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only relevant to production orders.

In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number of the held WIP inventory to be transferred. WIP balances exist at operation level, so it is necessary to enter an operation, which must be a standard operation and be defined as a count point on the planning route for the item entered.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being transferred. The lot number is only required if you enter 1 (Yes) in the WIP Lot Tracking Flag field in the Organisational Model.

Inventory Status

This determines the status of the quantity being adjusted. It controls whether the available or the held balance is updated. You can enter the following:

0 - Available.

1 - Held.

Held Reference

If the Inventory Status flag is set to 1 (held) in the previous field and if the Held Inventory Tracking Flag on the Organisational Model is set to 1 (held) then this is a required value. This reference can be used for a QA control number, container ID or simply as a functional notation.

Quantity

Enter the quantity you wish to transfer. Enter a positive quantity to transfer, or a negative quantity to reverse a prior transfer movement.

Unit Of Measure

Enter the unit of measure in which the adjustment quantity is to be expressed. This should be a valid unit of measure for the item. The quantity is converted to the equivalent quantity in the issuing unit of measure in the primary stockroom of the item, if relevant.

Reason Code

Enter a reason code to indicate why the transfer is occurring.

Allocate Inventory



6/MJI



Note: This is a production order facility only.

This option allows manual allocation of any available stock. The production order number is mandatory and must follow an option in which inventory has first been de-allocated from another production order to become free stock for that item.



When Allocate Inventory is selected on the menu, the WIP Inventory Allocations screen is displayed.

MG220	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95
WIP Inventory Allocations			
Date	8/12/95	Shift	1
WIP Location	?		
Item	?		
Operation	?		
Lot Number	?		
Order	?		
Quantity	000		
Reason	?		
Reversal			
F3=Exit F4=Prompt			
05-26	SA	MW	KS IM II KENB20A PET166S2

Fields:

Date

This defaults to the current system date.

Shift

You can enter the shift during which the allocation is to be recorded. This provides a more precise time frame for recording the transaction on the entered date. If entered, this should be a shift number on the shift profile in force on the day specified.

WIP Location

Enter the work station WIP location at which the free WIP inventory is located.

Item

Enter the parent item of the order.

Operation

Enter the operation sequence number at which the allocation is to be made.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being reported. The lot number is only required if you enter 1 (Yes) in the WIP Lot Tracking Flag field in the Organisational Model.

Order

Enter the production order number to allocate the inventory to. The order must have an Order type of 1 (standard), a status of at least Released, and be for the same parent item as the de-allocated order; that is the order from which inventory has been de-allocated. See Deallocate Inventory.

Quantity

Enter the quantity of free WIP inventory for the parent item to allocate to the order. The system checks that the quantity is less than or equal to the free standing balance.

Reason Code

Enter a reason code to indicate why the allocation is occurring. The reason code must be defined on the Inventory Descriptions File.

Reversal

This field can be used to reverse an unwanted or inaccurate allocation. You can enter the following:

0 - No. To make a normal allocation.

1 - Yes. To reverse a previous allocation.



Press **Enter** once to validate your entries. Press **Enter** for a second time to apply the transaction to the database. You can then continue with additional transactions or select **F3=Exit** to return to a menu.

Deallocate Inventory



7/MJI



Note: This is a production order facility only.

This option allows the manual de-allocation of specific items on a completed production order. It increases the available stock for the items. The order must not be archived. This option de-allocates any items remaining as allocated against a production order.



Tip: The order must have a status of complete and must not be archived.



When Deallocate Inventory is selected on the menu, the Deallocate Inventory screen is displayed.

```
MG221          Z1 - GB Demonstration Company    User GBJBAMS    8/12/95
Deallocate Inventory
Date 8/12/95 Shift
WIP Location.....?
Order.....?
Operation.....?
Lot Number.....?
Reason.....?
F3=Exit F4=Prompt F8=Update
05-26 SF MW KS IM II KENB20A PET166S2
```

Fields:

Date

This defaults to the current system date.

Shift

You can enter the shift during which the transaction is/was enacted.

WIP Location

Enter the work station WIP location at which the free WIP inventory is to be recorded. When allocating to another order, the system looks for free inventory in the WIP location entered.

Order

Enter the production order number to de-allocate from. The order must have an Order Type of 1 (Standard) and a status of 8 (Complete).

Reason Code

Enter a reason code to indicate why the transfer is occurring. The reason code must be defined on the Inventory Descriptions File.



Press **Enter** once to validate your entries. Press **Enter** for a second time to apply the transaction to the database. You may then continue with additional transactions or select **F3=Exit** to return to a menu.

Adjust Inventory

1...
2... **8/MJI**

This function enables amendments to be made to the quantity of WIP. WIP exists as part completed quantities of items at operation stages.

WIP inventory adjustments are used to increase or decrease WIP balances. This function may also be used to establish WIP balances when the system is first installed, as part of the initial stock take-on. Any of three WIP inventory balances: on-hand, held and subcontract can be adjusted.



When Adjust Inventory is selected on the menu, the WIP Inventory Adjustments screen is displayed.

MJ210	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:40:24
WIP Inventory Adjustments			
Date	8/12/95	Shift	1
WIP Location.....?	_____		
Item.....?	_____		
Order.....?	_____		
Operation.....?	_____		
Lot Number.....?	_____		
Subcontractor.....?	_____		
Shipper Number.....?	_____		
Inventory Status....	0	0=Available 1=Held Inventory	
Held Reference.....?	_____		
Quantity.....	.000		
Unit of Measure.....?	_____		
Reason Code.....?	_____		
F3=Exit F4=Prompt			
05-26	SF	MM	KS IM II KENB20A PET166S2

Fields:

Date

Enter the date on which this transaction took place or is deemed to take place. It defaults to the current system date.

Shift

You can enter the shift during which the adjustment is to be recorded. This provides a more precise time frame for recording the adjustment on the stated date.

If entered, this should be a shift number on the shift profile in force at the work station on the date specified.

WIP Location

Enter the WIP location for which the WIP balance is to be adjusted. Normally this is the WIP location associated with a work station on the planning route of the item and operation entered.

Item

This field is only relevant to schedule controlled items. Any item code entered must have a Schedule Controlled flag (review via Production Details Maintenance) setting of 1 (Yes). In a production order environment, an order and operation sequence are required to locate WIP inventory.

Order

This field is only relevant in an environment operating production orders. In a schedule environment, an item and operation sequence are required to locate WIP inventory.

Operation

Enter the operation sequence number for the WIP balance to be adjusted. WIP balances exist at operation level, so it is necessary to enter an operation, which must be a standard operation and defined as a count point on the planning route for the item entered.

WIP balances cannot be adjusted for the final operation on a route. Quantities produced at these operations are automatically transferred to Inventory and so do not remain in WIP, unless held. If held, adjustment must be made using Release Inventory or Scrap Held Inventory.

Lot Number

If the item being reported is lot controlled, then record the lot number of the batch being reported. The lot number is only required if you enter 1 (Yes) in the WIP Lot Tracking Flag field in the Organisational Model.

Subcontractor

If adjusting the subcontract balance, enter the subcontractor here. If entered, the item/operation/subcontractor must be defined on the subcontractor file.

Shipper Number

If you are adjusting the subcontract balance, you must enter a value in this field.

The shipper number must be entered if 1 (Yes) is entered in the Shipper Tracking Flag field in the Organisational Model.

Inventory Status

This determines the status of the quantity being adjusted. You can enter the following:

0 - Available. If a subcontractor has been entered, this must be 0 because subcontractor inventory cannot be held, until returned.

1 - Held Inventory.

Held Reference

If the Inventory Status field is 1 (Held), and if the Held Inventory Tracking Flag field on the Organisational Model is set to 1, then you must enter a value in this field. This reference can be used for a QA control number, container ID or simply as a functional notation.

Quantity

Enter the quantity by which you wish to adjust the WIP inventory balance. Enter a positive quantity to increase the balance or a negative quantity to reduce the balance.

Unit Of Measure

Enter the unit of measure in which the adjustment quantity is expressed. This should be a valid unit of measure for the item. The quantity is converted to the equivalent quantity in the issuing unit of measure in the primary stockroom of the item, if relevant.

Reason Code

Enter a reason code to indicate why the adjustment is being reported. The reason code must be defined on the Inventory Descriptions File.



Press **Enter** once to validate your entries. Press **Enter** for a second time to apply the transaction to the database. You may then continue with additional transactions or select **F3=Exit** to return to a menu.

Total Stock Status Enquiry



11/MJI

This enquiry allows you to see Inventory Management stock levels as well as WIP inventory available and held and at subcontractor balances.



When Total Stock Status is selected on the menu, the first Total Stock Status Enquiry screen is displayed.

Total Stock Status Enquiry Screen 1



When Total Stock Status is selected on the menu, the first Total Stock Status Enquiry screen is displayed.

The following fields are displayed:

Fields:

Org Model

Enter the live Organisational Model.

Item

Enter an item to enquire on.



When **Enter** is pressed on the first Total Stock Status Enquiry screen, the second screen is displayed.

Total Stock Status Enquiry Screen 2



When **Enter** is pressed on the first Total Stock Status Enquiry screen, the second screen is displayed.

The following fields and functions are displayed:

MJ500	Z1 - GB Demonstration Company	User	GBJBAMS	8/12/95
				16:27:27
Total Stock Status Enquiry				
<u>Stockroom Inventory</u>		Available	Held	
Org.Model... 01				
Item..... MS001		26.000	.000	
Product A				
<u>WIP Inventory</u>				
Operation		Available	Held	Subcontractor
■	30 Operation 30	.000	1.000	.000
-	20 Operation 20	2.000-	.000	.000
-	10 Operation 10	5.000	1.000	.000
Select '1' = WIP Location Stock Status				
Select '2' = WIP Inventory Movements				
F3=Exit F12=Previous F15=MPS/MRP Inquiry				
F16=Item Stockroom Inquiry F17=Inventory Availability				
10-02	SA	MW	KS	IM II KENB20A PET166S2

Fields:

Stockroom Inventory Section

Available

Inventory Management available=on-hand less frozen less allocated. This is company wide, not model-specific.

Held

Inventory Management frozen. Again, this is company wide, not model-specific.

WIP Inventory Section

(Untitled)

You can enter the following:

1 - WIP Location Stock Status. When you enter this option, the WIP Location Stock Status window is displayed.

2 - WIP Inventory Movements. When you enter this option, the WIP Inventory Movements screen is displayed.

Operation

The operation level of the WIP inventory listed is displayed for your information only.

Available

WIP available (on-hand less held less WIP at subcontractor) is displayed for your information only.

Held

The held WIP balance is displayed for your information only.

Subcontractor

The subcontractor WIP balance is displayed for your information only.

Functions:

F15

MPS/MRP Inquiry. When you select this function, the standard MPS/MRP enquiry function is displayed.

F16

Item Stockroom Inquiry. When you select this function, the Stock Room Balances window is displayed.

F17

Inventory Availability. When you select this function, the Inventory Availability enquiry is displayed. This is normally accessed in the Sales Order Processing module.



When 1 is entered in the (Untitled) field on the second Total Stock Status Enquiry screen, the WIP Location Stock Status window is displayed.



When 2 is entered in the (Untitled) field on the second Total Stock Status Enquiry screen, the WIP Inventory Movements screen is displayed.

WIP Location Stock Status Window (Option 1)

The purpose of this window is to show all WIP for the item, irrespective of the WIP location.



When 1 is entered in the (Untitled) field on the second Total Stock Status Enquiry screen, the WIP Location Stock Status window is displayed.

Total Stock Status Enquiry		WIP Location Stock status									
MJ500 Z1 - GB Demonstration Company User GBJBAMS 8/12/95 16:27:27 Stockroom Inventory Org.Model... 01 Item..... MS001 Product A WIP Inventory Operation 30 Operation 30 20 Operation 20 1 10 Operation 10		<table border="1"> <thead> <tr> <th>Loc</th> <th>Available</th> <th>Held</th> <th>Subcontractor</th> </tr> </thead> <tbody> <tr> <td>FS</td> <td>5.000</td> <td>1.000</td> <td>.000</td> </tr> </tbody> </table>		Loc	Available	Held	Subcontractor	FS	5.000	1.000	.000
Loc	Available	Held	Subcontractor								
FS	5.000	1.000	.000								
Select '1' = WIP Location Stock Select '2' = WIP Inventory Move F3=Exit F12=Previous F15=MPS/MRP Inquiry F16=Item Stockroom Inquiry F17=Inventory Availability 04-73 S2 MW KS IM II KENB20A PET166S2		F12=Previous F16=Lot Enquiry F19=Held Detail F17=Subcontractor F18=Operation Schedule									

Fields:

Operation

You can enter the operation to be displayed.

Loc

Location. The stockroom code is displayed for your information only.

Available

The WIP available is displayed for your information only.

Held

The held stock is displayed for your information only.

Subcontractor

The WIP at the subcontractor is displayed for your information only.

Functions:

F16

Lot Enquiry. The purpose of this enquiry is to be able to review the lot numbers which are recorded against WIP inventory. When you select this function, the Lot Enquiry screen is displayed.

F17

Subcontractor. The purpose of this window is to review the level of inventory at subcontractors. When you select this function, the Subcontractor Enquiry screen is displayed.

F18

Operation Schedule. The purpose of this window is to allow a review of current operation schedules for the item/operation selected. Schedules are presented in schedule date sequence, irrespective of work station. When you select this function, the Operation Schedule screen is displayed.

F19

Held Detail. The purpose of this window is to review the held references and lot numbers. When you select this function, the Held Detail screen is displayed.



When **F12=Previous** is selected, the second
Total Stock Status Enquiry screen is displayed.

WIP Inventory Movements Screen (Option 2)

The purpose of the screen is to display all or a selection of the WIP inventory movements booked against this item and operation.



When 2 is entered in the (Untitled) field on the second Total Stock Status Enquiry screen, the WIP Inventory Movements screen is displayed.

MJ573		Z1 - GB Demonstration Company		User	GBJBAMS	8/12/95
						16:29:58
WIP Inventory Movements						
Org Model.....?	01	Organisational Model 01				
Item.....?	MS001	Product A				
Operation.....?	10	Operation 10				
Trans Type.....?	1	(1= Onhand 2= Held)				
Reporting Type?		(Blank=All)				
Date Range.....	8/12/95 to 8/12/95					
WIP Loc Range.?	to	(Blank=All)				
Date	Trans No	Reporting Type	Activity	WIP Loc	Op	Movement Quantity
8/12/95	10043	PRODUCTION REPORTING	PRODRP	FS	10	3.000
8/12/95	10043	PRODUCTION REPORTING	PRODRP	FS	10	1.000-
8/12/95	10044	PRODUCTION REPORTING	PRODRP	FS	10	1.000-
8/12/95	10053	PRODUCTION REPORTING	PRODRP	FS	10	5.000
1=Select						
F3=Exit F4=Prompt F12=Previous						
00-20 82 MW KS IM II KENB20A PET166S2						

Fields:

Org Model

Enter the live Organisational Model.

Item

Enter an item to enquire on.

Operation

You can enter the operation level of the WIP inventory listed.

Trans Type

You can select whether Production WIP transactions (movements) affecting on-hand (default) or held WIP inventory are displayed.

Transaction types (codes) are transparent to users and a means of identifying updates to the main database; they are system defined and linked to appropriate reporting types which are themselves linked to activity types.

You can enter the following:

1 - Onhand. To display on-hand.

2 - Held. To display held transactions.

Reporting Type

You can enter a reporting type.

Reporting types are system defined and action specific updates to the database. A reporting type is never prompted for or entered directly during any booking or reporting routine, but is invoked as a consequence of the activity type to which it is linked. Certain activity types are user defined and may be specified during booking, whilst others are actioned automatically.

Reporting type descriptions are displayed against each listed transaction. Note that not all affect WIP inventory. In addition, note that a reporting type may be associated with more than one activity type; although an activity type may only be linked to one reporting type. For a list of reporting types see Maintain Activity Control File.

Date Range

You can enter the range of dates in the Date Range and To fields.



Warning: The Date Range field defaults to the current system date. You may need to change it for your enquiry.

WIP Loc Range

You can enter the range of stockrooms in the WIP Loc Range and To fields. The default is blank, which means all stockrooms.

(Untitled)

You can enter the following:

1 - Select. When you enter this option and press **Enter**, additional details are displayed.

Trans No

Transaction number. The processing reference assigned to the movement by Transaction Manager update routines.



When **F12=Previous** is selected, the second Total Stock Status Enquiry screen is displayed.

Stock Room Balances Window (F16)

This window provides visibility to the detailed Inventory Management Stock Balances which constitute available total on the Total Stock Status Enquiry screen.



When **F16=Item Stockroom Enquiry** is selected on the Total Stock Status Enquiry screen, the Stock Room Balances window is displayed.

Total Stock Status Enquiry		Available	Held	
<u>Stockroom Inventory</u>				
Org.Model...	01			
Item.....	MS001	26.000	.000	
Product A				
<u>WIP Inventory</u>				
Operation		Available	Held	Subcontractor
- 30 Operation 30		.000	1.000	.000
20 Operation 20		2.000-	.000	.000
Stock Room Balances				
Stockroom	Physical Stock	Allocated Stock	Available Stock	
- FG Finished Goods	26.000		26.000	
1=Select				
Position to:				
F12=Previous F22=Expand				
F3=Exit F12=Previous F15=MPS/MRP Inquiry				
F16=Item Stockroom Inquiry F17=Inventory Availability				
21-44	SF	MW	KS	IM II KENB20A PET166S2

Fields:

(Untitled)

You can enter the following:

1 - Select. When you enter this option, the Item/Stockroom Enquiry screen is displayed. You can press Enter to display the screens in turn. For more information see Item/Stockroom Enquiry.

Functions:

F22

Expand. When you select this function, additional fields are displayed.

Subcontract Stock Enquiry



12/MJI

This enquiry shows the subcontract or stock status by subcontractor for both WIP and materials shipped.



When Subcontract Stock is selected on the menu, the first Subcontractor Stock Status Enquiry screen is displayed.

Subcontractor Stock Status Enquiry Screen 1



When Subcontract Stock is selected on the menu, the first Subcontractor Stock Status Enquiry screen is displayed.

Fields:

Org Model

Enter the live organisation model.

Subcontractor

Enter the relevant subcontractor code.



When **Enter** is pressed on the first Subcontractor Stock Status Enquiry screen, the second screen is displayed.

Subcontractor Stock Status Enquiry Screen 2



When **Enter** is pressed on the first Subcontractor Stock Status Enquiry screen, the second screen is displayed.



Note: The parent item and any subcontract material is displayed.

MJ570		Z1 - GB Demonstration Company		User GBJBAMS	8/12/95 17:41:37
Subcontractor Stock Status Enquiry					
Org Model.....? 01					
Subcontractor.? GS01		Premier Food and Drug Supplies			
Item	Operation	Lot Number	Quantity		
MS001	10		2.000		
					Bottom
1=Active Shippers 2=Shipper History					
F3=Exit F4=Prompt F14=Total Stock Status ENTER=Process Selections					
00-02 S2 MW KS IM II KENB20A PET166S2					

Fields:

(Untitled)

The option is given to display open shippers associated with the item/operation/lot selected; that is, usually, for WIP inventory, where there is an outstanding balance between what has been shipped out and what is due back against a specific shipper (despatch) note; or open and closed shippers if historical data is required to be included.



Note: Shipper numbers can be closed manually before a zero balance is achieved. For material rather than WIP shipments, no returns are expected.

You can enter the following:

1 - Active Shippers. You can display shipper numbers where further receipts are expected. When you enter this option, the Subcontractor Shipper Enquiry screen is displayed.

2 - Shipper History. You can display both shipper numbers with expected receipts, and those for which no further receipts are expected. When you enter this option, the Subcontractor Shipper Enquiry screen is displayed.

Functions:

F14

Total Stock Status. When you select this function, the Total Stock Status Enquiry screen from which further full enquiries can be made is displayed.

Inventory Availability Enquiry



13/MJI

This enquiry provides visibility for:

- Inventory Management availability.
- A time-phased view of item schedules, current WIP position and projected item availability.

The enquiry calculates a projected completion date for any existing WIP balances by forward scheduling remaining operations for these balances.

It displays the WIP inventory as a time-phased summary, on the basis of availability dates which have been calculated as above.



When Inventory Availability is selected on the menu, the first Inventory Availability Enquiry screen is displayed.

Inventory Availability Enquiry Screen 1



When Inventory Availability is selected on the menu, the first Inventory Availability Enquiry screen is displayed.

Fields:

Org Model

Enter the live Organisational Model.

Item

Enter an item number for the enquiry.



When **Enter** is pressed on the first Inventory Availability Enquiry screen, the second screen is displayed.

Inventory Availability Enquiry Screen 2



When **Enter** is pressed on the first Inventory Availability Enquiry screen, the second screen is displayed.

```

MJ550                Z1 - GB Demonstration Company      User GBJBAMS      8/12/95
                                                    17:42:56

Inventory Availability Enquiry

Org.Model.?. 01
Item.....?. MS002
Product B

Available      Held
Quantity      Quantity
26.000        .000

Date      Planned      Earliest      Hours
Available Quantity S      Quantity      O/S      -----Last Operation Completed-----
1/12/95      80.000 2
4/12/95      131.000 2
8/12/95              1.000-      .189 20 Operation 20
15/12/95      13.000 2
8/01/96      47.000 2
9/01/96      131.000 2
12/01/96      5.000 2
              *
2/02/96      86.000 1
12/02/96      25.000 2
12/03/96      3.000 2

*****End Of Firm Schedule*****

F3=Exit  F4=Prompt  F12=Previous

05-16  S2  MW  KS  IM  II  KENB20A  PET166S2
  
```

Fields:

Available Quantity

This is the Inventory Management currently available balance, for all Inventory Management stockrooms (calculated as on-hand less frozen less allocated) for this item.

Held Quantity

This is the Inventory Management frozen balance total.

Date Available

The projected availability date for outstanding quantities of WIP.

Planned Quantity

The quantities of existing work schedules. Inside the firm period, firm and unplanned quantities are displayed. Beyond the firm period, suggested and firm schedule quantities are displayed.

S

Status. The schedule status. 1 indicates suggested. 2 indicates firm. 3 indicates an unplanned quantity.

Earliest Quantity

This is the quantity of WIP for which the Date Available completion date has been calculated based upon forward scheduling from the current WIP operation level.

Hours O/S

This is the number of calculated hours outstanding to complete this WIP inventory quantity. These hours do not include work performed on this WIP material, but does include work yet to be booked beyond the operation last reported.

Last Operation Completed

The last operation is reported as complete and the operation descriptions are displayed.

The message “---End of Firm Schedule---” prints at the Firm Period end date.

Inventory Movements Enquiry



14/MJI

This enquiry option provides details of on-hand and held WIP inventory movement transactions, processed by the Transaction Manager.

By using the parameters provided, the enquiry may be made very specific or cover a range of transactions. It also provides a means of searching for a particular transaction.



When Inventory Movements Enquiries is selected on the menu, the first WIP Inventory Movements screen is displayed.

Reporting types are system defined and action specific updates to the database. A reporting type is never prompted for or entered directly during any booking or reporting routine, but is invoked as a consequence of the activity type to which it is linked. Certain activity types are user defined and may be specified during booking, whilst others are actioned automatically.

Reporting type descriptions are displayed against each listed transaction. Note that not all affect WIP inventory. In addition, note that a reporting type may be associated with more than one activity type; although an activity type may only be linked to one reporting type. For a list of reporting types see Maintain Activity Control File.

Date Range

Enter the date range required. The default is today's date.

WIP Loc Range

WIP location range. Usually, WIP inventory is held in the WIP location associated with the work station defined on the planning route, or production order route depending on the origin of the inventory.

However, as WIP may be booked at other work stations with potentially dissimilar WIP locations the option is given to select a range to display ; if for example, you wanted to identify all non standard WIP balances. Left blank, all WIP inventory is included.



When **Enter** is pressed on the first WIP Inventory Movements screen, the second screen is displayed.

WIP Inventory Movements Screen 2



When **Enter** is pressed on the first WIP Inventory Movements screen, the second screen is displayed.

The screen displays a list of all the transactions.

MJ573	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:44:04
-------	-------------------------------	--------------	---------------------

WIP Inventory Movements

Org Model.....? 01 Organisational Model 01
Item.....? MS002 Product B
Operation.....? _____
Trans Type..... 1 (1= Onhand 2= Held)
Reporting Type? _____ (Blank=All)
Date Range..... 8/12/95 to 8/12/95
WIP Loc Range.? _____ to _____ (Blank=All)

	Date	Trans No	Reporting Type	Activity	WIP Loc	Op	Movement Quantity
-	8/12/95	10056	PRODUCTION REPORTING	PRODRP	FS	10	2.000
-	8/12/95	10057	PRODUCTION REPORTING	PRODRP	FS	20	2.000
-	8/12/95	10057	PRODUCTION REPORTING	PRODRP	FS	10	2.000-
-	8/12/95	10058	PRODUCTION REPORTING	PRODRP	FS	30	3.000
-	8/12/95	10058	PRODUCTION REPORTING	PRODRP	FS	20	3.000-
-	8/12/95	10058	PRODUCTION REPORTING	PRODRP	FS	30	3.000-

1=Select

F3=Exit F4=Prompt
04-20 84 MW KS IM II KENB20A PET166S2



When 1 is entered in the (Untitled) field on the second WIP Inventory Movements screen, the third screen is displayed.

WIP Inventory Movements Screen 3 (Option 1)

 When 1 is entered in the (Untitled) field on the second WIP Inventory Movements screen, the third screen is displayed.

This screen displays a detailed description of the selected transaction.

MS73		Z1 - GB Demonstration Company		User GBJBAMS		8/12/95 17:44:28	
WIP Inventory Movements - Details							
Org Model.....	01	Organisational Model 01					
Item.....	MS002	Product B					
Operation.....	10	Operation 10					
Reporting Type....	01	PRODUCTION REPORTING					
Location.....	FS	Date.. 8/12/95					
Trans Number.....	10056						
Trans Type.....	70	WIP MOVEMENT					
Activity Type.....	PRODRP	Production Reporting					
Movement Qty.....	2.000	Unit Of Measure.					
Movement Value....	73.65						
Resulting Balance..	2.000						
Lot Number.....							
Reason.....		????????????????????????????????					
Date.....	8/12/95						
Time.....	17:14:39	Week... 12		Period... 4			
Screen.....	QPADEV0016						
User.....	GBJBAMS						
F3=Exit F12=Previous							
01-02		MW		KS		IM II KENB20A PET166S2	

Stock Status and Valuation Report

1...
2... **21/MJI**

This report prints work-in-progress balances at WIP locations. WIP balances are held for completed quantities at count point operations defined on item routes.

This report can be run for negative WIP balances only, if required.

Work-in-progress locations can have on-hand, held and subcontract balances. The last two can be excluded from the report. If a count point operation is the last operation on a route, then it may have only a held WIP balance. If production from the last operation is not held, then it is automatically booked into finished goods inventory.

If WIP valuation is selected, then the balances are valued using the standard operation costs for the on-hand quantities.

The report can be sequenced by item or WIP location (or order, for production orders only). If it is sequenced by item, then all WIP balances for each item/operation are printed together.

If the report is sequenced by WIP location, all item/operation balances at WIP location are printed together.



When Stock Status & Valuation is selected on the menu, the Stock Status Report Selection screen is displayed.

MJ640	Z1 - GB Demonstration Company	User GBJBMS	8/12/95 17:45:00
Stock Status Report Selection			
Selection:			
Organisational Model.....?	_____		
WIP Locations from.....?	_____	to _____	
Item from.....?	_____	to _____	
Order.....?	_____	to _____	
Report Basis:			
Include subcontract details....	1	1=Yes	
Include held details.....	1	1=Yes	
Include Valuation.....	1	1=Yes	
Only Report Negative Inventory..	0	1=Yes	
Sequence:			
By WIP Location.....	1	1=Yes	
OR			
By Item.....	0	1=Yes	
OR			
By Order.....	0	1=Yes	
F3=Exit F4=Prompt F8 =Submit Job			
05-38	SF	MW	KS IM II KENB20A PET166S2

Fields:

Organisational Model

The model controls the WIP locations for which WIP balances are printed on the report. WIP locations are related to Organisational Model through the Work Station/WIP Location Maintenance function on the Utilities menu.

WIP Locations From/To

Enter a range of WIP locations. Leave blank to include all locations. If locations are entered, they should exist in the model specified.

Item From/To

If you wish to restrict the scope of the report to an individual item or a range of items, enter the lowest and highest items to be included in the From and To item selections. To include all items, leave the fields blank. Only those items that have operation WIP balances in the WIP locations defined to the specified model appear on the report.

Order

(Production orders only) Enter the range of production order numbers required on the report.

Include Subcontract Details

Indicates whether or not WIP balances at subcontractors should be included on the report. Enter 1 if subcontract details are to be included in the report. This is the default.

Include Held Details

Enter 1 if details of held balances are to be printed. The held quantity is included in the on-hand balance and has no effect on the valuation of WIP.

Include Valuation

This option controls whether WIP balance values are printed on the report. It defaults to 1 (yes). The value of a WIP balance is calculated by multiplying the on-hand quantity at the operation by the standard operation cost.

If the report is sequenced by item, then the values of all operation balances for the item are added together and the total printed. If the report is sequenced by WIP locations, then the values of all operation balances for each item in the WIP location are added together and a total printed for each item.

Only Report Negative Inventory

You can decide whether or not to restrict the scope of the report to negative WIP inventory balances. You can enter the following:

0 - No. Negative inventory is not required on the report.

1 - Yes. Negative inventory is required on the report.

Sequence By WIP Location

You can enter the following:

0 - No.

1 - Yes. The report is to be sequenced by WIP location. If so, Sequence By Item and Order fields must be set to 0. All WIP balances at a WIP location are grouped together, detailed by item and operation. Total item values by WIP location are printed.

Sequence By Item

You can enter the following:

0 - No.

1 - Yes. The report is to be sequenced by item. If so, Sequence by WIP Location and Order fields must be set to 0. WIP balances for all operations for an item are grouped together. Total item values are printed.

Sequence By Order

This field is only relevant to environments running production orders. Indicates whether or not the report should be sequenced by production order number.

You can enter the following:

0 - No.

1 - Yes. The report is to be requested by order. The Item and WIP Location fields must be set to 0.

WIP balances for all operations for an item are grouped together. Values are printed every time the item changes.

Held Inventory Report

1... **22/MJI**
2...

This report provides details of any held WIP inventory items. It facilitates checking to ensure items are not held any longer than necessary, and progressed in a timely way.



When Held Inventory is selected on the menu, the Held WIP Inventory Stock Status Report Selection screen is displayed.

MJ739	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 17:45:17
Held WIP Inventory Stock Status Report Selection			
Include Valuation..... ☒ 1=Yes			
Selection:			
Organisational Model.....? _____			
WIP Locations from.....? _____ to _____			
Item from.....? _____ to _____			
Operation Sequence.....? _____			
Report Basis:			
Include Held Details..... ☐ 1=Yes			
Sequence..... ☒ 1=Item/Operation, 2=Date/Held Reference Number			
F3=Exit F4=Prompt F8=Submit Job			
05-38	82	MW KS IM II	KENB20A PET166S2

Fields:

Include Valuation

Indicates if held balance values are printed on the report.

The value of the balance is calculated by multiplying the held quantity at the operation by the standard operation cost on the costing route.

0 - To exclude valuation. This is the default.

1 - To include valuation. The Hold Operation Cost flag on the Organisational Model needs to be set to 1 (yes) for the system to have the cost accounting date required to provide a valuation on WIP inventory.

Standard costs for production are used, and includes shrinkage if the Include Shrinkage in Reports flag on the Company Profile is set to 1 (yes). This setting may only be used with a report sequence of item/operation.

Organisational Model

Enter the live Organisational Model.

WIP Location Range

Enter a WIP location range or leave blank to include all locations.

Item Range

Enter an item range or leave blank to include all items.

Operation Sequence

Enter an operation or leave blank to include all operations.

Include Held Details

Indicates whether or not held reference details should be included on the report.

Sequence

Specify the report sequence for the report.

1 - To sequence by item/operation. This must be the setting for a report including WIP valuation.

2 - To sequence by date/held reference. This can only be selected if the Include Held Details field is set to 1 (yes).

Inventory Movements Report

1...
2... **23/MJI**

This report provides a printout of the inventory movements transactions and is the equivalent of the Inventory Movements Enquiry discussed earlier.



When Inventory Movements Report is selected on the menu, the WIP Movements History Report screen is displayed.

```

MJ736                Z1 - GB Demonstration Company    User GBJBAMS    8/12/95
                                      17:45:32

WIP Movements History Report

Organisational Model.?. ☐
Item Number Range....? _____ to _____
Operation Sequence...?. _____
Reporting Type.....? _____
WIP Loc. Range.....? _____ to _____
Date Range.....? 0/00/00 to 0/00/00
Week Number.....? _____
Period Number.....? _____

Report Sequence..... 1  {'1' = Date / Time           }
                        {'2' = WIP Location           }
                        {'3' = Reporting Type          }
Detail Level..... 1    {'1' = 1 line per transaction }
                        {'2' = 2 lines per transaction }

Balance Level..... 1   {'1' = Onhand}
                        {'2' = Held}

F3=Exit  F4=Prompt  F8=Submit Job

05-29    S2      MW      KS      IM      II  KENB20A  PET166S2
  
```

Fields:

Org Model

Enter the live Organisational Model.

Item Range

Enter the item number range required, leave blank for all.

Operation

Enter an operation to report specific operation WIP balances, or leave blank to include WIP at all operations.

Reporting Type

Reporting types are system defined and action specific updates to the database. A reporting type is never prompted for or entered directly during any booking or reporting routine, but is invoked as a consequence of the activity type to which it is linked. For a list of reporting types see Maintain Activity Control File.

WIP Loc Range

WIP location range. Usually, WIP inventory is held in the WIP location associated with the work station defined on the planning route, or production order route depending on the origin of the inventory. However, as WIP may be

booked at other work stations with potentially dissimilar WIP locations the option is given to select a range to display; if for example, you wanted to identify all non standard WIP balances. Left blank, all WIP inventory is included.

Date Range

Enter the date range required. The default is the current date.

Week Number

A week number, as defined to Inventory Management, may be entered to restrict the reporting of movements to the specified week entered.

Period Number

A period number, as defined to Inventory Management, may be entered to restrict the reporting of movements to the specified period entered.

Report Sequence

Indicate the sequence in which details should be reported. You can enter the following:

- 1 - For date/time.
- 2 - For WIP location.
- 3 - For reporting type.

Detail Level

Indicate the level of detail required.

- 1 - For 1 line per transaction.
- 2 - For 2 line per transaction.

Balance Level

This field determines whether transactions (movements) affecting on-hand (default) or held WIP inventory should be displayed.

- 1 - For on hand.
- 2 - For held.



Select **F8=Submit Job**.