

-
-
-
-
-

Chapter 3

Enquiries And Reports



Enquires

Item Master



1/P1E



Select Item Master on the menu to display the Production Data Item Master Enquiry screen.

Use this option to enquire on current item master details.

DB034		ZS - Style Demonstration Co.		USER GBJBAMS	29/02/96
					15:13:37
Production Data - Item Master Enquiry					
Item		ELF_B00TS Description: Elfin Boots			
Item Type: M Manufactured		Specification Ref.:		SPEC:7979	
		Fabric Type.....		LEATHER	
Planner: MS	Planning Route: 9	Costing Route:	9	Low Level Code:	
Forecast Level: 1		Planning Type:	1		
Production Sequence: 000200		Demand Policy:	2	Gtr of Sales or F/C, +	
		Smoothing Policy:	0	No Levelling	
		Planning Filter.:			
		Seasonal Profile:	02		
Min Order Qty:	150.000	Max Order Qty:	2000.000		
Mult Order Qty:	.000	Fixed Order Qty:	.000		
Safety Stock:	256.000	No. of days Supply:			
M/F Lead Time :	.09	Cumulative Lead Time:	49.09		
Primary Stockroom: FG Finished Goods Stockroom					
Order Policy: A Discrete		Mat'l Control Policy: 0 Formal issue			
F3=Exit		F12=Previous		F18=Additional Parameters	
				F22=Costs	
01-02		MW		KS IM II KENB20A PET166S2	

Fields:

Item

Enter an item code.

Low Level Code

Displays the lowest level at which the item appears on any route/BOM and is used by MPS and MRP to ensure their efficient processing. This is the only system maintained field. All other details are explicitly set against the item definition.

Functions:

F18

Display additional parameters.

F22

Display associated elemental costs.

Cost Centres



2/P1E



Select Cost Centres on the menu to display the Cost Centre Enquiry screen.

This enquiry displays the current values of standard and current rates for:

- Machines.
- Labour.
- Set up.
- Fixed and variable overheads.

DB020		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96	
						12:27:07	
Cost Centre Enquiry							
Cost Centre... ELF01							
Description... Elfin cost centre 1							
Department.... ELFIN							
				Standard		Current	
Machine	Rate/hr	2.70000		3.40000			
Labour	Rate/hr	3.55000		4.23000			
Setting	Rate/hr	3.33000		2.78900			
O/H 1	Method	E		E			
O/H 1	Rate		5.00000		5.00000		
O/H 2	Method	A		A			
O/H 2	Rate		5.00000		6.00000		
O/H 2	Value		.00000		.00000		
F3=Exit F12=Previous							
01-02		MW		KS		IM	
		II		KENB20A		PET166S2	

Fields:

Cost Centre

Enter a cost centre code.

Machines



3/P1E



Select Machines on the menu to display the Machine Enquiry screen.

This enquiry displays the current set up of the machine definition.

DB005

ZS - Style Demonstration Co.

USER GBJBAMS

27/02/96
16:30:20

Machine Enquiry

Machine..... ELF01

Description... Elfin preliminary work group

Department.... ELFIN

Foreman..... MS

Queue Time. 3.000

Std. Efficiency 100.000 %

Max Length

Std Length

Max Capacity

Std Capacity

Shift 1.....

24.0

8.0

24.0000

8.0000

Shift 2.....

Shift 3.....

Duration Calculation Basis (Default): 4 Greater of M/C or Lab,+Setting

Shift Profile (Default).....: 01 Day Shift

Default Shift Profile Capacity Factor...: Max... 10.00

Std... 5.00

Cost Centre... ELF01 Elfin cost centre 1

Calendar Code. 01

F3=Exit

F12=Previous

F20=Daily Profile

01-02

S*

MW

KS

IM

II

KENB20A

PET166S2

Fields:

Machine

Enter a machine code.

Functions:

F20

Display associated daily capacity profile.

Work Centres

1...
2...

4/P1E



Select Work Centres on the menu to display the Work Centre Enquiry screen.

Use this option to enquire upon current work centre details.

```

DB021      ZS - Style Demonstration Co.      USER GBJBAMS      27/02/96
                                           16:32:07

Work Centre Enquiry

Work Centre ..... WC1      Description Body Forming

Machine Description      Machine Description
CARD      Card room
HARD      Hardening

F3=Exit      F12=Previous      F21=Text

08-02      SF      MW      KS      IM      II      KENB20A      PET166S2

```

Fields:

Work Centre

Enter a work centre code.

Functions:

F21

Displays any text associated with the work centre.

Shift Profiles



5/P1E



Select Shift Profiles on the menu to display the Shift Profile Enquiry screen.

Use this option to enquire upon established shift profiles.

DB141	ZS - Style Demonstration Co.		USER GBJBAMS	27/02/96
				16:23:50
Shift Profile Enquiry				
Profile Code... 01				
Description.... Day Shift		As At... 00/00/00		
No.	Start Time	Finish Time	Effective From Date	Effective To Date
1	8:00	9:30	2/01/95	99/99/99
2	9:45	12:00	2/01/95	99/99/99
3	12:30	14:30	2/01/95	99/99/99
4	14:45	16:30	2/01/95	99/99/99
Comment				
F3=Exit F12=Previous				
06-60	SA	MW	KS	IM II KENB20A PET166S2

Fields:

Profile Code

Select a shift profile to enquire on.

As At

This is the effective date which will determine the shift entries displayed.

(Untitled)

Enter the start and finish time of the shift using the 24 hour clock.

Bundle Ticket Types



6/P1E



Select Bundle Ticket Types on the menu to display the Bundle Ticket Type Enquiry screen.

Use this option to enquiry upon bundle ticket type definitions.

DS691	ZS - Style Demonstration Co.	USER	GBJBAMS	29/02/96
				16:34:43
Bundle Ticket type Enquiry				
Bundle Ticket Type..... BTA				
Description.....	Button Bundle			
Search Family.....	C/S	Colour & Size		
Bundle Quantity.....	48.000	UOM.....	EA	
Bundle Quantity Variance.....	23.000			
Final Bundle Policy.....	0			
Document Type.....	4	Non-barcoded - A4 layout		
Ticket for Finished Goods Receipt..	0	(1=Yes)		
Finished Goods-Default Bundle Qty..	0	(1=Yes)		
Barcodes on Ticket.....	0	(1=Yes)		
No. of labels per Bundle.....				
Parallel Ticket Type.....	1	(1=Yes)		
F3=Exit F12=Previous F18=Characteristics Mix				
05-24	82	MW	KS	IM II KENB20A PET166S2

Fields:

Bundle Ticket Type

Enter a bundle ticket type code.

Functions:

F18

Display characteristics (dimensions) mixing rules.

Labour Skills



7/P1E



Select Labour Skills on the menu to display the Labour Grade Enquiry screen.

Use this option to view current labour skill and rate definitions.

DB254	ZS - Style Demonstration Co.	User	GBJBAMS	27/02/96
				16:34:11
Labour Grade Enquiry				
Labour Skill... E1				
Description.... Engineer				
Effective Date. 0/00/00				
Expiry Date.... 99/99/99				
F3=Exit F12=Previous F20=Skill Rates				
01-02	SE	MW	KS	IM II KENB20A PET166S2

Fields:

Labour Skill

Enter a labour skill code.

Functions:

F20

Display pay rates associated with this skill.

Labour Profiles



8/P1E



Select Labour Profiles on the menu to display the Labour Profile Enquiry screen.

Use this enquiry to view current labour profile details.

DS702	ZS - Style Demonstration Co.	USER GBJBAMS	27/02/96		
			16:35:48		
Labour Profile Enquiry					
Labour profile...: A1					
Description.....: Labour Profile 1					
Calendar.....: 01					
Department.....: DEPT01					
Shift Profile.....: 02					
Standard Efficiency..: 85.000 %					
Labour Grades included:					
Grade	Description	Qty	Time%	From	To
E1	Engineer	1	5	1/01/95	1/01/96
L1	Sewing Operator 1	2	100	0/00/00	99/99/99
S1	Supervisor	1	20	0/00/00	99/99/99
F3=Exit F12=Previous					
05-32	S	MW	KS	IM	II KENB20A PET166S2

Fields:

Labour Profile

Enter a labour profile code.

Subcontractors



9/P1E



Select Subcontractors on the menu to display the Subcontractor Enquiry screen.

DB287

ZS - Style Demonstration Co.

User

GBJBAMS

29/02/96

17:22:05

Sub-Contractor Enquiry

Item.....?.

Route.....?.

Operation.....?.

Subcontractor.....?.

F3=Exit

F4=Prompt

F16=Supplier Enquiry

05-24

S

MW

KS

IM

II

KENB20A

PET166S2

Fields:

Style

Enter the style code which uses a subcontract operation(s).

Route

Enter the route of the style/route/operation to enquire on. It is possible to define separate subcontractors for the same style on different routes.

Operation

Enter the specific subcontract, or prior, operation.

Subcontractor

Enter subcontractor code.

Standard Operations



10/P1E

Use this option to enquire upon a standard operation group. You may also view all the operation details defined for the selected group.



Note: The enquiry initially displays key operations.



Note: Additional options and functions other than those listed on the Options and Functions lines are available. The STDE type parameter on the parameter file enables you to define options and functions in addition to those supplied as standard.

Standard Operations Enquiry Screen 1

-  Select Standard Operations on the menu to display Standard Operations Enquiry screen 1.

From this screen, select an operation group.

Fields:

Operation Group

Enter an operation group code.

-  Press **Enter** on Standard Operations Enquiry screen 1 to display Standard Operations Enquiry screen 2.

Standard Operations Enquiry Screen 2



Press **Enter** on Standard Operations Enquiry screen 1 to display Standard Operations Enquiry screen 2.

This screen displays standard operation details for the selected operation group.

The screens and windows that follow are the same as for the Standard Operations maintenance option, but you cannot update details.

DS153	ST - Style Test & QA Company	USER QASTYLE	27/02/98
			10:07:40
Standard Operations Enquiry			
Group: W 6210/Cut ops 2			
0	G	Opsq	OpCode
■	W	10	10
-	W	20	20
-	W	30	30
-	W	40	40
		Description	Labour Specification ID.
		Cutting Machine 1	1.0000
		Cutting Machine 2	100.0000
		Cutting Machine 3	.5000
		Cutting Machine 4	10.0000
1=Select			
F3=Exit F12=Previous F13=Position To F23=More Options F24=More Keys			
6-2	SA	MW	KS CL IM DM II MARVIN KB PED201S1

Style Route/Bill Of Materials



11/P1E



To display the Routes/Structures Enquiry screen, select Style Route/Bill of Materials.

This enquiry lets you review style routes/bills of materials based on different routes, quantities and effectivity dates.

The screens and windows that follow are the same as for the Style Route/Bill Of Materials maintenance option.



Note: Additional options and functions other than those listed on the Options and Functions lines are available. The STYE type parameter on the parameter file enables you to define options and functions in addition to those supplied as standard

DB630

ZS - Style Demonstration Co.

USER GBJBAMS

29/02/96
17:16:35

Routes/Structures Enquiry

Style.....?..

Route

Quantity.....

Include wastage....

As at.....

Ignore Effectivity.

0

29/02/96

0

(Zero assumes Economic Order Qty.)

(1=Yes)

(1=Yes)

F3=Exit

F4=Prompt

F16=Item search

06-25

S

MW

KS

IM

II

KENB20A

PET166S2

Fields:

Style

Enter the style you wish to review

Route

Enter the route you wish to enquire on.

Quantity

This parameter allows you to see the effect of producing different sized batches (lot sizes) of the product. Material requirements are displayed proportionate to the standard lot size defined under the Style Route/Bill of Materials option.

By reducing or increasing the batch quantity here, the material requirements will be reduced or increased accordingly.

Blank - The system will assume the economic order quantity (EOQ) held on the route.

Include Wastage?

If you have specified operation and/or material wastage for this route, you can model the effect of wastage on the material requirements.

As At

This is the effective date which will determine the configuration of the bill of materials.

The procedure compares this control date with the effective start and end date on the route/BOM record of each material. If the effective date is less than the start date or greater/equal than the end date, the material is not extracted for display. The date defaults to the current date.

Ignore Effectivity

You may view the bill of material as a totality, that is, all materials will be shown irrespective of their effectivity status.

Functions:

F16

Enables an inventory search on the style prompt.

Text



12/P1E



Select Text on the menu to display the Text Enquiry screen.

This enquiry shows the current contents of the text file.

TX003	ZS - Style Demonstration Co.	USER GBJBAMS	5/03/96
Text Enquiry			15:34:41
Major Type...?..	█		
Sub-Type....?..			
File Key....?..			
F3=Exit F4=Prompt			
04-20	SE	MW	KS IM II KENB20A PET166S2

Fields:

Major Text Type

Enter the major text type you wish to enquire on.

Text Sub-Type

Enter the text sub-type for the major type you wish to enquire on.

Indented Materials Enquiry



13/P1E



Select Indented Materials Enquiry on the menu to display the Indented Materials Enquiry screen.

This enquiry provides a fully indented explosion of styles with structures. In addition, you can view a fully indented where-used analysis of a material.

```

DB007              ZS - Style Demonstration Co.      USER GBJBAMS    29/02/96
                                                    17:17:22

Indented Materials Enquiry

Style/Material...?: █
Route.....?: _

Materials Route....: 2          1=Costing Route    2=Planning Route
                               3=Entered Route

Quantity.....: .000 (Zero assumes Economic Batch Size)

Enquiry Type.....: 1          1=Explosion without wastage
                               2=Explosion with wastage
                               3=Where-used without wastage
                               4=Where-used with wastage

As at.....: 29/02/96
Ignore Effectivity.: _        1=Yes

F3=Exit  F4=Prompt  F16=Item Search

05-24    SE    MW    KS    IM    II  KENB20A  PET166S2
  
```

Fields:

Style/Material

Enter an item code. The display screen enables further explosions and retrievals to be requested without returning to this screen.

- Style for which an indented exploded list is required.
- Material for which an indented where-used retrieval is required.

Route

Enter the route for the first level explosion or implosion.

Materials Route

- For explosions, this route specifies the route which will be exploded for materials found in the first level parent style.
- For where-used enquiries, it determines which parents are imploded, by selecting parent style routes which match the entered route code.

Enquiry Lot Size

Enter a lot size which material requirement calculations are to be based upon. You can specify a quantity to reflect the different usage's of your routes. For example, you can enter a formulation batch size, a production batch size or an

accounting batch quantity. The material requirements will be adjusted according to the quantity selected.

The quantity defaults to the EOQ defined for the selected route. In the case of where-used enquiries this is the EOQ of the identified parent routes.

Enquiry Type

You can perform both types of enquiry taking into account or excluding wastage. The 'with wastage' options show material requirements based on the occurrence of planned operational and material wastage in the selected routes.

The default option is Indented Explosion without Wastage.

As At

Enter a date to establish the effectivity of materials in explosion or where-used enquiries. Only materials effective on this date will be selected for extraction and display. The date defaults to the current date.

Ignore Effectivity

You can view all materials regardless of their effectivity dates by selecting this option.

Bill Of Materials Explosion Screen



This screen is displayed as a consequence of requesting an explosion or where-used enquiry from the Indented Materials Enquiry.

The screen shows the total material structure of a style exploded down to the lowest level material, displayed as an indented list. In addition, a multi-level where-used implosion of a material can be requested which gives full visibility of the intermediate and ultimate consumption of the material, as well as its immediate parents. Usually, within Style Production, indented explosions rarely go below level 1.

A full list of selection parameters are enabled at the bottom of the screen to allow further display. The prompt requirements and definitions are exactly the same as those on the preliminary level.

DB007		ZS - Style Demonstration Co.		USER GBJBAMS	29/02/96
					17:18:05
Indented Bill of Materials Enquiry					
Style: ELF_BOOTS		Elfin Boots			
Quantity: 50.000		UOM: EA		Route: 2 As at 29/02/96 * Excludes wastage	
Receive into Stockroom FG		T			
Level	Input	St Description	P	Quantity	UOM
1	LEATHER	RM Leather (Elfins)	P	500.000	MT
1	CUTTER	RM Knife (Elfin)	T	5.000	EA
1	LACES	RM Laces (Elfins)	B	100.000	EA
1	SOLES	RM Soles (Elfins)	P	100.000	EA
1	EYELETS	RM Boot eyelets	B	400.000	EA
1	BOX	RM Boxes (Elfin)	B	50.000	EA
Item: <u>ELF_BOOTS</u>		Route: 2 Qty: <u>50.000</u>			
Material Route: <u>2</u>		(1=Costing Route 2=Planning Route 3=Entered Route)			
Enquiry Type.: <u>1</u>		(1 or 2 Parent Explosion - 3 or 4 Material Where-Used)			
F3=Exit F4=Prompt		F12=Previous F16=Item Search			
21-08 <u>S</u>		MW	KS	IM	II KENB20A PET166S2

Single Level Materials Where Used



14/P1E



Select Single Level Materials Where-Used on the menu to display the Material Where-Used Enquiry screen.

This enquiry provides a single-level implosion of a material to identify the style(s) on which the material is used.

Material

Enter a material code. This enquiry is single level, and will identify all immediate parents of the style.

As At

Enter a date to control the selection of parents for this material. Only style routes where the material is effective as at this date will be selected for display. The date defaults to the current date.

Ignore Effectivity

You can view all parents regardless of the material effectivity.

DB008		ZS - Style Demonstration Co.		USER GBJBAMS	29/02/96
Material Where-Used Enquiry					17:19:10
Material: LEATHER		Leather (Elfins)			
UOM.....: MT		Level 1		Effective as at 29/02/96	
Parent Item	Rte	Oper	Description	Quantity	Fix UOM
ELF_BOOTS	A	10	Material Assimilation	.000	EA
ELF_BOOTS	1	10	Layout of material	10.000	EA
ELF_BOOTS	2	10	Layout of material	10.000	EA
ELF_BOOTS	5	10	Layout of material	10.000	EA
ELF_BOOTS	5	10	Layout of material	1.500	EA
ELF_BOOTS	6	10	Layout of material	10.000	EA
ELF_BOOTS	7	10	Layout of material	10.000	EA
ELF_BOOTS	8	10	Layout of material	10.000	EA
ELF_BOOTS	9	10	Layout of material	10.000	EA

Material...: LEATHER		As at.: 29/02/96		1=Ignore Effectivity	
F3=Exit	F4=Prompt	F16=Item search	F12=Previous		
23-15	SP	MW	KS	IM	II KENB20A PET166S2

Reports

Item Master

1...
2...

20/P1E



Select Item Master on the menu to display the Production Data Item Master Report Selection screen.

```

DB019P      ZS - Style Demonstration Co.      USER GJBAMS      29/02/96
                                           15:15:24

Production Data - Item Master Report Selection

To produce a report showing a range of Items key in BOTH fields.
To produce a report for a specific Item key in the FROM field.
To produce a report for all Items leave BOTH fields blank.

Item Range:      From...?.. _____
                  To.....?.. _____

Print Production Details.. _ 1=Yes

Print Costing Details..... 1 0/blank = Print no Costs
                               1 = Standard Costs only
                               2 = Entered Cost Set Range only
                               3 = Standard and Entered Cost Set Range
                               4 = All Costs

Cost Set Range: From..... _____
                  To..... _____

-----
F3=Exit      F4=Prompt      F10=Cost presentation      ENTER To Submit

09-30      SF      MW      KS      IM      II      KENB20A      PET166S2

```

Fields:

Item Range

Enter an item range. Leave blank to report all items.

Print Production Details

You can request a detailed style report showing the current database values or a summary report showing the recorded standard and current costs.

Print Costing Details

Specify whether or not you require costing details on the report.

Cost Set Range

Enter a cost set range if option 2 or 3 was selected above.

Functions:

F18

Open cost presentation window.

Cost Centres



21/P1E



Select Cost Centres on the menu to display the Production Data Cost Centre Report Selection screen.

This report prints out details for one or a range of cost centres as entered via Cost Centre Maintenance.

DB024P	ZS - Style Demonstration Co.	USER GBJBAMS	5/03/96 12:27:24
Production Data - Cost Centre Report Selection.			
To produce a report showing a range of Cost Centres key in BOTH fields.			
To produce a report for a specific Cost Centre key in the FROM field.			
To produce a report for all Cost Centres leave BOTH fields blank.			
From		To	
Select...?...: _____		_____	
F3=Exit F4=Prompt ENTER To Submit			
15-27	SE	MW	KS IM II KENB20A PET166S2

Fields:

Cost Centre Range

Enter a cost centre range. Leave blank to print all cost centres.

Machines



22/P1E



Select Machines on the menu to display the Production Data Machine Report Selection screen.

This report lists machine details as defined via Machines Maintenance.

DB009P	ZS - Style Demonstration Co.	USER GBJBAMS	27/02/96
			16:30:34
Production Data - Machine Report Selection			
To produce a report showing a range of Machines key in BOTH fields.			
To produce a report for a specific Machine key in the FROM field.			
To produce a report for all Machines leave BOTH fields blank.			
	From	To	
Select...?..:	_____	_____	
Sequence....:	_ (1=Cost Centre 2=Department 3=Machine)		
Type.....:	_ (1=Detail 2=Summary)		
F3=Exit F4=Prompt ENTER To Submit			
14-27	SE	MW	KS IM II KENB20A PET166S2

Fields:

Machine Range

Enter a machine range. Leave blank to print all machines.

Report Sequence

You can sequence the report in three ways:

- 1 - By cost centre to show all machines in a cost centre.
- 2 - By department to show all machines in a department.
- 3 - By machine.

Report Type

You can produce a detailed report or summary listing:

- 1 - Detailed report.
- 2 - Summary listing.

Work Centres



23/P1E



Select Work Centres on the menu to display the Production Data Work Centre Report Selection screen.

This report lists current work centre details.

DB026P	ZS - Style Demonstration Co.	USER GBJBAMS	27/02/96 16:32:32
Production Data - Work Centre Report Selection			
To produce a report showing a range of Work Centres key in BOTH fields.			
To produce a report for a specific Work Centre key in the FROM field.			
To produce a report for all Work Centres leave BOTH fields blank.			
<u>FROM</u>		<u>TO</u>	
Select.....?. _____		_____	
F3=Exit F4=Prompt ENTER To Submit			
15-27	SE	MW	KS IM II KENB20A PET166S2

Fields:

Work Centre Range

Enter a work centre range. Leave blank to print all work centres.

Shift Profiles

1...
2...

24/P1E



Select Shift Profiles on the menu to display the Shift Profile Report Selection screen.

This report prints the current shift patterns for the selected shift profiles.

```
DB142                ZS - Style Demonstration Co.          USER GBJBAMS          27/02/96
                                                                16:24:09

Shift Profile Report Selection

Shift Profile Code: From...?...    (Blank for start)
                        To.....?...    (Blank for end)

As At Date..... 0/00/00

Print Where Used?.....    (1=Yes)

F3=Exit  F4=Prompt  ENTER To Submit

07-44      S2          MW          KS          IM          II  KENB20A  PET166S2
```

Fields:

Shift Profile Range

Enter a shift profile range. Leave blank to print all shift profiles.

As At Date

Specify an effective date to capture the effective shift patterns at a particular point in time. Only effective shifts will be selected.

Print Where-Used?

You can report all machines that use the shift profile(s).

Labour Skills



25/P1E



Select Labour Skills on the menu to produce a Labour Skills report.

Use this option to view current labour skill definitions and hourly rates.

The report is run immediately the option is selected.

Labour Profiles



26/P1E



Select Labour Profiles on the menu to display the Labour Profile Reports screen.

This report lists current labour profile details.

DS704P

ZS - Style Demonstration Co.

USER GBJBAMS

27/02/96
16:36:04

Labour Profile Reports

Enter From labour profile...?...:

(Leave blank for all)

To labour profile.....?...:

Effective from.....:

(enter zeros for start)

Effective to.....: 999999

(enter 999999 for end)

F3=Exit

F4=Prompt

ENTER To Submit

05-36

84

MW

KS

IM

II

KENB20A

PET166S2

Fields:

Labour Profile Range

Enter a labour profile range. Leave blank to include all labour profiles.

Effectivity Range

Enter a date range to include only profiles effective between two dates. Accept the defaults to include all profiles.

Subcontractors



27/P1E



Select Subcontractors on the menu to run the Subcontractors report.



Note: This report is run immediately the option is selected.

Style Route/Bill Of Material

1...
2...

28/P1E



Select Style Route/Bill Of Material on the menu to display the Route/BOM Report Selection screen.

This report produces a listing of selected route/material details.

```

DB010P          ZS - Style Demonstration Co.      USER GBJBAMS      29/02/96
                                           17:17:00

Route/BoM Report Selection

Print Items In The Range From: _____ (blank for first)
                               To: _____ (blank for last)

Print Route code.....: _____
OR Print All Route codes.....: 1

Quantity.....: _____ (Zero assumes Economic order qty.)

Include Wastage.....: 0

Effective As At.....: 29/02/96

Ignore Effectivity.....: 0

Detail level.....: 0 (0=All 1=Operations 2=Materials)

0=No 1=Yes
-----
F3=Exit  F4=Prompt  ENTER To Submit
05-33   SF        MW        KS        IM        II  KENB20A  PET166S2

```

Fields:

Style Range

Enter a style code. Leave blank to include all styles. A single style variant can be selected by entering the same style variant in both the from and to fields.

Route

Enter the route you wish to print details for.

Or Print All Routes

You can produce a report for all defined routes for the styles selected.

Quantity

Enter the desired batch size of the route(s) you are reporting on. Material requirements will be based on this quantity. The default quantity is the economic order quantity defined for the selected route.

Include Wastage

You can optionally base the material requirements on any planned wastage defined at operation or material level on the selected routes.

Effective As At

Enter an effective date to trap the live configuration of the selected style routes at a particular point in time. Only materials effective on this date will be extracted and reported. The date defaults to the current date.

Ignore Effectivity

You can report on all materials in selected style routes regardless of their effectivity.

Detail Level

You can select from 3 levels of detail to be printed on the report.

0 - All. Print operations (routes) and bills of materials (BOMs) details.

1 - Operation (route) details only.

2 - Bills of materials (BOMs) only.

Text



29/P1E



Select Text on the menu to display the Text Report Select Parameters screen.

This report prints details of the selected text categories.

TX005

ZS - Style Demonstration Co.

USER GBJBAMS

15:34:59

Text Report - Select Parameters

Major Type....?.

Sub-Type.....?. (Blank for all)

From File Key.?. (Blank for First Key)

To File Key...?. (Blank for Last Key)

F3=Exit F4=Prompt ENTER To Submit

04-20  MW KS IM II KENB20A PET166S2

Fields:

Major Text Type

Enter the major text type you wish to report on.

Sub-Type

Enter the sub-type text type you wish to report on.

From File Key

Enter the key of the text entity you wish to report on. Leave blank to print all text entities for Major/Sub-type combination.

To File Key

Enter the file key of the text entity you wish to print up to. Leave blank to print to the end of the file for the major/sub-type combination.

Indented Materials Report



30/P1E



Select Indented Materials Report on the menu to display the Indented Bill of Materials Report Selection screen.

This option produces an indented cost report for selected styles. All levels of the requested routes are processed to provide a simulation of the cost of production without reference to recorded style unit costs, except for bottom level material costs. The methodology is the same as that used by the Indented Costed Simulation enquiry (11/P1C).

Selection parameters allow you to:

- Use alternative methods of production.
- Use alternative material costing methods.
- Specify material effectivity dates.
- By changing the batch quantity size, simulate different batch and unit costs.

The report provides a detailed analysis of operation and material costs in an indented format, so it is easy to see how costs are built up through successive levels of product definition.

The cost element analysis is by default determined by the cost element management rules defined on the Company Profile. However, it is possible to tailor these rules to suit your requirements for a specific report, without effecting any changes to the Company Profile settings.

DB074	ZS - Style Demonstration Co.	USER GBJBAMS	29/02/96 17:18:32
Indented Bill of Materials Report Selection			
From Style.....?..		(Blank for start of file)	
To Style.....?..		(Blank for end of file)	
Route		or type 'ALL' for all Routes	
Material Route.?		(1=Planning 2=Costing 3=Entered route)	
Batch Quantity....		(Blank for Economic Order Qty)	
Costing Method....		(1=Standard 2=Entered Cost Set 3=No Costing)	
Cost Set.....			
Inc.wastage.....		(1=Yes)	
Material Costs....		(1=Production 2=Inventory)	
Operation details		(1=Yes)	
As at	29/02/96		
Ignore effectivity		(1=Yes, none costing report only))	
F3=Exit F4=Prompt F18=Cost presentation ENTER To Submit			
05-20	SE	MW	KS IM II KENB20A PET166S2

Fields:

Style Range

Enter a style range. Leave blank to report on all styles.

Route

Enter the route code to be used for the first level explosion of material styles and the calculation of 'this level' production costs for the selected styles. To select all routes, tab to the next prompt and type 'ALL'.

Or Type 'All' For All Routes

Enter 'ALL' to report on all routes defined for the selected styles.

Material Route

Low level material costs will be calculated against this route.

Batch Quantity

Enter the batch quantity to be costed. If left blank, the EOQ defined for each selected style/route will be used. The batch quantity will determine all lower level material usage, and be used to amortise fixed costs against when developing a unit cost for all selected styles.

Fixed costs are derived from the following:

- Set-up labour time.
- Fixed time, operation, labour and machine costs.
- Fixed user-defined costs.
- Fixed overheads.

(Production) Costing Method

Enter the costing method you wish to use to calculate production costs. You may choose not to include costs at all.

Cost Set

If option 2 was selected above, enter the cost set to be interrogated. The blank cost set (standard costs) will automatically be used if option 1 was selected. This field will be used to determine material costs:

- If Material Costs is subsequently set to 1 the system will use standard cost centre rates and standard material costs.
- If Material Costs is set to 2 the system will use current cost centre rates and non-standard material costs from the entered cost set.

Inc. Wastage

You can generate costs that take account of operational and material wastage. The default value of this parameter is defined on the Company Profile.

Material Costs

Unit material costs can be obtained from two sources:

1 - Use Production standard or entered cost set.

2 - Use Inventory stockroom value. This will use the cost held on the primary stockroom record for each material input; against the material's default costing method (standard, latest, average or FIFO) as defined via the Style/Material Details, Stockroom Details Maintenance screen.

These are the only recorded costs that are used to calculate style costs.

Operation Details

The report can optionally include summary operation details.

As At

Enter a date to establish the effectivity of the materials in exploded routes. Only materials that are effective on the specified date will be extracted for processing and cost contribution. The date defaults to the current date.

Ignore Effectivity

If you are producing an indented report without costs you can report on all materials regardless of their effectivity.

Functions:

F18

Enables you to redefine and/or alter the presentation sequence of cost elements for this report.

Materials Where Used



31/P1E



Select Materials Where Used on the menu to display the Materials Where Used Report Selection screen.

This report creates a single level where-used report for materials.

DB012P ZS - Style Demonstration Co. USER GBJBAMS 29/02/96
17:19:35

Materials Where Used Report Selection

From Material.....?. (Blank for start of file)

To Material.....?. (Blank for end of file)

Route?. or type 'ALL' for all Routes

As at date..... 29/02/96

Ignore Effectivity.. (1=Ignore Effectivity)

F3=Exit F4=Prompt ENTER To Submit

06-24 MW KS IM II KENB20A PET166S2

Fields:

Material Range

Enter a range of materials. Leave blank to include all materials.

Route

Enter the route you wish the system to use when imploding the selected materials to identify the styles they are used on. Only styles with this route defined will be extracted and reported on. Alternatively, tab to the next field to select all routes.

Report On All Routes

Enter 'ALL' in this field to report on all parents of selected materials on all defined routes where used.

As At Date

Enter an effective date to control the selection of styles. Only routes where a material is effective on the entered date will be imploded and the styles reported on.

Ignore Effectivity

You can report on all parents regardless of the effectivity.

Machine/WCentre Where Used



32/P1E



Select Machine/WCentre Where-Used on the menu to display the Production Data Machine/Work Centre Where Used Selection screen.

This report generates details of routes that use the specified work centres and machines. It identifies where machines and work centres are defined on style route operations. This facility enables you to assess the operational impact of changing a machine or work centre.

DB032P	2S - Style Demonstration Co.	USER GBJBAMS	29/02/96
			17:20:04
Production Data - Machine/Work Centre Where Used Selection			
To produce a report for a range of Machines/WrkCentres key in BOTH fields.			
To produce a report for a specific Machines/WrkCentres key in the FROM field.			
To produce a report for all Machines/WrkCentres leave BOTH fields blank.			
	<u>FROM</u>	<u>TO</u>	
Select...?..:	_____	_____	
Sequence.....:	1	(1=Machine 2=Work Centre	)
F3=Exit F4=Prompt ENTER To Submit			
15-27	SP	MW KS IM II	KENB20A PET166S2

Fields:

Select

Enter a machine or work centre range.

Sequence

You can sequence the report by machine or work centre.

Company Profile



33/P1E



Select Company Profile on the menu to run the Company Profile report.

This option submits a batch job to produce a report, listing details entered on the Style Production Company Profile.



To submit a batch job, press **F8**.