

-
-
-
-
-

Chapter 3

Utilities



Style Advanced Shipment Notices Utilities

This section defines the Advanced Shipping utilities procedures and relates to the following areas of the system:

- Company Profile maintenance
- Start / Stop ASN EDI Send

Company Profile Maintenance



1/STASU

Style Advanced Shipment Notices Company Profile defaults are entered from the Company Profile screen.

The ASN Defaults screen, and the Self Billing Parameters screen are displayed depending upon the input to the General Defaults.

Company Profile Maintenance Selection Screen



Select the Company Profile Maintenance option from the menu to display the Company Profile Maintenance screen.

```
AS010                                GJBAPH2  16/02/96
Company Profile Maintenance           14:17:31
Enter Company code ..... ? █

F3=Exit  F4=Prompt
05-30    SF      MW      KS      IM      II  KENB20A  PET007S1
```

Fields:

Enter Company Code

Enter the code of the company that you want to maintain.



Press **Enter** to display the Company Details screen.

Company Details Screen



Press **Enter** from the Company Profile Maintenance screen to display the Company Details screen.



*Note: In addition to maintaining the company profile in Advanced Shipping, Advanced Customer Scheduling Company Profile (if attached) will automatically lead in to the Advanced Shipping Company Profile after you select the final **F8=Update**.*

AS025ST - Style Test & QA CompanyUser: GBJBARW220/01/9810:20:44

Advance Shipment Notice - Company

Last consignment reference.....00000000

Shipping weight UOM.....?. _

Shipping volume UOM.....?. _

Transmit ASNs....._ (0/1)

Ship lead time in days....._

Display qtys as integers.._ (0/1)

F3=Exit F4=Prompt F8=Update F12=Previous

3-35SA MW KS CL IM DM II STUD140 KB PET179S1

Fields:

Last Consignment Reference

The system will display the last consignment number used or will default to 00000000 on the first set-up. This field is mandatory.

Shipping Weight UOM

This shows the company wide weight unit of measure for all shipping weights. This will default to blank, thus forcing an entry on the first time through for each Company. This field is mandatory.

Shipping Volume UOM

This field contains the default unit of measurement code for the volume of the consignment. Optionally enter a valid UOM code. This field is mandatory.

Transmit ASNs

This indicator identifies whether Advanced Shipment Notifications will be transmitted via EDI.

0 - ASNs are not to be sent via EDI. This is the default.

1 - ASNs are to sent via EDI.

This field is reserved for future use.

Ship Lead Time In Days

This flag indicates forecast requirements to be ship lead time adjusted. The default is 0. This flag can only be set to 1 if Ship Lead Time in Days is greater than zero.

Display Qtys As Integers

This is a system wide parameter and applies to Advanced Customer Scheduling and Advanced Shipping.

0 - Quantities are to be shown as decimal values up to 3 decimal places.

1 - Quantities are to be shown as whole numbers only. This is the default.



Press **Enter** to revalidate the screen. If Transmit ASNs is set to one, press **Enter** a second time to display the ASN Defaults.

Functions:

F8

This saves any changes made up to this point and displays the original selection screen. You **MUST** add data to all the associated company default screens the first time you set up a company.

Company ASN and Pack Details Defaults Screen

Use this screen to enter the Advanced Shipment Notification and Pack Detail default values. It is accessed via the Company Profile screen if the Create Pack Details or Transmit ASNs flags are equal to 1. If values are entered here, they will be used as defaults for the customer values and the Contract default.

```
AS030          ST - Style Test & QA Company      User GBJBARW2    20/01/98
                                           10:36:54
Advanced Shipment Notices ASN & Pack Details Defaults

Default pack type.....?. █
Default pallet type.....?. █
Transmit ASNIX12 856s..... (0/1) UCC manufacturers code.....
856 hierarchical levels..?. - - - -

F3=Exit F4=Prompt F8=Update F12=Previous

6-30  SA MW KS CL IM DM II STUD140 KB PET179S1
```

Fields:

Default Pack Type

Enter the pack type. This field is optional.

Default Pallet Type

Enter the pallet type. This field is optional.

Transmit ASNIX12 856s

This field indicates whether ASNIX12 856 ASNs are transmitted. The following options are available:

0 = No. The system will continue to send ASNs.

1 = Yes. The system will send ASNIX12 856 ASNs.

UCC Manufacturers Code

Enter code when UCC 128 container codes must be sent. This field is optional and is used in 856 ASNs if entered.

856 Hierarchical Levels

Enter up to 5 one character codes to indicate the default of the hierarchical level.

A default structure must be set up on this screen in order for 856 ASNs to be transmitted correctly. The default is associated with each consignment and automatically copied down to the customer details as a suggested default. It can be overridden on the Customer Defaults ASN And Pack Details screen and the Consignment Header screen.

This option allows you to set up what consignment details to send and in what sequence. The options available are:

S - Shipping. This option is defaulted and fixed to first position.

T - Tare. Pallet details.

O - Order. Order details

I - Item. Item details

P - Packing details.



Note: T,O,I and P can be entered in any order or omitted.



Press **Enter** to validate the screen.



Press **F8=Update** to update the entered details onto the Company parameters database.

Start ASN EDI Send

1...
2...

32/STASU

This is a background process which sends ASNs to the EDI function. This program must be run for all send / resend items identified.

This is a background/sleeper job, when active it monitors all ASNs to be sent.

Stop ASN EDI Send



33/STASU

This is a background process which stops ASNs being passed to the EDI function.