

-
-
-
-
-

Chapter 1

Maintenance



Company Profile



3/STCO

This procedure specifies the environment in which the Purchase Management application will operate.



Note: Extreme care must be taken when amending existing profiles due to the effect that the amendment may have on data already in the application.



Warning: If there is a Copy Company option within Utilities, JBA strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.

Maintain Profile Records Screen 1



Select Purchase Management Company Profile.



Note: The process screens are those referred to in the Company Profile section in Inventory Management.

Use this screen to select an existing company profile to maintain. A list of valid Company Codes and descriptions is displayed.

```
PM003                Purchasing Company Profile      User GBJBARW2  11/12/96
                                                           14:05:38

Maintain Profile Records
Sel  Company
-    AA  ROB TAILOR LTD
-    AH  ANDY HINTON TEST COMPANY
-    AU  Automator Testing Co
-    GW
-    JW          JW - Jeffs Company
-    MR  JBA System Test Company
-    RK  Style Production Company
-    SC  Steve Chesworth's Test Company
-    SH  Style Demonstration Co.
-    SI  SINGLE CURRENCY
-    SS  Steve Hughes Test Company
-    ST  JBA System Test Company
-    SW  Sherees Test Company
-    YT  MNM's Test Company for Catchwe          +

Enter New Company .....  _

1=Select
F3=Exit

05-03  SF  MW  KS  IM  II  KENB20A  PET178S2
```

Fields:

Sel

Select. Enter 1 against the existing company profile you want to maintain.

Enter New Company

Enter a code for new company to be added.



Warning: If there is a Copy Company option within Utilities, JBA strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.



Press **Enter** to display the second Maintain Profile Records screen.

Maintain Profile Records Screen 2



To display this screen press **Enter** on the first Maintain Profile Records screen.

Use this screen to maintain the company defaults for addresses, delivery instructions and print output queues.

All details for an existing company are displayed.

PM003	Purchasing Company Profile	User	GBJBARW2	11/12/96
Maintain Profile Records				14:06:32
Company Code: AA Name: ROB TAILOR LTD				
Address 1..				
Address 2..				
Address 3..				
Address 4..				
Address 5..				
Post code..				
Telephone..				
Fax Number..				
Address Defaults:				
Supplier Sales Office address sequence number... 000				
Receiving Address supplier XXX				
Receiving Address default sequence number 000				
Purchasing Defaults:				
Delivery Instructions - Item Prefix..... PREFIX				
Booking in point 3 1=G,2=I,3=S				
Output Queues:				
Reports..... QPRINT				
Orders..... QPRINT				
GRNs/Labels. QPRINT				
Debit Notes. QPRINT				
Hold 0=No,1=Yes 0				
Library.... QGPL				
F3=Exit (no update) F8=Update complete F12=Previous screen				
04-22 SF MW KS IM II KENB20A PET178S2				

Fields:

Name

This is your Company Name. This name is set up within Application Manager, or via the Copy Company option if it is available.

Address Lines 1 to 5 and Post Code

Enter your company address and post code. This would typically be your Head Office address.

Telephone and Fax Number

Enter your main company telephone number and fax number. These would typically be your Head Office contact numbers.

Supplier Sales Office Address Sequence Number

Enter the code which identifies the location code to which you would normally send purchase orders for each of your suppliers. For example, if you normally send purchase orders to your supplier's head office, then enter 000.



Note: You set the Head Office address, which will always have a sequence number of 000 within Names And Addresses in Accounts Payable Maintenance. For any other addresses

for the same supplier, which will have sequence numbers of 001 and over, you need to set them up within Despatch Addresses in Accounts Payable Maintenance.

Receiving Address Supplier

Enter a code using three numeric characters to identify your receiving address. Your company receiving addresses are held as addresses for a dummy supplier.

Receiving Address Default Sequence Number

You may have a number of company addresses, each identified by a three numerical character code. Enter the three character code to define your default receiving address. This is the location where you normally receive stock from your Suppliers.

Delivery Instructions Item Prefix

Delivery instructions are held as text against dummy item's. Enter a dummy item number to define your default delivery instructions.

Booking In Point

Enter the location into which receipts are normally booked in. This may be changed for each receipt at the point of receipt. Enter one of the following:

- 1 - Goods inwards.
- 2 - Inspection.
- 3 - Stores.



Note: If goods are received into locations 1 or 2 they are not available to Style Inventory Management.

Output Queues

Enter the normal printer output queue for each of these documents.



Note: The details you enter here will override any queues already set up within Application Manager.

- Reports.
- Orders.
- GRNs/Labels.
- Debit Notes.

Hold

Enter one of the following to indicate when output from reports should be printed.

- 0 - To print immediately.
- 1 - To hold the print job in the queue.

Library

Enter the library which contains the output queue.



Press **Enter** to display the third Maintain Profile

Records Screen.

Maintain Profile Records Screen 3



To display this screen press **Enter** on the second Maintain Profile Records Screen.

Use this screen to define the environment in which this company is to be processed. All details for an existing company are displayed.

PM003 Purchasing Company Profile		User	GBJBARW2	11/12/96
				14:07:20
Maintain Profile Records				
Company Code:	AA	Name:	ROB TAILOR LTD	
System Tailoring:				
Which Purchase Ledger is to be used?.....	1	(1 or 2)		
Do you wish to access the Purchase Ledger log?.....	1	(0=N,1=V)		
Which Requisition System is to be used?.....	1	(1 or 2)		
Which Scheduling System is to be used?.....	2	(1 or 2)		
Which Inventory System is to be used?.....	1	(1 or 2)		
		(1=OSL, 2=Other)		
Goods Received Notes to print?.....	1	(0=N,1=V)		
Goods Received Labels to print?.....	1	(0=N,1=V)		
Invoice Match Inhibit if goods NOT in Stores location?..	1	(0=N,1=V)		
Update Current Price at:- Order Entry?	1	(0=N,1=V)		
		Invoice Match?.....		
	1	(0=N,1=V)		
Blank Supplier after Order Entry?	1	(0=N,1=V)		
Print Invoice Matching detail?	1	(0=N,1=V)		
Item Receipts - Enter the number of days forward of due				
date that delivery will be accepted.....	014			
General Ledger Company Code	21			
F3=Exit (no update) F8=Update complete F12=Previous screen				
06-61	SP	MW	KS	IM II KENB20A PET178S2

Fields:

Which Purchase Ledger Is To Be Used?

Enter one of the following:

- 1 - To use JBA Accounts Payable.
- 2 - To not use JBA Accounts Payable, or to use another Accounts Payable package with Style Purchase Management.

Do You Wish To Access The Purchase Ledger Log?

If the JBA Accounts Payable is in use enter one of the following:

- 0 - To not match purchase receipts against invoices on the Accounts Payable Log.
- 1 - To match purchase receipts against invoices on the Accounts Payable Log.



Note: If you want to match invoices select 1.

Which Requisition System Is To Be Used?

Enter one of the following:

- 1 - If JBA Purchase Requisitioning is to be used.
- 2 - If JBA Purchase Requisitioning is not to be used.

Which Scheduling System Is To Be Used?

Enter 2 in all circumstances as no Purchasing Scheduling System is available.

Which Inventory System Is To Be Used?

Enter one of the following:

- 1 - If the JBA Style Inventory Management is to be used.
- 2 - If any other is to be used.

Goods Received Notes To Print?

Enter one of the following:

- 0 - To not print GRNs.
- 1 - To print GRNs.

Goods Received Labels To Print?

Enter one of the following:

- 0 - To not print goods received labels.
- 1 - To print goods received labels.

Invoice Match Inhibit If Goods Not In Stores Location?

Enter one of the following:

- 0 - To enable matching of receipts to invoices in any location, that is, Goods Inwards, Inspection or Stores.
- 1 - To inhibit the matching of receipts to invoices until the goods have been processed through Inspection.



Note: If you have chosen Stores as your booking in point, then you would probably would not want invoice matching to take place.

Update Current Price At Order Entry?

Enter one of the following:

- 0 - If update is not required.
- 1 - To update the current price on the item/supplier profile at order entry time, if the price entered is not equal to the current price.

Update Current Price At Invoice Match?

Enter one of the following:

- 0 - If this update is not required.
- 1 - To update the current price on the item/supplier at invoice matching time, if the invoice price entered is not the same as the current price.

Blank Supplier After Order Entry?

Enter one of the following:

- 0 - To retain supplier details after purchase order entry. Use this if you enter multiple orders for the same supplier.
- 1 - To blank supplier and address details between entry of orders.

Print Invoice Matching Detail?

Enter one of the following:

0 - To inhibit print invoice matching detail.

1 - To produce the Invoice Matching report automatically.



Note: You can also print invoice matching details via Accounts Payable.

Item Receipts

Enter the number of days before an order line due date that you will accept delivery of goods from your supplier. This acts as a time fence so that when you receive goods, orders with a due date beyond this value will not be displayed.

General Ledger Company Code

Enter the General Ledger Company Code to which this Purchase Management company is to be linked.



Note: If you enter the General Ledger company it must be a valid General Ledger company. It will use the default base currency code of this General Ledger company and will determine if it is multi-currency or not.



Note: The Accounts Payable used by this Purchase Management company is determined by the selection of this General Ledger Company Code. A Purchase Management company will use any Accounts Payable company which interfaces to the General Ledger company specified here.



When you select **F8=Update**, the current values on the Maintain Profile Records Screens are written back to the Company Profile records. You can select **F8=Update** on this screen, or on subsequent screens.



Press **Enter** to display the fourth Maintain Profile Records Screen.

Maintain Profile Records Screen 4



To display this screen press **Enter** on the third Maintain Profile Records Screen.

Use this screen to specify the automatic numbering, if required, for purchase orders, Goods Received Notes, and Debit Notes.

All details for an existing company are displayed.

PM003	Purchasing Company Profile	User GBJBARW2	11/12/96
			14:08:33
Maintain Profile Records			
Company Code: AA Name: ROB TAILOR LTD			
Order Numbering:			
Automatic Order Numbering?..... 1 (0=N,1=Y)			
Start Number... 000001		Ending 999999	
Last Order number used..... 000604			
Order Number Prefix..... P			
Goods Received Note Numbering:			
Automatic Goods Received Notes numbering?..... 1 (0=N,1=Y)			
Start Number... 0000001		Ending 9999999	
Last GRN number used..... 0000337			
Debit Note Numbering:			
Debit Notes to print?..... 1 (0=N,1=Y)			
Start Number... 00001		Ending 99999	
Last Debit Note number used..... 2			
Currency Defaults:			
Which Conversion Rate		Orders?.. PERD Receipts ?.. PERD	
Code defaults are used?		Invoices ...?.. PERD	
F3=Exit (no update) F4=Prompt F8=Update complete F12=Previous screen			
07-64 SF MW KS IM II KENB20A PET178S2			

Fields:

Order Numbering

Automatic Order Numbering?

Enter one of the following:

0 - To enter order numbers manually.

1 - To generate order numbers in sequence.



If you select automatic order numbering, then the following four entries are required.

Start Number

Enter the first Purchase Order number you want to use.

Ending

Enter the last permissible order number in your range of Purchase Orders.

Last Order Number Used

This is the last order number generated; this is maintained by Purchase Management.

Order Number Prefix

Enter the character you want to use as a prefix for generated order numbers.

This is useful within a multi company environment, so that orders from different companies can be distinguished easily. You can also use this prefix to differentiate between purchase orders and requisitions.

Goods Received Note Numbering

Automatic Goods Received Note Numbering?

Enter one of the following:

0 - To enter GRN numbers manually.

1 - To generate GRN numbers automatically.



If you select automatic goods received note numbering, then the following entries are required.

Start Number

Enter the first GRN number you want to use.

Ending

Enter the last permissible GRN number for the range you want to use.

Last GRN Number Used

This is the last GRN number generated. This is maintained by Purchase Management.

Debit Note Numbering

Debit Notes To Print?

Enter one of the following:

0 - To inhibit Debit Notes.

1 - To produce a document detailing returned goods.



If you select automatic debit note numbering, then the following entries are required.

Start Number

Enter the first Debit Note number you want to use.

Ending

Enter the last permissible Debit Note number for the range you want to use.

Last Debit Note Number Used

This is the last Debit Note generated. This is maintained by Purchase Management.

Currency Defaults

Which Conversion Rate Code Defaults Are Used?

Enter the default rate code to be used for the conversion from prime currency to base currency on Orders and Receipts for each function. This rate code is set up in the General Ledger.

If a Rate Code is blank, then Purchase Management will look for a Rate Code of YYMM, where YY is the year and MM the month; for example, 9709 for September 1997.



On selecting **F8=Update**, the current values on the screen, and previous screens, are written back to the Company Profile record. **F8=Update** can be selected on this screen or subsequent screens.



Press **Enter** to display the fifth Maintain Profile Records Screen.

Maintain Profile Records Screen 5



To display this screen press **Enter** on the fourth Maintain Profile Records Screen.

Use this screen to maintain the permissible ranges of planners/purchasing officer numbers and item classes. Details for an existing company are displayed.

```

PM003              Purchasing Company Profile      User QASTYLE      5/06/97
                                                    12:00:23

Maintain Profile Records
Company Code: ST   Name:   Style Test & QA Company

Purchasing Officer Range:
Purchase Officer to be mandatory? (0=N,1=Y).... 0
Indicate the Purchasing Officer range associated with this company:-
                Starting Purchasing Officer.. 1 Ending.. 99999

Item Class Range:
Indicate the Item Class range associated with this company:-
                Starting Item Class.. AA Ending.. ZZ

Validate GL codes on non-stock orders? (0=No, 1=Warning, 2=Error message).. 1
Delete P.O Audits? (0=No, 1=Yes)..... 0

-----
F3=Exit (no update)  F8=Update complete  F12=Previous screen

07-52   SF      MW      KS      IM      II  EDN400A  PET149S2
  
```

Fields:

Purchase Officer To Be Mandatory?

Enter one of the following:

0 - Purchase Officer codes need not be entered on Purchase transactions and allocated to all defined styles.

1 - A Purchase Officer must be entered.



Note: You define Purchase Officers (or Planners) within the Planners Names option in Style Purchase Management Maintenance.

Starting Purchasing Officer

Enter the first Planner/Purchasing Officer Number to be used.

Ending Purchasing Officer

Enter the last number of the range of Planner/Purchasing Officer Numbers to be used.

Starting Item Class Range

Enter the first item class code to be used.

Ending Item Class Range

Enter the last item class code for the range.

Validate GL Codes On Non-Stock Orders?

Non-stock purchase orders can be controlled through the use of GL account code validation. Company profile flags control validation against the chart of accounts only, not against accounts with buyer.

Enter one of the following:

0 - To process non-stock orders without GL code validation.

1 -To display a warning message: Account Invalid, which can be overridden by pressing **Enter**.

2 - To display an error message: Account Invalid, and cannot be overridden.

Delete P.O. Audits?

Delete Purchase Order Audits. Enter one of the following:

0 - To retain purchase order amendments following audit report print, and have access through PO enquiry.

1 - To delete purchase order amendments following audit report print.



On selecting **F8=Update**, the current values on the screen, and previous screens, are written back to the Company Profile record. **F8=Update** can be selected on this screen or subsequent screens.



Press **Enter** to display the Requisitions screen if Purchase Requisitioning is being used. If Purchase Requisitioning is not being used, the procedure is complete.

Maintain Profile Records Screen 6



To display this screen press **Enter** on the fifth Maintain Profile Records Screen.

Use this screen to specify the options for the Purchase Requisitioning application.

```

PM003          Purchasing Company Profile      User GBJBARW2   11/12/96
                                                14:09:33

Maintain Profile Records
Company Code: AA   Name:   ROB TAILOR LTD

Requisitions System Options:

Order class for sourced requisitions..... 1  1 - 4
Release flag value on creation of requisition... 1

New order flag default value..... 1  (0=No,1=Yes)
New order created on change of Purchase Officer. 0  (0=No,1=Yes)

Requisition Numbering
      Start number..... 0000000 Ending number... 9999999
      Last number used... 1571

Authorisation required for modified
sourced requisitions..... 0  (0=No, 1=Yes)

-----
F3=Exit (no update)  F8=Update complete  F12=Previous screen

00-52  SF  MW  KS  IM  II  KENB20A  PET178S2
  
```

Fields:

Order Class For Sourced Requisitions

Enter the Order Class to be assigned to requisitions generated by the Inventory Management and Material Requirements Planning applications. This must be in the range 1-4 as these classes indicate stock orders.

Release Flag Value On Creation

Enter the Default Release Flag value when creating requisitions automatically. When requisitions are entered manually, the release flag is specified at the time of entry. This will help differentiate between system generated requisitions and manually created requisitions.



Tip: The next two fields determine how policies are generated when you create purchase orders from requisitions.

New Order Flag Default Value

Enter one of the following:

0 - To add the requisition to an existing order where supplier despatch address, currency, order class and stockroom match.

1 - To always create a new order when converting requisitions to purchase orders.

New Order Created On Change Of Purchase Officer

This field is linked to the New Order Flag Default Value. Enter one of the following:

0 - To add the requisition to an existing order where supplier despatch address, currency, order class, stockroom and purchase officer match.

1 - To create new orders on change of Purchase Officer number.

Start Number

Enter the first requisition number to be generated.

Ending Number

Enter the last requisition number permitted for automatic generation.

Last Number Used

This is the last requisition number generated by Purchase Management.

Authorisation Required For Modified Sourced Requisitions

Enter one of the following:

0 - To exclude modified sourced requisitions (generated by Inventory Management, Master Production Scheduling, Material Requirements Planning and Distribution Requirements Planning) from the requisition authorisation routines.

1 - To include modified sourced requisitions in the requisition authorisation routines.



Select **F8=Update** to write the current values on the Maintain Profile Records Screens to the Company Profile record.

Parameters And Sundry Codes

1/STPMM

Parameters and Sundry Codes are used to describe and validate the various codes used within Purchase Management. They are designed so that, as far as possible, they are set up and defined by the user.

They comprise of a parameter type (table header), and parameter details (table entries).

These codes serve two purposes:

- Tailor system requirements.
- Reduce the amount of data entry, thus improving the accuracy of your entries.

Style Purchase Management primarily uses these codes in:

- Order Entry.
- Returns and Adjustments.

Parameters are grouped together in family units. For example Units of Measure are grouped together, as are Scrap Reason Codes.

Each family is identified by a parameter type code, and each family member by a parameter detail code.

All parameters, whether type or detail, are identified by a parameter ID code. You must enter these details for tables with this selected Parameter Type option. It applies only to the UOM table from the standard parameters (this represents the conversion factor into the group UOM).



Note: The UOM Group Code must be entered for a UOMC parameter, and must exist as a GUMC parameter.

You must set up at least one GUMC parameter to define a group of units of measure for which conversion factors may be maintained.

For instance you may define an EACH group of units. The following units of measure (UOMC types) could be set up in each group, with the following conversion factors:

UOMC GUMC Conversion

EA (Each) EA 1

TN (Ten) EA 10

HN (Hundred) EA 100

The conversion factors define the conversion of each UOMC type into the group unit. The conversion factors are used for non-stock orders. Stock units and conversions are defined on the Item Master file.

When UOMC descriptions are displayed on screens or reports, only the first eight characters are shown.

Item class descriptions hold a description for each Class Code.



Tip: Item class is only defined at item level, if Style Inventory Management is not is use.

Order classification defines the type of items ordered on a purchase order. It is specified at Order Header level. Order classes are:

1- 4 Stock Orders.

5, 7, 8 Non stock orders.

6 Service Order.

Scrap Reason Codes define a reason for returning goods to a supplier, or scrapping goods against an order.

Schedule Types define a purchase order as being scheduled; for example, the goods ordered on a single order line are to be delivered in more than one drop, on more than one date, according to the schedule defined on the order.



Tip: A Parameter File Maintenance Report is automatically printed, giving the Before and After images for all parameters maintained in this option. This is performed on return to the menu.

Parameter File Maintenance Screen 1



Select Parameter File.

Use this screen to select the parameter type (table header), or parameter detail (table detail), you want to maintain. A list of valid parameter types and their descriptions are displayed for the company. You can also create new parameter codes using this option.

```
PM008                      ST - JBA System Test Company      User GBJBARW2    27/10/95
                                                                9:15:15

Parameter File Maintenance

      Parameter Type...    PTDS Enter PTDS to define new type
      Parameter I.D...?.   GUMC

Type  Description
FABF  Fabric faults
GLND  MPV description
GUMC  Group Unit of Measure Code
ITCL  Item Class Description
ORDC  Order Classifications
SCRC  Scrap Reason Codes
STVP  Schedule Order Type
UOMC  Unit of Measure Code
WHSE  Warehouse Descriptions
XDEF  User Defined Field Description

F3=Exit  F4=Prompt

06-36  SF  MW  KS  IM  II  KENB20A  PET178S2
```

Fields:

Parameter Type

Enter PTDS to maintain a parameter type.

Enter a valid parameter type from the list.

Parameter ID

Enter the parameter type to be maintained.



Tip: You can enter PTDS to maintain a parameter type, or create a new one. In this case you then enter a parameter type (for example, GUMC) in the parameter ID field.

Tip: To maintain an existing parameter type such as UOMC, you must then enter an existing parameter ID (for example, EA) in the ID field.

For example, enter:

- Parameter Type = PTDS
- Parameter ID = GUMC

To display the Parameter Type screen for unit of measure codes. For more information see the second Parameter File Maintenance screen.

If you enter:

- Parameter Type = GUMC
- Parameter ID = EA

The Parameter Detail screen will display the unit of measure EA. For more information see the third Parameter File Maintenance screen.



To display the second Parameter File Maintenance screen press **Enter**.

Parameter File Maintenance Screen 2



To display this screen enter valid parameter types and parameter IDs on the first Parameter File Maintenance screen and press **Enter**.

Use this screen to add or update parameter types (table headers).

All details for an existing parameter type are displayed with the literal AMENDMENT.

If the parameter type is a new one, a blank screen is displayed with the literal INSERTION.

PM008	ST - JBA System Test Company	User GBJBARW2	27/10/95 9:26:59
Parameter File Maintenance			
Parm Type	PTDS		
Parm I.D	FABF	AMENDMENT	
Description (Maximum) Size....:	20		
I.D. Size....:	2	& Format....:	N (C=Character,N=Numeric)
Description.:	Fabric faults		Max size 30
Value required....:	- (1=Yes/Blank) (V=Value,P=Percentage)		
F3=Exit F11=Delete F12=Previous			
09-36	SA	MW	KS IM II KENB20A PET178S2

Fields:

Parm Type

This is your selected Parameter type.

Parm ID

This is your selected Parameter identification.

Description (Maximum) Size

Enter the maximum number of characters allowed for the description of this parameter type. It must be in the range 1-30 inclusive.

ID Size

Enter the number of characters allowed for the identifier for this parameter type; for example, ORDC is a one character code, UOMC is a two character code and so on. It must be in the range 1-4 inclusive.

Format

Enter one of the following:

C - For the parameter ID to be alphanumerical character based.

N - For the parameter ID to be numerical character based.

Description

Enter the description for the parameter type. The description appears on the list of types on the initial select screen.

Value Required

Enter one of the following:

1 - To choose to define a value or percentage to the parameter.

Blank - To not choose to define a value or percentage to the parameter.

If you select to define a value or percentage to the parameter enter one of the following:

V - To assign a value to the parameter.

P - To assign a percentage to the parameter.

Functions:

F11

Delete. Use this to delete the parameter type.



Tip: A Parameter File Maintenance Report is automatically output, giving the Before and After images for all parameter types that have been maintained in this option. This is performed on return to the menu.



Press **Enter** to validate, and write the details to the Parameters file.

Parameter File Maintenance Screen 3



To display this screen enter a parameter type and parameter ID on the first Parameter File Maintenance screen and press **Enter**.

Use this screen to maintain the parameter details within the parameter type selected. Relevant details for an existing parameter are displayed with the literal AMENDMENT. If the parameter is a new one, a blank screen is displayed with the literal INSERTION.

PM008	ST - JBA System Test Company	User GBJBARW2	27/10/95 9:36:58
Parameter File Maintenance			
Parm Type	GUMC	Group Unit of Measure Code	
Parm I.D	BX	INSERTION	
Description.: _____ Max size 30			
(V=Value,P=Percentage)			
F3=Exit F12=Previous			
12-18	SA	MW	KS IM II KENB20A PET178S2

Fields:

Parm Type

From previous screen.

Parm ID

The parameter code to be updated, from the previous screen.

Description

Enter the description for this parameter, its maximum size is set on the first Parameter File Maintenance screen.

Value/Percentage

Enter one of the following:

V - To assign a value to the parameter.

P - To assign a percentage to the parameter.

Leave blank if you do not want to assign a value or percentage to the parameter.



Press **Enter** to validate and write the details to the Parameters file.

Item Specifications





2/STPMM

If any inventory application is installed other than Style Inventory Management, then for every stock item delivered, a record must exist in the item specification file. These records are maintained via this option.

You will need to set up details of descriptions, class, nominal code, unit of measure, alternatives and supersession data for each item.



Warning: where the Style Inventory Management application is installed, Purchase Management references the Items file directly for stock items, and the Item Specification data is not required. You would always set up style details within Style Inventory Management.



Product Specification Maintenance Screen 2



To display this screen select an item/product on the first Product Specification Maintenance screen and press **Enter**.

Use this screen to maintain the specification details for the selected item. If a specification is found for the item, its details are displayed with the literal AMENDMENT. Otherwise, a blank screen is displayed with the literal INSERTION.

PM006	ST - JBA System Test Company	User GBJBARW2	27/10/95 9:41:36
Product Specification Maintenance		INSERTION	
Product...	ANORAKPG	Product class.?.	__
Specification line 1	_____		
line 2	_____		
line 3	_____		
Nominal Codes			
Material	_____		
Price variance	_____		
Currency variance	_____	Purchasing Officer.?.	_____
Stocking u.o.m. .?...	_____	Standard Cost	_____ .00000
Purchase u.o.m. .?...	_____	Stocked Product	_____ 1=Yes, 0=No or Blank
Conversion factor	_____ .00000		
VAT code	_____		
Alternative product	_____		
Supersession date	_____		
Supersession product	_____		
Sub assembly part no.	_____		
F4=Prompt F18=Text Review			
F12=Previous	05-46	SF	MW KS IM II KENB20A PET178S2

Fields:

Product Class

This entry is optional. If entered, it must exist as a parameter code. This is available as a report selection criterion for Sales Analysis, for example, Fashion, Hosiery and so on.

Specification Lines 1 to 3

Enter upto three lines of text which will be printed with any purchase order line for this item (unless order line text is entered for the item).

Material

Enter a nominal code, this is used to detail the supplier invoice on stock items. These codes are also used in report, for example, accruals, price variance.

Price Variance

Enter a nominal code, this is used to detail the price variance on stock items. These codes are also used in report, for example, accruals, price variance.

Currency Variance

Currency variance is not currently used by Style.

Stocking UOM

Enter the issue unit of measure. This is set up within Inventory Management against Major Type UOMC.

Purchase UOM

Enter the unit of measure in which the item is bought. This is set up within Inventory Management against Major Type UOMC.

Conversion Factor

You must enter the value which would convert the Purchase UOM to the Stocking UOM. It cannot be zero.

For example, Issue UOM = BX (Box)

Purchase UOM = CA (Case - with 10 boxes per single case)

Conversion Factor = 0.1

VAT Code

Enter a valid code from the VAT rate table (General Ledger). This is an optional entry.

Alternative Product

Enter the code of an item to be used as an alternative. This must be an existing item.

Supersession Date

Enter the date details for the item which has superseded this item.

Supersession Product

Enter the item code which has superseded this item. The supersession item be an existing item.

Sub-Assembly Part No

Enter the dummy item code for sub-contract work.

When items are sent out for sub-contract work, the order will be raised for the value added by the sub-contractor.

So it is necessary to set up a dummy item for the outwork.

When you receive the outworked item into stores, Style Purchase Management replaces the dummy item number (as entered in this field) with the full value item number (the actual item code) so that the inventory can be updated correctly.

Once the validation is complete, the details on the screen are written to the Item Specification file.

Purchasing Officer

Enter the code of the Purchasing Officer responsible for this item. Purchase Officer (or Planner) Names are set up within the Planner Names option in Style Purchase Management Maintenance, and can be set as a mandatory entry on the Purchase Management Company Profile. For more details see the fifth Maintain Company Records screen.

Standard Cost

Enter the standard cost per stocking unit of measure. This is used to provide a cost valuation of orders and receipts for reporting.

Stocked Product

Enter one of the following:

0 - To specify this item as a non-stocked item. This item is then not received into Stores.

1 - To specify this item as a stocked item. This item is then controlled by Inventory Management and must be received into Stores.

Functions:

F11

Delete. Use this to delete the item specification.

F18

Text Review. Use this to display the Purchase Text window.

Purchase Text Window (F18)



To display this window select **F18=Text Review** on the second Product Specification Maintenance screen.

Use this window to maintain text for the selected item. If text is found for the item, then it is displayed.

PM006

ST - Style Distribution Company

User STYLEEDU

8/09/97
13:14:47

Product Specification Maintenance

Product... BAG3-1D

Product class.?. __

INSERTION

Specification line 1
line 2
line 3

N

Material
Price variance
Currency variance
Stocking u.o.m. .?...
Purchase u.o.m. .?...
Conversion factor
VAT code
Alternative product
Supersession date
Supersession product
Sub assembly part no.

F4=Prompt
F12=Previous

14-33

SA

MW

KS

CL

IM

DM

II

KENB20A

KB

PET310S1

PURCHASE TEXT FOR

BAG3-1D

1

2

3

4

5

6

Position to __ Insert __ after __
Delete __ from __

Fields:

Purchase Text For

Enter up to 99 lines of item text. This text is printed on the purchase order in place of the item specification lines if requested.

Position To

Enter the line number where display is to start.

Insert/After

Enter the number of lines you want to insert, and the line number after which you want this to be inserted.

Delete/From

Enter the number of lines you want to delete, and the line number after which you want this to be deleted.



Select **F8=Update** to write the screen details to the Item Text file.

Purchase Planner Names




3/STPMM

This option is used to maintain the codes and names for Purchasing Officers or Planners in the company. Planners can be used on the product specification option to allocate responsibility for products. They are also viewed on the Purchase Order Header screen when you create a purchase order.

Planner Name Maintenance Selection Screen

 Select Planner Names.

Use this screen to select the correct Purchasing Officer or Planner number to be maintained. You can also use this option to create new Planner details.



S No.	Planner	More:
4	ROLENT BUYER	

Fields:

Planner Number

Select a Planner code (Purchase Officer) to maintain existing details.

Or, enter a new code to create details for a new Planner.

 *Note: The number of Planners you can create, and the format of the codes is governed by the range of planning officers you have already specified on the fifth Maintain Profile Records screen within Style Purchase Management Company Profile.*

 Press **Enter** to display the Planner Name Maintenance Detail screen.

Planner Name Maintenance Detail Screen



To display this screen press **Enter** on the
Planner Name Maintenance Selection screen.

Use this screen to update details for the an existing Planner (or Purchasing Officer),
or create details for a new Planner or Purchase Officer.

If the selected Purchasing Officer is found, their details are displayed together with
the literal AMENDMENT. Otherwise, a blank screen is displayed with the literal
ADDITION. The Planner number from the selection screen is displayed.

PM167	ST - JBA System Test Company	User GBJBARW2	27/10/95
			9:53:13
Planner Name Maintenance		AMENDMENT	
Planner Number...	1		
Planner Name...	NAME		
Extension Number...	3245		
F3=Exit F11=Delete F12=Previous (To Select)			
00-35	SF	MM	KS IM II KENB20A PET178S2

Fields:

Planner Name

You must enter the name of the Purchasing Officer or Planner.

Extension Number

Enter the telephone extension number for the above person.



Press **Enter** to validate the information and write
the details to the Purchasing Officer file.

Item Supplier Profile



4/STPMM

The Item Supplier Profile is used by Purchase Management to provide details of supply of an item from a specific supplier. Cumulatives of Orders and Receipts together with the current price and any price structure details which exist for the supplier, along with the Suppliers Item Reference, are maintained. Ordering rules, for scheduling, are also recorded but for memo purposes only.

If no item supplier profile exists when the item is bought, Style Purchase Management will create one in order entry or invoice matching using the price input for that order.



Note: If you have activated Purchase Requisitioning, then a you must create an item supplier profile for the default supplier.

Product Supplier Profile Maintenance Screen 1



Select Product Supplier Profile option.

Use this screen to select the item and supplier combination you want to maintain. You can use this option to create a new item and supplier combination.

```
PM165          ST - Style Distribution Company  USER STYLEEDU  8/09/97
                                                    14:01:56

Product Supplier Profile Maintenance

Product Style.?.  █
Supplier.....?.  █

Maintenance level... █

                        1=Style
                        2=Style/colour
                        3=Style/size
                        4=Style/colour/size
                        5=Style/colour/size price matrix

F3=Exit  F4=Prompt

6-19  SA  MW  KS  CL  IM  DM  II  KENB20A  KB  PET310S1
```

Fields:

Product Style

Enter the item to be created or updated.

Supplier

Enter the Supplier Code. This must be an existing code.

Maintenance Level

Enter the appropriate number for the level at which you wish to maintain the product:

1 - Style. This is for the entire style, for example, all T Shirts.

2 - Style/Colour. This is for each colour variant of a style, for example, Red T Shirt.

3 - Style/Size. This is for each size variant of a style, for example, Small T Shirt.

4 - Style/Colour/Size. This is for each colour and size variant of a style, for example, Small Red T Shirt, Medium Black T Shirt.

5 - Style/Colour/Size Price Matrix. This is for each size, colour and price variant of a style.



Press Enter to display the second Product Supplier Profile Maintenance screen.

Product Supplier Profile Maintenance Screen

2



To display this screen press Enter on the first Product Supplier Profile Maintenance screen.

Use this screen to create or maintain details for the selected item/supplier combination. The screen displays the selected product and supplier combination. If the item/supplier combination is found, the literal AMENDMENT is also displayed.

Otherwise, the remaining fields are blank and INSERTION is displayed.

```

PM165                ST - JBA System Test Company    USER GBJBARW2    27/10/95
                                                           10:02:02
Product Supplier Profile Maintenance
Product... LADYSH/1      Ladies Shoe 1              AMENDMENT
Supplier.. FS05         Thierry SA
                        15 Rue de Louvre
                        75012 Paris
                        France

Current Price.  █          PR Last price change.. 27/10/95
Discount.  _____ % Lead time in days.. 000 Receipts to date...
Supplier Product.. _____ Orders to date.....
                                                           PR
-----Ordering Rules-----
% Basis..  _____.00  Minimum....  Maximum..  _____
                        Multiples..  _____

F3=Exit  F11=Delete  F12=Previous  F14=Landed Costs
F21=Text

14-17  SF  MW  KS  IM  II  KENB20A  PET178S2
  
```

Fields:

Current Price

Enter the current price of the item from this supplier, relating to the Purchase UOM displayed.



Note: The next three fields are only displayed if you are maintaining an existing product and supplier profile.

Last Price Change

This is the date that the current price was last amended. This can have been amended in either Order Entry, Invoice Matching, or via this screen.

Receipts To Date

This is the total quantity of this item received from this supplier, in purchase units of measure.

Orders To Date

This is the total quantity of this item ordered from this supplier, in purchase units of measure.

Discount %

Enter the standard percentage discount for this product and supplier combination. This discount provides the default for the first line discount on purchase orders.

Lead Time In Days

Enter the lead time, in days, for delivery of the item from this supplier. This lead time is used in the Supplier Performance report calculations.

Supplier Product

Enter the suppliers reference for the item. This is useful if the supplier has a different reference code for this style.

Ordering Rules

You can enter % Basis, Minimum, Maximum and Multiple re-order defaults for memo purposes only.

Functions:

F11

Delete. Use this to delete a product and supplier profile.

F14

Landed Costs. Use this to attach landed costs to a product and supplier profile.

F21

Text. Use this to display text screen for item/supplier.



Press **Enter** to validate the details on this screen and write them to the Product Supplier file.

Landed Costs Entry (F14)



To display this screen select **F14=Landed Costs** on the second Product Supplier Profile Maintenance screen.

Use this screen to attach additional cost elements, if known, against the item/supplier. Landed costs are purchasing costs incurred over and above the basic purchase price of goods or services. They are set up within the Landed Cost Code Maintenance option within Style Purchase Management. The selected style, stockroom and unit of measure are displayed for verification.

PM095ST - JBA System Test CompanyUSER GBJBARW227/10/9510:03:06

Landed Costs Entry

Item..... LADYSH/1Ladies Shoe 1

Supplier.. FS05????????????????????????????????

UoM..... PRPair

Currency.. FRFFranc

Cost Code Description (?)	Landed Cost	Perc/ Value (1/0)	Cmpd Ind (1/0)	Price Dependant (1/0)
ED	6.5000	0	■	-
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—
—	—	—	—	—

F3=Exit F4=Prompt F8=Update F12=Previous

12-66SFMMWKSIMIICKENB20APET178S2

Fields:

Cost Code

Select a valid cost code. These codes are set up via Landed Cost Code Maintenance. You can attach up to 10 landed costs to a product and supplier profile. The description is retrieved and displayed.

Landed Cost

Enter the cost for this additional cost element using up to five decimal places. These costs are considered standard priced costs.



Note: For more information regarding the next three fields, see Landed Cost Code Maintenance within Style Purchase Management Maintenance.

Perc/Value

Percentage/Value indicator. This indicator is returned from the landed cost file, but can be overridden. Enter the following:

0 - Cost is a value to be added to product cost.

1 - Cost is a percentage to be applied to the product cost.

Cmpd Ind

Compound Indicator. This is returned from the Landed Cost file, but can be overridden. Enter one of the following:

0 - To accumulate the cost when you apply the price.

1 - To compound the cost when you apply the price.

Price Dependant

This is returned from the Landed Cost file, but can be overridden. Enter one of the following:

0 - To not accumulate costs.

1 - To accumulate costs. These will be calculated and added to the item cost. These are attached here, or when the order is received into your normal receipt location.




Select **F8=Update** to update the landed cost details.

Supplier Window (F21)

 To display this window select **F21=Text** on the second Product Supplier Profile Maintenance screen.

Use this screen to create or maintain text information for the selected item/supplier combination. This text is used for memo purposes only. The window displays the selected product and supplier profile details. It also displays any existing text for this Product and Supplier combination. You can enter up to 99 lines of text for this Product and Supplier combination.



PM165 ST - JBA System Test Company USER GBJBARW2 27/10/95 10:06:10

Product Supplier Profile Maintenance AMENDMENT

Product... LADYSH/1 Ladies Shoe 1

Supplier.. FS05 Thierry SA
15 Rue de Louvre
75012 Paris
Fra

Current Price. _____
Discount. _____ % Lea
Supplier Product.. _____

% Basis.. .00 Minim
Multi

F3=Exit F11=Delete
F21=Text

14-56 SA MW KS IM II KENB20A PET178S2

Supplier FS05 Thierry SA LADYSH/1

1 The supplier despatches items in a pre-
2 packed state
3
4
5
6

Position to _____ Insert _____ after _____
Delete _____ from _____

F5=Refresh F8=Update F12=Previous

Fields:

Position To

Enter the line number where display is to start.

Insert/After

Enter the number of lines you want to insert, and the line number after which you want this to be inserted.

Delete/From

Enter the number of lines you want to delete, and the line number after which you want this to be deleted.

Functions:

F5

Refresh. Use this to refresh the screen to the position first displayed.

 Select **F8=Update** to write the text lines on the screen to the Product and Supplier Text file.

Delivery Instructions



5/STPMM

Use this option to maintain a set of delivery instructions for the company. These instructions are assigned to an order in Order Entry and Order Maintenance, and appear on purchase order prints.

Delivery instructions are set up on the Item Specification file using an item created from the 12-character prefix (identified on the Company Profile), and a three-character suffix entered through this maintenance option.

Enter an existing code to maintain and delete data. Enter a new code to add new Delivery Instructions.

Delivery Instructions Maintenance Screen 1

 Select Delivery Instructions.

Use this screen to select the code for the set of delivery instructions to be maintained. You can also use this option to create a new set of delivery instructions.

PM163ST - JBA System Test CompanyUser GBJBARW227/10/9510:10:23

Delivery Instructions Maintenance

Code ? ?

Select Delivery Instruction Code

Code	Description
ABB	LEAVE WITH DOORMAN
001	DELIVER ONLY ON WEDNESDAY

1=Select

F5=Refresh F12=Previous

F3=Exit F4=Prompt

14-38SA MW KS IM II KENB20A PET178S2

Fields:

Code

Select an existing delivery instruction code to maintain details. Enter a new code using up to three alphanumeric characters to create a new set of delivery instructions

 Press **Enter** to display the second Delivery Instructions Maintenance screen.

Delivery Instructions Maintenance Screen 2



To display this screen press **Enter** on the first Delivery Instructions Maintenance screen.

Use this screen to create or maintain the Delivery Instructions for the selected code. The Delivery Instructions Code from the previous screen is displayed. If the code is found, the existing instructions are displayed, together with the literal AMENDMENT. If the code is a new one, the instructions are blank, and the literal is INSERTION.

PM163	ST - JBA System Test Company	User GBJBARW2	27/10/95 10:10:23
Delivery Instructions Maintenance		AMENDMENT	
Code ABB			
Delivery Instructions	line 1	LEAVE WITH DOORMAN	
	line 2		
	line 3		
F11=Delete F12=Previous (Re-select)			
07-30	SF	MW	KS IM II KENB20A PET178S2

Fields:

Delivery Instructions Lines 1 to 3

Enter the instructions for the code. You can enter up to three lines of 50 characters. You can define as many delivery instructions as required. Delivery instructions are used on the purchase order header and are printed on the purchase order for your supplier's information.



Note: You can change the delivery instruction on the purchase order header to cater for any change in delivery requirements.



Press **Enter** to update the Item Specification file (a dummy record) with the code and text.

Receiving Addresses



6/STPMM

Use this option to create or maintain a set of receiving address location codes for the company.

Receiving addresses are set up on the Supplier Master file using a dummy supplier, identified on the Company Profile, and a three-character code entered through this maintenance option.

There is always a default receiving address location code, which is defined here and is specified on the company profile.


These location codes are used in conjunction with the receiving address to indicate what your receiving address is for a particular order.

Receiving address location codes are assigned to a purchase order in Order Entry and Order Maintenance, and appear on purchase order prints. The default always appears on your purchase orders but can be overridden to any that you create here.

Receiving Address Maintenance Screen 1

 Select Receiving Addresses.

Use this screen to create a new receiving address code or select the code for the receiving address to be maintained.



PM259 ST - JBA System Test Company User GBJBARW2 27/10/95 10:12:20

Receiving Address Maintenance

Code...?. ?

Select Receiving Address Code

Code	Description
000	DEFAULT ADDRESS
001	ADDRESS 1

1=Select
F5=Refresh F12=Previous

F3=Exit F4=Prompt

14-36 SF MW KS IM II KENB20A PET178S2



Fields:

Code

Select an existing receiving address code to maintain or delete details attached to it.

Or enter a new code to add a new receiving address.

 Press **Enter** to display the second Receiving Address Maintenance screen.



Supplier External Text



7/STPMM

Use this option to create or maintain external text for a supplier, which you can choose to print on the purchase order form.

Supplier External Text Maintenance Screen

 Select Supplier External Text.

Use this screen to select the supplier for whom you want to create or maintain external text.

PM250

ST - JBA System Test Company

User GBJBARW2

27/10/95
10:16:50

Supplier External Text Maintenance

Supplier..?.

F3=Exit

F4=Prompt

06-20



MW

KS

IM

II

KENB20A

PET178S2

Fields:

Supplier

Enter a valid Supplier Code as held on the Supplier Master File.

 Press **Enter** to display the Untitled Supplier window.

Untitled Supplier Window



To display this window press **Enter** on the Supplier External Text Maintenance screen.

Use this window to create or maintain the external text details for the selected supplier. The window displays the Supplier Code from the previous screen, together with the supplier's name from the Supplier Master File. Any existing external text found for the supplier will also be displayed.



Tip: You can maintain up to 99 lines of external text for the selected supplier.

PM260 ST - JBA System Test Company User GBJBARW2 27/10/95 10:16:50

Supplier External Text Maintenance

Supplier...?. ?

Supplier FS05 Thierry SA

1 All orders should be despatched within 6

2 weeks

3

4

5

6

Position to ___ Insert ___ after ___

Delete ___ from ___

F5=Refresh F8=Update F12=Previous

F3=Exit F4=Prompt

15-38 SA MW KS IM II KENB20A PET178S2

Fields:

Position To

Enter the line number where display is to start.

Insert/After

Enter the number of lines you want to insert, and the line number after which you want this to be inserted.

Delete/From

Enter the number of lines you want to delete, and the line number after which you want this to be deleted.

Functions:

F5

Refresh. Use this to refresh the screen to the position first displayed.



Select **F8=Update** to write the details to the Text file.

Container Details

1... **2...** 8/STPMM

Use this option to maintain container details, if known, against one or more purchase orders. This data would normally be entered when the supplier indicates goods are ready for despatch from the factory.

This provides an audit trail of each container your Supplier despatches to you, tracking details such as the flight or vessel numbers, through to bond details for Custom and Excise purposes.

Container Details Maintenance Screen 1



Select Container Details.

Use this screen to record the container number concerned.

AP720	ST - JBA System Test Company	User GBJBARW2	27/10/95
Container Details Maintenance			10:21:29
Container Number.? _____			
F3=Exit F4=Prompt			
05-21	SA	MW	KS IM II KENB20A PET178S2

Fields:

Container Number

Enter a container number using up to 20 alphanumeric characters for an addition, or select a valid number for amendment.



Press **Enter** to display the second Container Details Maintenance screen.

Container Details Maintenance Screen 2



To display this screen is displayed press **Enter** on the first Container Details Maintenance screen.

Use this screen to enter all data applicable to the shipment of this particular container. All the fields are optional entries and data is only entered when or if known.

AP720	ST - JBA System Test Company	User GBJBARW2	27/10/95 10:21:29
Container Details Maintenance			
Container Number.. MIKES TEST CONTAINER			
Import Reference..	IREF/10	Advice Note.....	AD0010
Transport Type....		Vessel/Aircraft..	TITANIC
Country/Origin..?	SL	Voyage/Flight....	
Supplier Name.....		Flag Nationality.	
Port of Loading...	BOSTON	Shipping Company.	
Container Size....		Shipping Agent...	
No. of Cartons....	12	Nett Weight.....	.00
Bill of Lading....		Seal Number.....	
Letter of Credit..	LC00000012	Period Entry No..	
Destination.....?	IR	Bond Number.....	
Port of Entry.....	DOVER		
F3=Exit F4=Prompt F12=Previous			
09-64 SF MW KS IM II KENB20A PET178S2			

Fields:

Import Reference

Enter the import reference code for this container, using up to 12 alphanumeric characters.

Transport Type

Enter the method of transportation for this container, using one alphanumeric character.

Country of Origin

Enter the country of origin; this must exist on the Descriptions file under Major Type ECTY.

Supplier Name

Enter the Supplier name, using up to 20 alphanumeric characters.

Port of Loading

Enter the port that this container will start its journey from, using up to 12 alphanumeric characters.

Container Size

Enter the size of the container, using two alphanumeric characters.

No. of Cartons

Enter the number of cartons held within the container. The value can be up to six digits with zero decimals.

Bill of Lading

Enter the Bill Of Lading reference, using up to 20 alphanumeric characters.

Letter of credit

Enter your letter of credit reference, using up to 12 alphanumeric characters.

Destination

Enter the country of destination; this code must exist on the descriptions file under Major Type ECTY.

Port of Entry

Enter the port at which the container will enter the country, using up to 12 alphanumeric characters.

Advice note

Enter the reference of any advice note that you have received from your supplier using up to 16 alphanumeric characters.

Vessel/Aircraft

Enter details regarding the vessel transporting your container, for example, the registration number of the aircraft, or the name of the vessel, using up to 16 alphanumeric characters.

Voyage/Flight

Enter the flight or voyage reference codes, using up to 16 alphanumeric characters .

Flag Nationality

Enter the original nationality of the supplier, using two alphanumeric characters .

Shipping Company

Enter the name of the shipping company responsible for transporting the container using up to eight alphanumeric character.

Shipping Agent

Enter the name of the shipping agent, or contact, using up to 12 alphanumeric characters.

Nett Weight

Enter the nett weight of the container, using up to nine digits with two decimals.

Seal Number

Enter the seal number on the container, using up to eight digits with zero decimals.

Period Entry No

Enter the period that this container is due to be received into the country, using up to four digits with zero decimals.

Bond Number

Enter the bond number for Custom and Excise purposes, using up to four digits with zero decimals.



Press **Enter**, to validate the details and display the third Container Details Maintenance screen.

Container Details Maintenance Screen 3



To display this screen press **Enter** on the second Container Details Maintenance screen.

Use this screen to record any payment details and dates for the container. All the fields are optional entries and data is only entered when or if known.

AP720	ST - JBA System Test Company	User GBJBARW2	27/10/95 10:21:29
Container Details Maintenance			
Freight.....	.00000	Demurrage.....	.00000
Insurance.....	.00000	Royalties.....	.00000
Commission....	.00000	Spare 1.....	.00000
Duty.....	.00000	Spare 2.....	.00000
VAT.....	.00000	Invoice Total..	.00000
		Estimate	Actual
Date of Departure.....	0/00/00	0/00/00	
Date of Arrival at Port.....	0/00/00	0/00/00	
Date of Arrival in Warehouse.....	0/00/00	0/00/00	
Additional Details.....			
F3=Exit F12=Previous F8=Update F9=Update and attach P/0s			
05-17 SF MW KS IM II KENB20A PET178S2			

Fields:

Freight

Enter any freight payments, using up to 15 digits with five decimals.

Demurrage

Enter any rate payable to the freight owner for failure to unload the container within the time allocated to do so, using up to 15 digits with five decimals.

Insurance

Enter any insurance charge for the container using up to 15 digits with five decimals.

Royalties

Enter any royalty payments that you need to make for the contents of the container, using up to 15 digits with five decimals.

Commission

Enter any commission payment that you need to make to an agent, using up to 15 digits with five decimals.

Spare 1 & 2

These are free format fields for any additional payments that you need to make, enter two values, using up to 15 digits with five decimals.

Duty

Enter any import duty payment to Customs and Excise, using up to 15 digits with five decimals.

VAT

Enter any VAT payment to be made on receipt of the container, using up to 15 digits with five decimals.

Invoice Total

Enter the total payment required, as detailed on the invoice sent by your supplier, using up to 15 digits with five decimals.



Note: You can enter both estimated and actual dates for the next three fields. This could be useful to record slippage in lead times for future reference.

Date Of Departure

Enter the date that the container left the supplier or the country of origin. You must enter valid dates.

Date Of Arrival At Port

Enter the date that the container arrived at the port in your country. You must enter valid dates.

Date Of Arrival In Warehouse

Enter the date that the container arrived at your warehouse, or the Custom and Excise warehouse.

If you enter a date then it will update all purchase order line delivery dates attached to the container. This amended date will therefore be used in Stock Availability Enquiry.



Note: The actual date will take preference over the estimated date.

Additional Details

Enter up to three lines of 30 alphanumeric characters of free format text.

Functions:

F9

Update and Attach P/Os. Use this to update the system and attach Purchase Orders to the container.



Select **F9=Update and Attach P/Os** to display the Container Detail Entry screen.

Container Detail Entry Screen (F9)



To display this screen is displayed select **F9=Update And Attach P/IOs** on the third Container Details Maintenance screen.

Use this to attach multiple purchase order numbers to the container. The screen displays the selected container number from the first Container Details Maintenance screen. Any purchase orders that have already been attached will be displayed.

```

AP602                ST - JBA System Test Company        USER GBJBARW2    27/10/95
                                                           10:29:46
Container Detail Entry

Container ..... MIKES TEST CONTAINER

P/O No.      P/O No.      P/O No.      P/O No.      P/O No.      P/O No.

_____ _ 1=Amend/2=All

F3=Exit  F12=Previous

21-02      Sf      MW      KS      IM      II  KENB20A  PET178S2

```


Container Details Entry Screen (Option 1)



To display this screen enter 1 in the Untitled selection field on the Container Details Enquiry screen and press **Enter**.



Note: This screen is also known as the Purchase Order Amendment screen.

Use this screen to amend purchase order details (that is, line numbers or quantities) before inclusion in the container.

See Style Purchase Management Processing - Order Amendment for further details.

User Authority Values



9/STPMM

Use this option to maintain user-specific authorisation values. These are used, in Goods Receiving and Invoice Matching, to check that the user has sufficient authority to confirm a difference in value (under or over), from the original order. If either the absolute value or percentage of order line value, maintained in this option, are exceeded then the user is prevented from confirming the acceptance.

User Authority Value And Percentage Maintenance Screen 1



Select User Authority Value And Percentage.

Use this screen to select the user profile to be maintained.



Tip: The user profile must have been previously defined to System Manager.

```
PM012                ST - JBA System Test Company    User GBJBARW2    27/10/95
                                                           10:38:29

User Authority Value And Percentage Maintenance

Enter User Profile:      & Press ENTER to continue.

F3=Exit

05-23    SF    MW    KS    IM    II    KENB20A    PET178S2
```

Fields:

User Profile

You must enter the user profile that you wish to maintain; the user profile must have been defined to System Manager.



Press **Enter** to display the second User Authority Value And Percentage Maintenance screen.

User Authority Value And Percentage Maintenance Screen 2



To display this screen press Enter on the first User Authority Value and Percentage Maintenance screen.

Use this screen to update the value and the percentage, or both, of order line value which the user can confirm as an acceptable difference (in Goods Receiving and Invoice Matching). If authority values are found for the selected user profile, then these are displayed.

PM012	ST - JBA System Test Company	User GBJBARW2	27/10/95 10:38:29
User Authority Value And Percentage Maintenance			
ADDITION			
Enter or Amend Authority Parameters for User Profile GBJBARW2			
Authority Value: <u>1000.00</u>			
Percentage: <u>50.00</u> %			
Allow amended match: <u>0</u> 0 = No, 1 = Yes			
Press Enter to Update File:			
F3=Exit (Re-select) F11=Delete			
13-45	SA	MM	KS IM II KENB20A PET178S2

Fields:

Authority Value

Enter the maximum difference in value that the user can accept. This is the value tolerance for this user.

Percentage

Enter the maximum percentage difference of line value that the user can accept.



Tip: You can enter either Authority Value, Percentage, or both. You cannot leave both fields blank.

Allow Amended Match

Enter one of the following:

0 - Do not allow this user to accept an amended match.

1 - Do allow this user to accept an amended match.



Press **Enter** to validate, the details and write

them to the Authorities file.

Landed Cost Codes




10/STPMM

Use this option to create and maintain landed cost codes and their associated attributes.



*Note: Landed cost codes are added to a product by selecting **F14=Landed Costs** on the second Product Supplier Profile Maintenance screen.*



Landed Cost Code Maintenance Screen 2



To display this screen press **Enter** on the first Landed Cost Code Maintenance screen.

Use this screen to amend or create details for the selected code.

PM098	ST - JBA System Test Company	User GBJBARW2	27/10/95
			10:42:27
Landed Cost Code Maintenance			
AMENDMENT			
Landed Cost Code.....	ED		
Description.....	Excise Duty		
Percent/Value (1/0).....	1		
Compound Indicator (1/0)...	0		
Price Dependency (1/0)....	0		
F3=Exit F11=Delete F12=Previous (To Select)			
08-42	SP	MW	KS IM II KENB20A PET178S2

Fields:

Description

Enter the landed cost description using up to 30 alphanumeric characters.

Percent/Value

Enter one of the following:

0 - To denote that a cost value per unit of measure for the order line will apply.

1 - To denote a percentage of the item cost will apply.

Compound Indicator

For Percentage Based Landed Costs

Enter one of the following:

0 - To accumulate them by adding them when applying them to the price.

1 - To compound the percentages by multiplying them when they are applied to the price.

For Value Based Landed Costs

Enter one of the following:

0 - To indicate that they will be applied after the percentages.

1 - To indicate that the value code will be accumulated with the price before applying the percentages.

Price Dependency

Enter one of the following:

0 - Denotes non-accumulative costs.

1 - Denotes accumulative costs. Accumulative costs will be calculated and added to the price which gives the value on which the non-accumulative will be calculated.



Press **Enter** to update the details and return to the first Landed Cost Code Maintenance screen.

Supplier Fax Numbers



11/STPMM

If you have the Cobwebb Fax module you can send your purchase orders by fax transmission rather than printing and posting them.

Use this option to create and maintain as many fax numbers as you wish against the delivery addresses of the supplier.

Supplier Fax Number Maintenance Screen 1



Select Supplier Fax.

Use this screen to select the supplier for whom you wish to maintain fax numbers.

Fields:

Supplier

Enter the supplier code for the supplier you wish to maintain fax numbers for.



Press **Enter** to display the second Supplier Fax
Number Maintenance screen.

Supplier Fax Number Maintenance Screen 2



To display this screen press **Enter** on the first Supplier Fax Number Maintenance screen.

Use this screen to add or update the selected supplier fax numbers. The screen displays the selected supplier, and any existing fax numbers over all address location codes. You can record fax numbers for the Head Office (normally location code 000) and any subsidiary offices as required.

PM261	Z1 - Demonstration Company	User SP1	31/08/94 11:04:02
Supplier Fax Number Maintenance			
Supplier... GS01		Premier Food and Drug Supplies	
Sel.	Add cde.	Fax Number	Description
-	000	09998768712	Accounts Department
-	000	09998768713	Purchasing Department
-	000	09998768765	Head Office
Add cde. ____ Fax. _____ Desc. _____			
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Name

The supplier's name is recalled from the Supplier Master file.

Sel.

Select.

Enter 1 to select an existing fax number for update or deletion.

The details are transferred to the entry fields at the bottom of the screen for amendment.

To delete fax number details, select the number with 1 and delete the details from the entry fields.



Tip: Use the entry fields at the bottom of the screen to add new fax numbers to the supplier.

Add Cde.

Enter the address location code for the supplier using a three digit code; for example, 000 for the head office.

Fax Number

Enter the fax number, including codes, without any blanks or dashes.

Description.

Enter a description for the fax number. This is particularly useful if the supplier has more than one.



Select **F8=Update** to write the details to the Supplier Fax Numbers file.

Vendor Details



12/STPMM

Use this option to create and maintain details of your supplier's route and freight arrangements. This information is displayed on the Purchase Order Header.

Maintain Vendor Details Screen 1

 Select Vendor Details.

Use this screen to select the vendor and address location code that these freight and route arrangements apply to.

AP620 ST - JBA System Test Company User GBJBARW2 11/12/96
13:44:02

Maintain Vendor Details

Vendor...?... _____ _____

F3=Exit F4=Prompt

05-15  MW KS IM II KENB20A PET178S2

Fields:

Vendor

Enter a new vendor code and address location code combination to create new route and freight details.

Select an existing vendor and address location code combination to maintain existing route and freight details.

 Press **Enter** to display the second Maintain Vendor Details screen.

Maintain Vendor Details Screen 2



To display this screen press **Enter** on the first Maintain Vendor Details screen.

Use this screen to add or maintain the details for the vendor selected on the initial screen.

AP620	ST - JBA System Test Company	User GBJBARW2	11/12/96 13:47:51
Maintain Vendor Details			
Vendor.....	ZBP_AP01	Bernard Procter's Supplier.....>	jkgfghgd
Routing code...?..	<u>A</u>	Routing Code A	
Freight terms...?..	<u>A</u>	Freight Code A	
F3=Exit F4=Prompt F8=Update F12=Previous			
10-21	<u>SF</u>	MW	KS IM II KENB20A PET178S2

Fields:

Routing Code

Enter a routing code for the selected vendor. These must have been set up within Descriptions under Major Type ROUC.

Freight Terms

Enter freight terms for the selected vendor. These must have been set up within Descriptions under Major Type FRGT.



Select **F8=Update** to update the details entered.

Application Maintenance File Prints

You can also produce a listing of various options within File Lists in Maintenance.

- Parameters and Sundry Codes

1... **21/STPMM**
2...

- Item Specifications

1... **22/STPMM**
2...

- Purchase Officer Names

1... **23/STPMM**
2...

- Receiving Addresses

1... **24/STPMM**
2...

- Delivery Instructions

1... **25/STPMM**
2...

- Container details

1... **26/STPMM**
2...

- User Authority

1... **27/STPMM**
2...

When you select each option you can submit a batch job to the system. These prints consist of a listing of the current records in each file and are particularly useful during the set up of the system to check that all the correct entries have been made. See the information on Reports for further details.