

-
-
-
-
-

Chapter 4

Explorer System Configuration



What Is System Configuration?



Warning: System Configuration is intended for the System Administrator only.

System Configuration enables the System Administrator to give permissions to the person using Explorer by enabling or disabling various facilities for them. For example: If you check the Save As field in the System Configuration Menu Window then the next time Explorer is opened the Save As option on the File Menu on the Main Menu Bar is enabled.



Note: The System Configuration Menu Bar is displayed with the System Configuration Menu Window.



Note: You can access the System Configuration Menu by using the System Configuration button on the Preferences Window. If this button is also disabled then contact your System Administrator who may want to reset permissions for you.

If you install JBA's Administration Tools product then System Configuration is displayed as an option on your Program Menu as well as Explorer.

System Configuration Menu Bar

The System Configuration Menu Bar has two drop-down menu options:

- File Menu
- Help Menu.

File Menu

Menu options:

Open INI File

Opens a new .INI file.



Tip: You don't have to do this because the System Configuration will use by default the last .INI file you saved.

Save INI File

Saves the .INI file.



Tip: After doing this you need to restart Explorer so that it recognises your new settings.

Save As

Save the .INI file with a new name.



Tip: After doing this you need to restart Explorer so that it recognises your new settings.



Note: Below this is a list of the recently accessed Ini files.

Exit

Close System Configuration without saving any changes.

Help Menu

Menu options:

System Configuration Help

Displays the online help to assist you in configuring System 21 Explorer.

About


Displays System 21 version information.

System Configuration Windows

The following sections give you detailed information about each individual window within System Configuration.

System Configuration Menu Authorisation Window

-  To display this window, select the System Configuration button on the Preferences Window and then select the Menu Authorisation panel.



You can give permissions to the person using Explorer by enabling or disabling various facilities for them. For example: If you check the Save As field in the System Configuration Menu Window then the next time Explorer is opened the Save As option on the File Menu on the Main Menu Bar is enabled.

 **Warning:** *If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.*

Fields:

Main

This group box displays fields relating to some of the options on the File Menu on the Main Menu Bar.

 **Note:** *The options Open, Action Keys and Exit on the File Menu are always enabled and so you do not see them on this System Configuration Window. Explorer Activity Manager is always*

enabled when there is an activity running.

New

Check this to enable the New option.

Save

Check this to enable the Save option.

Save As

Check this to enable the Save As option.

Server Session

Check this to enable the Server Session option.



Note: This option displays the Server Session Window so you can sign on to a host session.

Format

Check this to enable the Format option.



Note: This option displays the Keyboard Id Window.

Work With Submitted Jobs

Check this to enable the Work With Submitted Jobs option.



Note: This option displays a list of the jobs that you have submitted for processing on the server.

Work With Server Prints

Check this to enable the Work With Server Prints option.



Note: This option displays a list of reports that you have submitted for printing on the server, and you can also use the displayed screen to control the print queue.

Work With Messages

Check this to enable the Work With Messages option.



Note: This option displays a window listing messages that have been sent to you. You can reply, but cannot enter new messages.

Options Menu

This group box displays fields relating to some of the options on the Options Menu on the Main Menu Bar.

Role Code

Check this box to enable the Role Codes option on the Options menu.



Note: This option enables you to define role codes for existing role menus using the Role Codes Window.

Create Context Menu

This group box displays fields relating to the options on the Role Activity Space Area Pop Up menu: Folder; Activity and Program. By checking the boxes in the System Configuration Menu Window you can enable the options on the Pop Up menu.



Tip: This context sensitive pop up menu is available when you click with the right mouse button on any space in the Role Activity Area of Explorer.

Activity Context Menu

This group box displays fields relating to some of the options on the Role Activity Area Pop Up menu: Delete and Properties. By checking the boxes in the System Configuration Menu Window you can enable the options on the pop up menu.



Tip: This context sensitive pop up menu is available when you click with the right mouse button on any activity in the Role Activity Area of Explorer.

Action List Context Menu

This group box displays fields relating to the option Override on the Action List Pop Up Menu. Check this box to enable the Override option on the pop up menu.

Buttons:

There are no buttons on this window.




Warning: If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.

System Configuration Preference Authorisation Window



To display this window, select the System Configuration button on the Preferences Window. Then select the Preference Authorisation panel.



You can give permissions to the person using Explorer by enabling or disabling various facilities for them. For example: If you check the Launch On Role Menu Change field then the next time Explorer is opened the Launch On Role Menu Change option on the Preferences Window is enabled and can then be checked or unchecked.



Warning: *If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.*

Fields:

Options

This group box displays fields relating to some of the fields on the Options panel of the Preferences Window.

Run QARun

For JBA internal use only.

Use InfoBase Help Files

Check this to enable the Use InfoBase Help Files field on the Preferences Window.



Note: This field enables you to use the InfoBase Help Text.

Launch on Role Menu Change

Check this to enable the Launch on Role Menu Change field on the Preferences Window.



Note: This field enables you to create a new copy of JBA System 21 Explorer each time that you change your role.

Refresh Action List

Check this to enable the Refresh Action List field on the Preferences Window.



Note: This field enables you to select a number of minutes in order to instruct Explorer to update the Action list.



Note: When a user executes an activity in a Action list then the list is automatically updated and this happens whether this field on the Preferences Window is checked or not. Please refer to the Action List button on the Explorer Toolbar.

Screen

This group box displays fields relating to some of the fields on the Screen panel of the Preferences Window.

Use Bold Font

Check this to enable the Use Bold Font field on the Preferences Window.



Note: This field enables you to set text to Arial Monospaced Bold. The default is Normal.

Function Key Text Only

Check this to enable the Function Key Text Only field on the Preferences Window.



Note: This field enables you to hide or display the function key numbers.

Designer

Check this to enable the Designer field on the Preferences Window. This enables the System Administrator to tailor the System 21 window display for the Explorer user.



Note: This field enables you to enable the Designer facility.



Warning: Designer is intended for the System Administrator only.



Note: You can access Designer only if the Designer field, in the Preferences Window, has

been checked. If the Designer field in the Preferences Window is disabled then contact your System Administrator who may want to reset permissions for you.



Note: Only non Visual Component windows can be reformatted in Explorer.

The Designer button on the toolbar may not always be available to you. When you start an activity the Designer button is displayed on the toolbar provided that:

- The window is not a Visual Component.
- The Designer field, in the Preferences Window, has been checked.
- There is only one active session. If you start a second session the Designer button becomes automatically disabled.
- The host screen contains a magic number.

Recognition And Reformatting

Check this to enable the Recognition & Reformatting field on the Preferences Window.



Note: This field enables you to either: display screens edited using System 21 Designer or use System 21 defaults to display data from the server without any Designer changes.

System Wide Settings

Check this to enable the System Wide Settings group box on the Preferences Screen Window.

System Configuration



Warning: Please check with your System Administrator before making changes to this setting.

Enabled

Check this to enable the System Configuration button on the Preferences Window.



Warning: This means that you can lock yourself out of System Configuration! You may want to do this for safety reasons, but this means that you then have to run System Configuration as a stand alone program or manually update the .INI file.

Buttons:


There are no buttons on this window.



Warning: If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.

System Configuration Servers Window

 To display this window select the System Configuration button on the Preferences Window and then select the Servers panel.



This window displays a list of servers and protocols previously set up and several group boxes, Connection Type, User Default, Environment, Password Default and Company, which you use to define the default connection information for each server.

 **Warning:** If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.

This is what you do:

Add to the list

Click the Add button, enter a server name in the displayed window and click the OK button. You can then enter the details for the server. Click the Update button to save the information and add the server to the displayed list.

Delete from the list

Select an item in the list view and then click the Delete button.

Edit an item in the list

Select an item from the list view, click the Edit button. The details are displayed in the group boxes and the Edit button then changes to Update. Make any changes to the information then click the Update button.

Fields:

Connection Type

Server

Enter the server name.

Protocol

Select the protocol for the server.

Use DNS

Choose this option if you use a DNS to locate your server.

Use IP Address

Choose this option and enter an IP address in the box to use an IP address to locate your server.

User Default

Choose which user to use to access this server. You can choose a specific user or use the user logged on to System 21 Explorer or Windows.

Environment

Choose whether to use the server's default environment or a specified environment.

Password Default


Enter, and confirm, the password to use as default for this server.

Company

Choose whether to use the default company for the specified user or a specific company.

System Configuration Toolbar Window

 To display this window select the System Configuration button on the Preferences Window and then select the Toolbar panel.



You can add your own buttons to the toolbar. You can set up an ActiveX project or an .EXE program to link to it.

 **Warning:** *If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.*

There is a list view, called User Added Buttons, which displays the details of any buttons you add. The order of the list items reflects the position of the new buttons on the Explorer toolbar. The Move arrows enable you to move any item up and down the list. The buttons at the bottom of the window enable you to maintain the list. You have to select an item in the list in order to enable all of the buttons. This is what you do:

Add to the list

Click the Add button to display the Toolbar Button Details Window. When you complete the details on this window the details for the new button are displayed in the list view.

Add a space separator in front of a button on the toolbar

Position the cursor in the list view to indicate where to put the space. Click the Add Separator button.

Delete from the list


Select an item in the list view and then click the Delete button.

Edit an item in the list

Select an item from the list view, click the Edit button and note that the details are displayed in the Toolbar Button Details Window. When you complete the details on this window the new details are displayed in the list view.

System Configuration Settings Window

 To display this window select the System Configuration button on the Preferences Window and then select the Settings panel.



You can configure the Role Menu and Work Management settings.

 **Warning:** If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.

Work Management

Enable Action List Toolbar Button

Check this box to enable the Action List button on the toolbar. 

Enable Action Tracker Toolbar Button

Check this box to enable the Action Tracker button on the toolbar. 

Prompt For Role Code On Menu Creation

Check this box to cause Explorer to prompt you to enter a role code whenever you create a new role menu using the options File / New and File / SaveAs on the main menu bar.

Emulator Options

Manual Window Configuration

Check this box to enable the Window Recognition Utility. This utility is installed as part of Administration Tools.

Maximum Number Of Sessions

Change the maximum number of sessions allowed at any one time, up to a maximum of 17.

Role Menus

Role Menu Designer

Check this to enable the Role Menu Designer button on the toolbar. 

Enable 'All Role Menus' User(*)

There is a user set up which has access to all the existing role menus. The name of this user is * (asterisk). Check this box to enable this user.

Enable 'Change Explorer User' Toolbar Button

Check this to enable the Change Explorer User button on the toolbar. 

Set Explorer User To Windows User

Check this to set the System 21 Explorer user to the user logged on to Windows.

Currency Conversion

Enable Currency Conversion

Check this to enable the Currency Conversion button on the toolbar. 

Currency Database Location

Enter the location of the currency database (JBAEMU.MDB).

Application Server Settings

Enable 'Always Prompt For Application Server Settings' Toolbar Button

Check this to enable the Always Prompt For Application Server Settings button on the toolbar.




Allow User To Change

Specify whether the user can change the user, server, company or environment when logging on to a server by checking the appropriate box.

System Configuration Document Viewer Window

-  To display this window select the System Configuration button on the Preferences Window and then select the Document Viewer panel.



You can configure the Document Viewer settings.

 Tip: Please refer to the Document Viewer section of this online Help.

 **Warning: If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.**

Authority

Enable Explorer Document Viewer Toolbar Button

Check the box to directly enable this button. 

Enable Access To Explorer Preferences Document Viewer Tab

Check the box to enable the tab access to Document Viewer on the Preferences Window.

Document Index

Choose between access locally on your PC (default) or ODBC.

The database name is displayed for you. You set this in the Document Viewer Database field on the System Configuration File Paths Window.

For ODBC access only you then enter the User Data Source Name. This should match one of the data source names set up on your machine. To check this look at your Windows Control Panel and select the ODBC icon.

Locations

Support Files

This is a directory containing all the bitmaps used by Document Viewer. The default location is:

C:\Program Files\JBASys21\DVRes.

Technical Reference

This is the Technical Reference program. The default location is:

C:\Program Files\JBASys21\TechnicalReference.exe.

Document Viewer Options

Allow Access To Register Files

Enables access to the File\Register menu option from the Document Viewer menu bar.

Allow Access To Editing Document Types

Enables access to the Edit\Document Types menu option from the Document Viewer menu bar.

Shows Links To Technical Documentation

Note that when you right click on an Elemental Activity in Explorer, or Constructor, you can select the Documentation option and launch the Document Viewer. Document Viewer then makes an automatic link to the Technical Reference facility. This makes available the details for the activity. The Document Viewer index has a Document Category of ConstructorACT and Document Key matches the Task Code for the activity.

If you keep this box checked then this link from the Document Viewer to the Technical Reference is displayed in the Document Viewer Window. Document Viewer displays the link to Technical Reference as a single document and displays it with a filing cabinet symbol.



The example below shows what you would see in the Document Viewer where OE032220 is a Task Code.

Example:


Document	Size	Modified	Viewer
 OE032220			C:\PROGRAM FILES\JBASYS21\TechnicalReference.exe

In this case the Document Viewer index would consist of:

- Document Category - ConstructorACT
- Document Key - OE032220.

System Configuration File Paths Window

-  To display this window select the System Configuration button on the Preferences Window and then select the File Paths panel.



Explorer can switch between different host application versions. Use this window to set up File Paths for each version. You select an application version and then edit the location of the Support Files relating to that version.

 **Warning:** Some application versions have been set up for you but you can change the names or any of the details or you can create new ones. However, JBA recommend that you do this with caution.

 **Warning:** If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.

Fields and buttons:

Application Version

Drop Down List

This is a list containing the names of all the versions of data installed on your machine.

For example if you select v352 it means that you want to use the databases, processes, activities, role menus and help files which accompany System 21 Explorer Version 3.5.2. All these files are found under:

c:\Program Files\JBASys21\v352\

New

Press this button to add a new version name to the list. The name must contain only alphanumeric characters. Use this if you have installed your own customised .RMU files.

Edit

Press this button to enable the remainder of the fields on this window.

Delete

Press this button to delete a version name from the list.

Location For Support Files

Role Menus

The path to the Explorer role menus (.RMU). For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Rmu

Run Time Database:

The path to the JBARTime.mdb database holding the run time details. This includes details for role users, reformatting and runtime components. For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Data

Design Time Database:

The path to the JBADTime.mdb database holding the design time activity details. For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Data

Visual Components

Path to the Visual Components database JBAVC.MDB. For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Data

Document Viewer Database

Path to the Jbadv.mdb database of documents used by Document Viewer. For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Data

Processes And Activity Lists

The path to the files containing Activities (.ACT files) and Business Processes (.BPR files). For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352

Support

The path to the support files. For example, the default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352

Help Files

The path to any Help (.HLP) files from which you want to make links, using Designer. For example, this might be the path to the InfoBase or Explorer help files. The default for version 3.5.2 would be:

c:\Program Files\JBASys21\v352\Help

Document Viewer Documents

Use this in order to set Alias Path Options for the Document Viewer.



Tip: Please read the section called Set An Alias Path Option in the Document Viewer part of this help.

When you register a document, using the Register A Document Window in Document Viewer, you have to specify a file pathway. If you have a number of documents this registration process can take some time. If you decide to move those documents at any time, for any reason, then you would have to delete those documents and then register them all over again, or manually edit the database.

However, if when registering you specify an alias pathway, this means that you can later move your documents. All you have to do then is to change the alias pathway. The path changes, to all the documents which have been registered with that alias, are then re-established with the new definition and you don't have to delete them and register them all over again.



Warning: You must complete this System Configuration field before you register any documents in Document Viewer. If you register documents and do not specify an alias path option you cannot go back later and add it on. You have to delete the document from Document Viewer and register it again or manually edit the database.

You type in here a list of alias names and pathways. You invent the alias name but the pathway must match, or partially match, the pathway specified in the File field on the Register A Document Window in the Document Viewer utility, where your documents are currently stored.

For example, if you have the following in the File field, on the Register A Document Window:

c:\Documents\Reports\demo.bmp

then you need to select an alias with a matching path like this:

demoalias=c:\Documents\Reports

or with a partially matching path like this:

demoalias=c:\Documents

You could type in a number of aliases; for example, type a list like this, without using any spaces and press Enter at the end of each line:

aliasr=c:\Documents\Reports

aliasf=c:\Documents\Forms


aliasm=c:\Documents\Memos

Select Save INI from the File Menu.

System Configuration Visual Components Window



To display this window select the System Configuration button on the Preferences Window and then select the Visual Components panel.



Warning: *If you want to download from a Web address you need Internet Explorer Version 3 or above installed on your machine.*

In order to make the most effective use of hard disk space Visual Components are demand loaded from the server onto the PC. You load them as you need them when running an application program. Visual Components can be separately installed on the PC. If a Visual Component cannot be found on the PC, because it has not been installed, you need to determine how you want the screen to be refreshed.

Use this window to state:

- Whether you want to use Visual Components in place of the Green-On-Black screens for JBA System 21 Applications.
- What you want to happen if a Visual Component cannot be found on the PC.

Show Visual Components

- Unchecked (off) - System 21 uses its defaults to display data from the server on Green-On-Black screens. The remaining fields are disabled.
- Checked (on) - System 21 hides the character based screen and displays a Visual Component instead, provided that one exists for the application window. You then use the remaining fields to determine what you want to happen if a Visual Component cannot be found on the PC:
 - No Automatic Component Refresh (Default)
This tells the system not to download the Visual Component from the server but to use the Green-On-Black character based screen instead.
 - Refresh Components From Network Server
This tells the system to download the Visual Component from the server. You enter the server directory where the Visual Components are located.
 - Refresh Components From Web Server
This tells the system to download the Visual Component from a Web address. You enter the address of the Web URL where the Visual Components are located. For this you need Internet Explorer Version 3 or above installed on your machine.

You can change the time-out limit for downloading Visual Components from the server to the PC. The default is 300 seconds. When the Visual Component is being downloaded the user will be asked, after the time-out period, if they want to abort the downloading process or continue to wait.



Warning: If you make any changes, you are automatically prompted to save your changes when you exit System Configuration.


Toolbar Button Details Window



To display this window select Add or Edit from the System Configuration Toolbar Window.

You can maintain details for a button which you have defined for the Explorer toolbar. There are three panels: Type; Action and Style.

Type



You can select Start An Object in order to launch an ActiveX project from the toolbar button.

You can select Start A Program in order to launch an .EXE program from the toolbar button.

Action



Note: Please refer to System 21 Technical Information for interface details.

This panel enables you to define the activation details.

Fields:

If you are starting an object then the Server and Class fields are enabled for you. If you are starting a program then only the Program field is enabled.

Program

The path and name of the program to be launched by your button.


Server

The server name for the object to be launched by your button.

Class

The class name for the object to be launched by your button.

Style



This panel enables you to set up the icon for your button.

Fields:

Icon

Browse to find an icon.

Tool Tip Text

The text you want to display when the cursor rests over the button on the toolbar.

Buttons:



Note: The buttons are the same for all three panels.

Cancel

Close the panel without saving the changes.

OK

Save the changes and close the panel.