

# ■ YouTube Video Script

Transform Your Audio to PRO Level

■ Tech Channel

■ Hinglish

■ 10–12 Min

■ Viral Format

■ HOOK

■ PROBLEM

■ VALUE

■ STORY

■ SOLUTION

■ BONUS

■ CTA

## ■ HOOK

0:00 – 0:30

■ Camera on face — intense expression

content chahe kitna bhi achha ho, agar  
audio kharab hai... to log video ko dekhna band kar hi dete hain

Aaj main tumhe dikhaunga — bilkul FREE tools se, apni raw audio ko PRO level pe kaise le jaaye. Aur  
haan — ye tricks wahi hain jo MrBeast ke audio engineers use karte hain. Toh bana rahe —  
kyunki ye video tumhare channel ki life badal sakti hai! n

## ■ PROBLEM SETUP

0:30 – 1:30

■ Screen recording — show a bad audio waveform

Dekh bhai, jab hum record karte hain — 3 cheezein hoti hain jo audio barbad karti hain:

■ Background Noise (fan, traffic, AC)

■ Echo / Reverb (kamre ki walls se)

■ Low Volume / Muddy Sound

Agar tumare audio mein ye teen problems hain — toh chill karo, aaj sab fix ho jaayega.

## ■ TOOLS INTRODUCE KARO

1:30 – 2:30

"Toh kaun se tools use karein?" — Bhai, sirf 2 tools kaafi hain:

| Tool                    | Price | Use            |
|-------------------------|-------|----------------|
| Adobe Podcast (Enhance) | FREE  | AI-powered fix |
| Audacity                | FREE  | Basic cleanup  |

Dono ka link description mein hai — abhi download kar, baad mein seekhna.

■■ STEP BY STEP PROCESS2:30 – 7:00

■ STEP 1 — Adobe Podcast AI Enhance | 2:30 – 4:00

■ Screen recording

"Yaar ye cheez toh jaadu hai seedha!"

1. Adobe.com/podcast pe ja
2. 'Enhance Speech' click kar
3. Apni raw audio file upload kar
4. 30 second mein — studio quality audio ready! ■

■ BEFORE

■ AFTER

"Bhai seriously — ye FREE hai aur ye kaam karta hai jaise Rs. 50,000 ka mic laga ho!"

■ STEP 2 — Audacity Manual Clean | 4:00 – 6:00

Agar aur control chahiye — toh Audacity mein ye 3 cheezein karo:

- ① Noise Reduction: Effect → Noise Reduction → Get Noise Profile → Apply (Pehle background ka 2 sec sample select kar, phir poori audio pe apply kar)
- ② EQ: Effect → Filter Curve EQ Bass (below 80Hz) cut karo | Mid (1kHz–5kHz) boost karo — voice clear hogi
- ③ Compression: Effect → Compressor Threshold: -18dB | Ratio: 3:1 — volume consistent rehta hai

■ STEP 3 — Final Polish | 6:00 – 7:00

"Ek last step jo 90% creators skip karte hain!"

Loudness Normalization: Effect → Loudness Normalization → Set -14 LUFS

-14 LUFS = YouTube ka standard! ■ Video audio distort nahi hogi.

## ■ BONUS TIPS

7:00 – 8:30

■ Tip 1 — Mic ko seedha munh ke saamne mat rakh — thoda side pe rakh → Pop sounds kam honge

■ Tip 2 — Kapdon ke andar record kar ya wardrobe ke paas — best DIY soundproofing

■ Tip 3 — Phone ka mic + RODE app + Adobe Enhance = Cinematic audio!

■ Tip 4 — Recording se pehle 5 second chup reh — noise profile ke liye

## ■ BEFORE / AFTER MOMENT

8:30 – 9:00

■ BEFORE Same Mic | Same Room | Kharab Audio

■ AFTER Same Mic | Same Room | PRO Audio!

"Yaar — same mic, same room, same voice... but PRO level audio. Bas settings ka fark hai."

## ■ CALL TO ACTION

9:00 – 9:30

■ Face cam — energetic

LIKE maar abhi — seriously ek second ka kaam hai

■ SUBSCRIBE kar — agli video mein: Video Quality ko PRO kaise banao

■ Comment mein likh "AUDIO FIXED" — toh main jaanunga tune poori video dekhi!

■ Description mein dono FREE tools ke links hain — use kar!

Milte hain agli video mein. Peace! 🙌■

## ■ OUTRO

9:30 – 10:00

End screen dikhao — 2 recommended videos ke cards "Ye bhi dekh ■"

## ■ Script Quick Stats

| Element | Detail |
|---------|--------|
|---------|--------|