
HEADS UP - Add Logging Messages in Spring 5.1

The Problem

In Spring 5.1, the Spring Development team changed the logging levels internally. As a result, by default you will no longer see the red logging messages at the INFO level. This is different than in the videos.



The Solution

If you would like to configure your app to show similar logging messages as in the video, you can make the following updates listed below. Note, you will not see the EXACT same messages, since the Spring team periodically changes the text of the internal logging messages. However, this should give you some additional logging data.

```
cterminated> HelloSpringApp [Java Application]
Oct 13, 2018 7:26:59 AM org.springframework.bear
FINE: Creating shared instance of singleton bear
Oct 13, 2018 7:26:59 AM org.springframework.bear
FINE: Creating shared instance of singleton bear
Run a hard 5k
Just Do It: Today is your lucky day!
Oct 13, 2018 7:26:59 AM org.springframework.cont
FINE: Closing org.springframework.cont
```

Overview of the steps

- 1. Create a bean to configure the parent logger and console handler
- Configure the bean in the Spring XML config file

Detailed Steps

1. Create a bean to configure the parent logger and console handler

This class will set the parent logger level for the application context. It will also set the logging level for console handler. It sets the logger level to FINE. For more detailed logging info, you can set the logging level to level to FINEST. You can read more about the logging levels at http://www.vogella.com/tutorials/Logging/article.html

This class also has an init method to handle the actual configuration. The init method is executed after the bean has been created and dependencies injected.

File: MyLoggerConfig.java

```
    package com.luv2code.springdemo;
    import java.util.logging.ConsoleHandler;
    import java.util.logging.Level;
    import java.util.logging.Logger;
```

```
import java.util.logging.SimpleFormatter;
7.
8. import org.springframework.context.annotation.AnnotationConfigApplicationContext;
10. public class MyLoggerConfig {
11.
12.
             private String rootLoggerLevel;
             private String printedLoggerLevel;
13.
14.
15.
             public void setRootLoggerLevel(String rootLoggerLevel) {
16.
                      this.rootLoggerLevel = rootLoggerLevel;
17.
             }
18.
19.
             public void setPrintedLoggerLevel(String printedLoggerLevel) {
20.
                      this.printedLoggerLevel = printedLoggerLevel;
21.
22.
             public void initLogger() {
23.
24.
25.
26.
                      Level rootLevel = Level.parse(rootLoggerLevel);
                      Level printedLevel = Level.parse(printedLoggerLevel);
27.
29.
                      // get logger for app context
                      Logger applicationContextLogger = Logger.getLogger(AnnotationConfigA
   pplicationContext.class.getName());
31.
32.
                      // get parent logger
33.
                      Logger loggerParent = applicationContextLogger.getParent();
35.
                      // set root logging level
36.
                      loggerParent.setLevel(rootLevel);
37.
                      // set up console handler
38.
                      ConsoleHandler consoleHandler = new ConsoleHandler();
                      consoleHandler.setLevel(printedLevel);
                      consoleHandler.setFormatter(new SimpleFormatter());
                      // add handler to the logger
43.
                      loggerParent.addHandler(consoleHandler);
44.
45.
             }
46.
47. }
```

2. Configure the bean in the Spring XML config file

In your XML config file, add the following bean entry. Make sure to *list this as the first bean* so that it is initialized first. Since the bean is initialized first, then you will get all of the logging traffic. If you move it later in the config file after the other beans, then you will miss out on some of the initial logging messages.

File: applicationContext.xml (snippet)

Adding Spring Security to CRM REST API

Source code is available here.

Once you make these updates, then you will be able to see additional logging data. :-)