

```

/* =====
ATM CASH LOADING
===== */

CREATE OR ALTER PROCEDURE Load_ATM_Cash
(
    @ATMID                INT,
    @LoadedAmount          DECIMAL(18,2),
    @LoadedByEmployeeID    INT
)
AS
BEGIN
    SET NOCOUNT ON;

    BEGIN TRY
        BEGIN TRANSACTION;

        -- 1. Validate loading amount
        IF @LoadedAmount <= 0
        BEGIN
            THROW 50001, 'Loaded amount must be greater than zero.', 1;
        END;

        -- 2. Validate employee
        IF NOT EXISTS
        (
            SELECT 1
            FROM Employees
            WHERE EmployeeID = @LoadedByEmployeeID
                  AND Status = 'Active'
        )
        BEGIN
            THROW 50002, 'Employee does not exist or is not active.', 1;
        END;

        -- 3. Validate ATM
        IF NOT EXISTS
        (
            SELECT 1
            FROM ATM
            WHERE ATMID = @ATMID
                  AND Status = 'Active'
        )
        BEGIN
            THROW 50003, 'ATM does not exist or is not active.', 1;
        END;

        -- 8. Commit everything
        COMMIT TRANSACTION;

        -- 9. Return result
        SELECT
            @ATMID AS ATMID,
            @CurrentCashBalance AS OpeningATMBalance,
            @LoadedAmount AS LoadedAmount,
            @CurrentCashBalance + @LoadedAmount AS ClosingATMBalance,
            @LoadedByEmployeeID AS LoadedByEmployeeID,
            'ATM cash loaded successfully.' AS Message;
    END TRY
    BEGIN CATCH
        -- Roll back if any error occurs
        IF @@TRANCOUNT > 0
            ROLLBACK TRANSACTION;

        THROW;
    END CATCH;
END;
GO

```

```

DECLARE @CurrentCashBalance DECIMAL(18,2);
DECLARE @CashCapacity       DECIMAL(18,2);

-- 4. Get current ATM balance and capacity
SELECT
    @CurrentCashBalance = CashBalance,
    @CashCapacity = CashCapacity
FROM ATM
WHERE ATMID = @ATMID;

-- 5. Check ATM cash capacity
IF @CurrentCashBalance + @LoadedAmount > @CashCapacity
BEGIN
    THROW 50004, 'ATM cash capacity exceeded.', 1;
END;

-- 6. Update ATM cash balance
UPDATE ATM
SET
    CashBalance = CashBalance + @LoadedAmount,
    LastCashLoadDate = SYSDATETIME()
WHERE ATMID = @ATMID;

-- 7. Record ATM cash loading
INSERT INTO ATMCashLoading
(
    ATMID,
    LoadedAmount,
    LoadedByEmployeeID,
    LoadDate,
    Remarks
)
VALUES
(
    @ATMID,
    @LoadedAmount,
    @LoadedByEmployeeID,
    SYSDATETIME(),
    'Cash loaded into ATM'
);

END TRY
BEGIN CATCH

    -- Roll back if any error occurs
    IF @@TRANCOUNT > 0
        ROLLBACK TRANSACTION;

    THROW;
END CATCH;

END;
GO

```

```
-- View all ATM cash loading transactions
SELECT * FROM ATMCashLoading;

-- View ATM details for specific ATMs
SELECT * FROM ATM
WHERE ATMID IN (11, 15);
```

150 %

Results Messages

CashLoadID	ATMID	LoadedAmount	LoadedByEmployeeID	LoadDate	Remarks
------------	-------	--------------	--------------------	----------	---------

	ATMID	BranchID	ATMCode	ATMType	Location	CashBalance	CashCapacity	LastCashLoadDate	Status
1	11	8	ATM082	OnSite	DEL002 Branch Premises	840375.61	2000000.00	2026-08-12 23:18:48.1268026	Active
2	15	12	ATM121	OnSite	CHN002 Branch Premises	1530247.87	2000000.00	2026-08-12 23:19:16.5403975	Active

Query executed successfully.

SATYAM\SQLEXPRESS (16.0 RTM) SATYAM\ABHI (73) BankingSystem 00:00:00 2 rows

---Example : Load cash into ATM 11

EXEC Load_ATM_Cash

```
@ATMID = 11,
@LoadedAmount = 100000,
@LoadedByEmployeeID = 10;
```

---Example : Load cash into ATM 11

EXEC Load_ATM_Cash

```
@ATMID = 15,
@LoadedAmount = 200000,
@LoadedByEmployeeID = 30;
```

---Example : View ATM cash loading record and updated ATM balance

SELECT * FROM ATMCashLoading

select * from ATM

120 %

Results Messages

1	ATMID	OpeningATMBalance	LoadedAmount	ClosingATMBalance	LoadedByEmployeeID	Message			
1	11	840375.61	100000.00	940375.61	10	ATM cash loaded successfully.			
1	ATMID	OpeningATMBalance	LoadedAmount	ClosingATMBalance	LoadedByEmployeeID	Message			
1	15	1530247.87	200000.00	1730247.87	30	ATM cash loaded successfully.			
	CashLoadID	ATMID	LoadedAmount	LoadedByEmployeeID	LoadDate	Remarks			
1	7	11	100000.00	10	2026-08-14 20:22:23.2537647	Cash loaded into ATM			
2	8	15	200000.00	30	2026-08-14 20:22:23.2547631	Cash loaded into ATM			
	ATMID	BranchID	ATMCode	ATMType	Location	CashBalance	CashCapacity	LastCashLoadDate	Status
7	9	7	ATM071	OnSite	DEL001 Branch Premises	774058.81	2000000.00	2026-07-17 00:00:00.0000000	Active
8	10	8	ATM081	OnSite	DEL002 Branch Premises	479543.67	2000000.00	2026-08-02 00:00:00.0000000	Active
9	11	8	ATM082	OnSite	DEL002 Branch Premises	940375.61	2000000.00	2026-08-14 20:22:23.2537647	Active
10	12	9	ATM091	OnSite	BLR001 Branch Premises	1099170.32	2000000.00	2026-08-01 00:00:00.0000000	Active
11	13	10	ATM101	OffSite	BLR002 Railway Station	1430998.24	2000000.00	2026-08-05 00:00:00.0000000	Active
12	14	11	ATM111	OnSite	CHN001 Branch Premises	1565453.04	2000000.00	2026-08-02 00:00:00.0000000	Active
13	15	12	ATM121	OnSite	CHN002 Branch Premises	1730247.87	2000000.00	2026-08-14 20:22:23.2547631	Active
14	16	12	ATM122	OnSite	CHN002 Branch Premises	1759455.61	2000000.00	2026-07-07 00:00:00.0000000	Active
15	17	13	ATM131	OnSite	PUN001 Branch Premises	1011689.16	2000000.00	2026-07-11 00:00:00.0000000	Active
16	18	14	ATM141	OnSite	KOL001 Branch Premises	1657577.23	2000000.00	2026-07-11 00:00:00.0000000	Active

Query executed successfully.

SATYAM\SQLEXPRESS (16.0 RTM) | SATYAM\ABHI (73) | BankingSystem | 00:00:01 | 24 rows