

ComponentSpace
SAML for ASP.NET
Step by Step Guide
Service Provider

ComponentSpace SAML for ASP.NET Step by Step Guide - Service Provider

Contents

Introduction	1
Creating a Certificate	1
Creating the Local Service Provider Configuration	1
Exporting the Local Service Provider Metadata	1
Importing the Partner Identity Provider Metadata	2
Updating the Application Code	2
Testing SAML SSO	2

Introduction

This document walks you through the recommended steps for enabling your web application to act as a service provider and support SSO with partner identity providers.

More detailed information about the SAML API, SAML configuration and related topics is available in the various documents listed in the Quick Start Guide.

Creating a Certificate

An X.509 certificate and associated private key are required if SAML messages sent by your service provider are to be signed or SAML assertions are to be encrypted.

If you're supporting SP-initiated SSO or SLO, we recommend signing the associated SAML messages.

Use the CreateSelfSignedCert console application to create a self-signed certificate. For more information, refer to the Certificate Guide.

CreateSelfSignedCert.exe

Neither the private key file nor its password should be shared with third parties.

Copy these certificate files to a certificates folder under your application.

Creating the Local Service Provider Configuration

SAML configuration is used to specify the local service provider. The Configuration Guide describes the various alternatives for specifying SAML configuration. Here we will use the simplest approach which is to store the SAML configuration in a saml.config file in your application's root folder.

Use the CreateConfiguration console application to create a saml.config file. For more information, refer to the Configuration Guide.

CreateConfiguration.exe

Copy the generated saml.config file to your application's root folder.

Exporting the Local Service Provider Metadata

SAML metadata is the standard format for exchanging configuration information between SAML providers. SAML metadata is supplied to partner providers so they can update their internal configuration to support SSO.

Use the ExportMetadata console application to generate the SAML metadata. For more information, refer to the SAML Metadata Guide.

ExportMetadata.exe

Share the SAML metadata with your partner provider(s). You could make the metadata available for download from a URL or supply it in an email etc.

Importing the Partner Identity Provider Metadata

SAML metadata supplied by partner providers is used to update your SAML configuration.

Use the ImportMetadata console application to update the SAML configuration. For more information, refer to the SAML Metadata Guide.

ImportMetadata.exe

Updating the Application Code

The Developer Guide describes the various SAML APIs to support SSO and SLO flows when acting as the service provider.

The Examples Guide walks through the SAML specific code in the example service provider.

Use these guides to enable SAML SSO in your application.

Testing SAML SSO

Before testing, ensure the following have been completed:

- 1. The saml.config has been created and is located in your application's root folder.
- 2. The local and partner certificate files are located in your application's certificates folder.
- 3. Your application has been updated to call the SAML API.
- 4. The partner provider has imported your SAML metadata and is ready.