F	^F	3.	75	LAB	1
\		. )	<i>.</i> . )	IΑD	4

Writing Assembly Code

Lab Time: Thursday 1000-1200

Eric Prather

# **PRELAB QUESTIONS**

1. The stack pointer is a register that stores a memory address pointing to the location on a first-in first-out (FIFO) region of memory called the "stack". It can be used to keep track of a call stack or for data-although in this lab, its main purpose should be as an augment to the program counter (PC). It is initialized in the SPI\_INIT: section of our AVR code to the manual-prescribed memory address (see manual page 13).

#### Pseudocode:

```
Initialization Region:
   R16 = High byte of RAMEND // const
   Stack Pointer 1 = R16
   R16 = low byte of RAMEND // const
   Stack Pointer high = r16
   //Cannot combine instructions
```

2. The AVR instruction LPM is short for "Load Program Memory". It loads the value pointed to by Z to the specified register. It is different from the regular load command, which loads from data memory, not program memory. Program memory is organized in 2B words. Here is some pseudocode to demonstrate its operation:

#### Pseudocode:

```
r17:16 = loadProgramMemory(Z) // r17:16 = programMemory[Z]
```

3. This assembly definition file provides a series of useful macros, similar to the atmel c headers (Discussed in Prather\_Eric\_Lab2\_Report.pdf). For example, the I/O pins are all given names and values here via .equ commands. Some other important features, such as the special registers and special data pointers, are also defined here. This question requires examples of definitions to be provided, so here is a screenshot:

```
; DDRA - Port A Data Direction Register
                        ; Data Direction Register, Port A, bit 0
.equ
        DDA0
                = 0
        DDA1
                = 1
                        ; Data Direction Register, Port A, bit 1
.equ
.equ
        DDA2
                = 2
                        ; Data Direction Register, Port A, bit 2
                        ; Data Direction Register, Port A, bit 3
.equ
        DDA3
                = 3
        DDA4
                = 4
                        ; Data Direction Register, Port A, bit 4
.equ
.equ
        DDA5
                = 5
                        ; Data Direction Register, Port A, bit 5
.equ
        DDA6
                = 6
                        ; Data Direction Register, Port A, bit 6
                        ; Data Direction Register, Port A, bit 7
.equ
        DDA7
                = 7
; PINA - Port A Input Pins
                        ; Input Pins, Port A bit 0
.equ
        PINA0
                = 0
        PINA1
                        ; Input Pins, Port A bit 1
.equ
                = 1
        PINA2
                        ; Input Pins, Port A bit 2
.equ
                        ; Input Pins, Port A bit 3
.equ
        PINA3
                = 3
                        ; Input Pins, Port A bit 4
.equ
        PINA4
                = 4
                        ; Input Pins, Port A bit 5
.equ
        PINA5
                = 5
                        ; Input Pins, Port A bit 6
.equ
        PINA6
                = 6
        PINA7
                = 7
                        ; Input Pins, Port A bit 7
.equ
```

**INTRODUCTION** 

This project is the first AVR programming task in this course. It requires foundational knowledge regarding AVR

instructions.

PROGRAM OVERVIEW

After running one-time initialization, an infinite loop executes that writes "strings" (i.e. bytes[]) to the LCD display. It involves a detailed discussion of memory access, which was not especially pertinent to prior labs. It also provides

a stack pointer for function alls.

INIT

The initialization routine provides a one-time initialization of key registers that allow the BumpBot program to

execute correctly. First the Stack Pointer is initialized, allowing the proper use of function and subroutine calls. Port B was initialized to all outputs and will be used to direct the motors. Port D was initialized to inputs and will

receive the whisker input. Finally, the Move Forward command was sent to Port B to get the TekBot moving

forward.

MAIN

Performs three looping branching conditionals, augmented by the subroutines described later:

1. Button 0 pressed: Write "Hello world" to one line and "Eric Prather" to the other of the LCD

2. Button 1 pressed: Inverse of 0.

3. Button 3 pressed: Clear LCD

WRITE Z L

Transfers the program data at address Z to the memory at address Y. Uses X as an intermediary data buffer.

 $READ_D$ 

Rudimentary "read" function for IO pins which was stripped down following a more efficient bitmask

representation being discovered.

LCDDriver.asm

The LCDDriver.ASM file contains several subroutines which have already been written and provided as part of lab

4. As such, it is not described in great detail here. Documentation for each question is provided individually. It is

also available in this handy set of one-line references in the lab4 pdf:

Page 3

- LCDInit Initialize the LCD (call once from within INIT)
- LCDWrite Update all characters of both lines
- LCDWrLn1 Update all characters of line 1 only
- LCDWrLn2 Update all characters of line 2 only
- LCDClr Clear (write "space" to) all characters of both lines
- LCDClrLn1 Clear all characters of line 1 only
- LCDClrLn2 Clear all characters of line 2 only
- LCDWriteByte Write directly to a single character of the LCD
- Bin2ASCII Convert an 8-bit unsigned value into an ASCII string

## **ADDITIONAL QUESTIONS**

1. In this lab, you were required to move data between two memory types: program memory and data memory. Explain the intended uses and key differences of these two memory types.

The ATMega128 has two different main types of memory available on the board with different intrinsic properties, plus a third persistent type that serves as a bootstrapper that can be flashed to by an external programmer. The program memory is organized into two-byte words and has several addresses of importance (such as 0000, the address the program counter begins at). Fetch instructions will usually relate to program memory. Address indexing in program memory is especially unique, as a special operation is required to get the "high" and "low" bytes of various parts of program memory. Usually, the contents of program memory are **processor instructions**. Data memory, on the other hand, has very few rules and is organized intuitively into one-byte chunks. Usually, the content of data memory is **defined and maintained by the program** according to the program instructions (hence data in data memory has no intrinsically assigned meaning). Data *can* be placed in program memory, such as for constant literal values- in fact, we do this with strings in our lab. However, data can only be written to program memory during runtime on "self-programmable" devices.

2. You also learned how to make function calls. Explain how making a function call works (including its connection to the stack), and explain why a RET instruction must be used to return from a function.

A function call simply stores the current instruction address on the stack and moves the program counter to point at a certain address. Then, the "ret" command restores the program counter back to its original position by "popping" this address from the stack. Often times, the values in the registers are also pushed and popped to the stack so that they can be unloaded/reloaded alongside the "subroutine", but this is not always the case. The system breaks down if the stack pointer is not pointing to the original address at the end of the subroutine, so that is the main thing to keep in mind when fiddling with this.

The specific function of the stack is described in the prelab. However, very briefly, it is a first-in first-out (FIFO) data structure with a special register pair associated with it (the "stack pointer"), generally growing from RAMEND downwards.

3. To help you understand why the stack pointer is important, comment out the stack pointer initialization at the beginning of your program, and then try running the program on your mega128 board and also in the simulator. What behavior do you observe when the stack pointer is never initialized? In detail, explain what happens (or no longer happens) and why it happens.

When the stack pointer is never initialized, its default value is undefined. In this specific hardware, all registers are set to 0 in order to prevent "frying" the board, so that means this will be the original address pointed to by the stack pointer as well. This means that the stack originally points to the **beginning of the program**, and because the stack grows **downwards**, the first time it is decremented the board will cause what is known as a "stack overflow error". The handling thereof varies by implementation, but the AVR128Mega board will either reboot or wrap to an inaccessible pointer (outside of the range of valid memory addresses, \$FFFF) and cause a cascading issue.

# **DIFFICULTIES**

- I accidentally included LCDDriver.asm at the beginning of my main file instead of at the end.
- I tried to use the port B lamp outputs for debugging purposes, but it turns out that a property of the LCD
  driver prohibited access to Port B. Spent some time with the TA troubleshooting this, but it took up all of
  my lab section and set me behind somewhat
- I couldn't quite figure out how to move from program memory to data memory right. I tried to use the debug utility to fix this to no avail. After spending a lot of time on this on my own, I ended up figuring out that if I just ignored the fact that program memory was organized into 16 bit words, it worked just fine. All of the bytes were contirguous anyway, as long as I bitshifted after my first assignment I could increment freely for some reason. Maybe that is an intrinsic part of the LPM command (it bitshifts right, increments, then bitshifts left if it sees Z+?). Actually, I bet that's the case.
- I was doing a really complicated thing with bit-shifting to try to apply a bit mask when it was much simpler to write andi 0b00000001 and cpi 0b00000001, for example.

## **CONCLUSION**

This lab introduced a variety of fundamental assembly programming language concepts which will be essential in future assignments. It also served to integrate many of the discussions of AVR principles from the lecture of the class with the lab. Understanding the architecture of the ATMega128 board was tremendously helpful in outlining which specific functionalities needed to be implemented in the code. For example, the requirement of the stack pointer initialization or of the interoperability of program and data memory would not have been intuitive with a higher-level programming background alone, where such items are handled by a compiler.

This lab was unique in that it was my first proper assembly program, so I had to put a wide variety of different skills all to the test at the same time.

### Source Code

```
Author: Eric Prather (prathere@oregonstate.edu)
; *
        (932580666)
        Date: January 27, 2020
.include "m128def.inc"
                            ; Include definition file
.include "mizsder.inc"; include de ;.include "LCDDriver.asm"; Include Driver
Internal Register Definitions and Constants
.def mpr = r16
                                  ; Multipurpose register is
                                              ; required for LCD Driver
.def mpr2 = r23
                                  ; I need one too!
.def loop_count = r24
.def
     init loop count = r25
;* Start of Code Segment
.cseg
                                         ; Beginning of code segment
;* Interrupt Vectors
.org $0000
                                  ; Beginning of IVs
          rjmp INIT
                                       ; Reset interrupt
.org $0046
                                   ; End of Interrupt Vectors
Program Initialization
; **********************************
INIT:
                                        ; The initialization routine
           ; Initialize Stack Pointer (Code from Lab 1)
           ldi
                       mpr, low(RAMEND)
                       SPL, mpr
           011
                                       ; Load SPL with low byte of RAMEND
                       mpr, high(RAMEND)
           ldi
                       SPH, mpr
                                       ; Load SPH with high byte of RAMEND
           out
           ; Initialize LCD Display;
           rcall LCDInit; In LCDDriver.asm
           ; Initialize Port D for input (Code from Lab 1)
           ; Unclear if this is handled by LCDInit as well,
           ; but I think it's best to be safe and double-check
           ; it all here.
           ldi
                       mpr, $00
                                        ; Set Port D Data Direction Register
                                        ; for input
           out
                       DDRD, mpr
           ldi
                       mpr, $FF
                                        ; Initialize Port D Data Register
                                        ; so all Port D inputs are Tri-State
                       PORTD, mpr
           out
           ; Move strings from Program Memory to Data Memory
           ; STRING NAME - STRING NAME END
           ; STRING_HW - STRING_HW END
            ; Haven't figured out how to do this yet.
           ; Do not use the LED outputs because they are reserved
           ; by the LED drivers.
           ; rjump MAIN
            ; NOTE that there is no RET or RJMP from INIT, this
           ; is because the next instruction executed is the
            ; first instruction of the main program
;* Main Program
; $0100 = line 1
; $0110 = line 2
; Y register points to data memory
```

```
; Z register points to program memory
             *********
MAIN:
                                                ; The Main program
             rcall LCDClr
             ldi init loop count, 6
MAIN LOOP:
             rcall READ_D ; Used to be more in this function but now it's pretty desolate
             andi mpr2, 0b00000001
              cpi mpr2, 0b00000001; only care abt one bit for conditional
             breq SKIP1
              ; Case 1: Pressed 0
             ldi YL, low($0100)
ldi YH, high($0100)
             ldi ZL, low(STRING_NAME << 1)</pre>
             ldi ZH, high(STRIN\overline{G} NAME << 1)
              rcall WRITE Z Y
             ldi YL, low(\$0110)
             ldi YH, high($0110)
             ldi ZL, low(STRING_HW << 1)
ldi ZH, high(STRING_HW << 1)</pre>
             rcall WRITE Z Y
             rcall LCDWrite
SKIP1:
             rcall READ_D
             andi mpr2, 0b00000010 cpi mpr2, 0b00000010
             breq SKIP2
              ; Case 1: Pressed 0
              ldi YL, low($0110); note this is swapped from case 1
             ldi YH, high($0110)
             ldi ZL, low(STRING_NAME << 1)</pre>
             ldi ZH, high(STRING NAME << 1)
              rcall WRITE Z Y
             ldi YL, low($0100); note this is swapped from case 1
             ldi YH, high($0100)
             ldi ZL, low(STRING_HW << 1)
ldi ZH, high(STRING_HW << 1)</pre>
             rcall WRITE Z Y
             rcall LCDWrite
SKIP2:
             rcall READ_D
             andi mpr2, 0b10000000 cpi mpr2, 0b10000000
             breq MAIN_LOOP
              ; Case 3: Pressed 7 (clear)
              rcall LCDClr
             rjmp MAIN LOOP
                                       ; jump back to main and create an infinite
                                                       ; while loop. Generally, every main
program is an
                                                        ; infinite while loop, never let the
main program
                                                        ; just run off
             rjmp
                    MAIN
;* Functions and Subroutines
;-----
; Func: WRITE Y Z
; Desc: Writes the contents of Y (in data memory) from Z
; (in program memory). Uses X as a buffer.
;-----
      mov loop_count, init_loop_count
LOOP WRITE Z Y:
      ; lpm r27, Z+ ; XL = r27
```

```
; lpm r26, Z+ ; XH = r26
       ;st Y+, r27
       ;st Y+, r26
       ;inc ZL
       ; IMPORTANT: Multiply ALL PROGRAM MEMORY ADRESSES BY TWO when assigning.
       ; Following four lines are ARGUMENTS: they are set by the caller
       ; before responsibility is passed to this function.
       ; ldi start_of_string_low addr ZL
; ldi start_of_string_high addr ZH
       ; ldi data memory target low YL
       ; ldi data_memory_target_high YH
      ; Following lines depend on Y and Z being initalized as above
       ; Read 2 byte from program memory, write 2 byte to data memory.
      lpm r26, Z+;
       lpm r27, Z+;
       st Y+, r26;
       st Y+, r27;
       ;inc ZL ; Point to next byte in program memory
       ;inc YL ; Point to next byte in data memory
       ; Loop until word is done.
       cpi loop_count, 0
       dec loop count
      brne LOOP WRITE Z Y
      ret
; Func: Read D
; Desc: Puts PIND values as required into mpr2
READ_D:
             in mpr2, PIND
              ; and i mpr2, (1 << 0 | 1 << 1 | 1 << 7); set all unused bits to 0?
; Func: Template function header
; Desc: Cut and paste this and fill in the info at the
          beginning of your functions
FUNC:
                                                ; Begin a function with a label
              ; Save variables by pushing them to the stack
              ; Execute the function here
              ; Restore variables by popping them from the stack,
              ; in reverse order
                                                        ; End a function with RET
;* Stored Program Data
; *********************************
; An example of storing a string. Note the labels before and
; after the .DB directive; these can help to access the data
;-----
STRING BEG:
              "My Test String"
.DB
                                         ; Declaring data in ProgMem
STRING END:
STRING NAME:
             "Eric Prather"
STRING NAME END:
STRING HW:
              "Hello World!"
.DB
```

WTRING_HW_END:					
,*************************************					
;* Additional Program Includes					
<b>,</b> ************************************					
.include "LCDDriver.asm"	; Include the LCD Driver				